

# globus gssapi error Reference Manual

## 2.5

Generated by Doxygen 1.4.4

Tue Aug 11 20:21:07 2009

# Contents

<a href="#">1 globus gssapi error Module Index</a>	<a href="#">1</a>
<a href="#">2 globus gssapi error Directory Hierarchy</a>	<a href="#">1</a>
<a href="#">3 globus gssapi error Module Documentation</a>	<a href="#">1</a>
<a href="#">4 globus gssapi error Directory Documentation</a>	<a href="#">6</a>

## 1 globus gssapi error Module Index

### 1.1 globus gssapi error Modules

Here is a list of all modules:

<b>Globus GSSAPI Error API</b>	<a href="#">1</a>
<b>Error Construction</b>	<a href="#">2</a>
<b>Error Data Accessors and Modifiers</b>	<a href="#">3</a>
<b>Error Handling Helpers</b>	<a href="#">4</a>

## 2 globus gssapi error Directory Hierarchy

### 2.1 globus gssapi error Directories


This directory hierarchy is sorted roughly, but not completely, alphabetically:

<b>library</b>	<a href="#">6</a>
----------------	-------------------

## 3 globus gssapi error Module Documentation

### 3.1 Globus GSSAPI Error API

Collaboration diagram for Globus GSSAPI Error API:



These globus\_error functions are motivated by the desire to provide a easier way of generating new error types, while at the same time preserving all features (e.g.

## Modules

- [Error Construction](#)
- [Error Data Accessors and Modifiers](#)
- [Error Handling Helpers](#)

### 3.1.1 Detailed Description

These globus\_error functions are motivated by the desire to provide a easier way of generating new error types, while at the same time preserving all features (e.g.

memory management, chaining) of the current error handling framework. The functions in this API are auxiliary to the function in the Globus Generic Error API in the sense that they provide a wrapper for representing GSSAPI errors in terms of a globus\_error\_t.

Any program that uses Globus GSSAPI Error functions must include "globus\_error\_gssapi.h".

## 3.2 Error Construction

Collaboration diagram for Error Construction:



Create and initialize a Globus GSSAPI Error object.

### Construct Error

- globus\_object\_t \* [globus\\_error\\_construct\\_gssapi\\_error](#) (globus\_module\_descriptor\_t \*base\_source, globus\_object\_t \*base\_cause, const OM\_uint32 major\_status, const OM\_uint32 minor\_status)

### Initialize Error

- globus\_object\_t \* [globus\\_error\\_initialize\\_gssapi\\_error](#) (globus\_object\_t \*error, globus\_module\_descriptor\_t \*base\_source, globus\_object\_t \*base\_cause, const OM\_uint32 major\_status, const OM\_uint32 minor\_status)

## Defines

- #define [GLOBUS\\_ERROR\\_TYPE\\_GSSAPI](#)

### 3.2.1 Detailed Description

Create and initialize a Globus GSSAPI Error object.

This section defines operations to create and initialize Globus GSSAPI Error objects.

### 3.2.2 Define Documentation

#### 3.2.2.1 #define GLOBUS\_ERROR\_TYPE\_GSSAPI

Error type definition.

### 3.2.3 Function Documentation

#### 3.2.3.1 `globus_object_t* globus_error_construct_gssapi_error (globus_module_descriptor_t * base_source, globus_object_t * base_cause, const OM_uint32 major_status, const OM_uint32 minor_status)`

Allocate and initialize an error of type GLOBUS\_ERROR\_TYPE\_GSSAPI.

##### Parameters:

- base\_source* Pointer to the originating module.
- base\_cause* The error object causing the error. If this is the original error, this parameter may be NULL.
- major\_status* The GSSAPI major status
- minor\_status* The GSSAPI minor status

##### Returns:

The resulting error object. It is the user's responsibility to eventually free this object using `globus_object_free()`. A `globus_result_t` may be obtained by calling `globus_error_put()` on this object.

#### 3.2.3.2 `globus_object_t* globus_error_initialize_gssapi_error (globus_object_t * error, globus_module_descriptor_t * base_source, globus_object_t * base_cause, const OM_uint32 major_status, const OM_uint32 minor_status)`

Initialize a previously allocated error of type GLOBUS\_ERROR\_TYPE\_GSSAPI.

##### Parameters:

- error* The previously allocated error object.
- base\_source* Pointer to the originating module.
- base\_cause* The error object causing the error. If this is the original error this parameter may be NULL.
- major\_status* The GSSAPI major status
- minor\_status* The GSSAPI minor status

##### Returns:

The resulting error object. You may have to call `globus_error_put()` on this object before passing it on.

## 3.3 Error Data Accessors and Modifiers

Collaboration diagram for Error Data Accessors and Modifiers:



Get and set data in a Globus GSSAPI Error object.

### Get Major Status

- OM\_uint32 `globus_error_gssapi_get_major_status` (globus\_object\_t \*error)

### Set Major Status

- void `globus_error_gssapi_set_major_status` (globus\_object\_t \*error, const OM\_uint32 major\_status)

## Get Minor Status

- OM\_uint32 [globus\\_error\\_gssapi\\_get\\_minor\\_status](#) (globus\_object\_t \*error)

### 3.3.1 Detailed Description

Get and set data in a Globus GSSAPI Error object.

This section defines operations for accessing and modifying data in a Globus GSSAPI Error object.

### 3.3.2 Function Documentation

#### 3.3.2.1 OM\_uint32 globus\_error\_gssapi\_get\_major\_status (globus\_object\_t \* *error*)

Retrieve the major status from a gssapi error object.

**Parameters:**

*error* The error from which to retrieve the major status

**Returns:**

The major status stored in the object

#### 3.3.2.2 void globus\_error\_gssapi\_set\_major\_status (globus\_object\_t \* *error*, const OM\_uint32 *major\_status*)

Set the major status in a gssapi error object.

**Parameters:**

*error* The error object for which to set the major status

*major\_status* The major status

**Returns:**

void

#### 3.3.2.3 OM\_uint32 globus\_error\_gssapi\_get\_minor\_status (globus\_object\_t \* *error*)

Retrieve the minor status from a gssapi error object.

**Parameters:**

*error* The error from which to retrieve the minor status

**Returns:**

The minor status stored in the object

## 3.4 Error Handling Helpers

Collaboration diagram for Error Handling Helpers:



Helper functions for dealing with Globus GSSAPI Error objects.

## Error Match

- globus\_bool\_t [globus\\_error\\_gssapi\\_match](#) (globus\_object\_t \*error, globus\_module\_descriptor\_t \*module, const OM\_uint32 major\_status)

## Wrap GSSAPI Error

- globus\_object\_t \* [globus\\_error\\_wrap\\_gssapi\\_error](#) (globus\_module\_descriptor\_t \*base\_source, OM\_uint32 major\_status, OM\_uint32 minor\_status, int type, const char \*source\_file, const char \*source\_func, int source\_line, const char \*short\_desc\_format,...)

### 3.4.1 Detailed Description

Helper functions for dealing with Globus GSSAPI Error objects.

This section defines utility functions for dealing with Globus GSSAPI Error objects.

### 3.4.2 Function Documentation

#### 3.4.2.1 globus\_bool\_t globus\_error\_gssapi\_match (globus\_object\_t \* error, globus\_module\_descriptor\_t \* module, const OM\_uint32 major\_status)

Check whether the error originated from a specific module and match a specific major status.

This function checks whether the error or any of it's causative errors originated from a specific module and contains a specific major status. If the module descriptor is left unspecified this function will check for any error of the specified major\_status and vice versa.

##### Parameters:

- error* The error object for which to perform the check
- module* The module descriptor to check for
- major\_status* The major status to check for

##### Returns:

GLOBUS\_TRUE - the error matched the module and major status GLOBUS\_FALSE - the error failed to match the module and major status

#### 3.4.2.2 globus\_object\_t\* globus\_error\_wrap\_gssapi\_error (globus\_module\_descriptor\_t \* base\_source, OM\_uint32 major\_status, OM\_uint32 minor\_status, int type, const char \* source\_file, const char \* source\_func, int source\_line, const char \* short\_desc\_format, ...)

Allocate and initialize an error of type GLOBUS\_ERROR\_TYPE\_GLOBUS which contains a causal error of type GLOBUS\_ERROR\_TYPE\_GSSAPI.

##### Parameters:

- base\_source* Pointer to the originating module.
- major\_status* The major status to use when generating the causal error.
- minor\_status* The minor status to use when generating the causal error.
- type* The error type. We may reserve part of this namespace for common errors. Errors not in this space are assumed to be local to the originating module.
- source\_file* Name of file. Use \_\_FILE\_\_
- source\_func* Name of function. Use \_globus\_func\_name and declare your func with GlobusFunc-Name(<name>)

*source\_line* Line number. Use `__LINE__`

*short\_desc\_format* Short format string giving a succinct description of the error. To be passed on to the user.

... Arguments for the format string.

**Returns:**

The resulting error object. It is the user's responsibility to eventually free this object using `globus_object_free()`. A `globus_result_t` may be obtained by calling `globus_error_put()` on this object.

## 4 globus\_gssapi error Directory Documentation

### 4.1 /builddir/build/BUILD/globus\_gssapi\_error-2.5/library/ Directory Reference

library

**Files**

- file `globus_error_gssapi.c`
- file `globus_error_gssapi.h`
- file `globus_i_error_gssapi.c`
- file `globus_i_error_gssapi.h`

## Index

/builddir/build/BUILD/globus\_gssapi\_error-  
2.5/library/ Directory Reference, [6](#)

Error Construction, [2](#)

Error Data Accessors and Modifiers, [3](#)

Error Handling Helpers, [4](#)

Globus GSSAPI Error API, [1](#)

globus\_error\_construct\_gssapi\_error

    globus\_gssapi\_error\_object, [3](#)

globus\_error\_gssapi\_get\_major\_status

    globus\_gssapi\_error\_accessor, [4](#)

globus\_error\_gssapi\_get\_minor\_status

    globus\_gssapi\_error\_accessor, [4](#)

globus\_error\_gssapi\_match

    globus\_gssapi\_error\_utility, [5](#)

globus\_error\_gssapi\_set\_major\_status

    globus\_gssapi\_error\_accessor, [4](#)

globus\_error\_initialize\_gssapi\_error

    globus\_gssapi\_error\_object, [3](#)

GLOBUS\_ERROR\_TYPE\_GSSAPI

    globus\_gssapi\_error\_object, [2](#)

globus\_error\_wrap\_gssapi\_error

    globus\_gssapi\_error\_utility, [5](#)

globus\_gssapi\_error\_accessor

    globus\_error\_gssapi\_get\_major\_status, [4](#)

    globus\_error\_gssapi\_get\_minor\_status, [4](#)

    globus\_error\_gssapi\_set\_major\_status, [4](#)

globus\_gssapi\_error\_object

    globus\_error\_construct\_gssapi\_error, [3](#)

    globus\_error\_initialize\_gssapi\_error, [3](#)

    GLOBUS\_ERROR\_TYPE\_GSSAPI, [2](#)

globus\_gssapi\_error\_utility

    globus\_error\_gssapi\_match, [5](#)

    globus\_error\_wrap\_gssapi\_error, [5](#)