

globus gssapi error Reference Manual

2.5

Generated by Doxygen 1.4.4

Fri Jun 26 22:20:50 2009

Contents

1 globus gssapi error Module Index	1
2 globus gssapi error Directory Hierarchy	1
3 globus gssapi error Module Documentation	1
4 globus gssapi error Directory Documentation	6

1 globus gssapi error Module Index

1.1 globus gssapi error Modules

Here is a list of all modules:

Globus GSSAPI Error API	1
Error Construction	2
Error Data Accessors and Modifiers	3
Error Handling Helpers	4

2 globus gssapi error Directory Hierarchy

2.1 globus gssapi error Directories


This directory hierarchy is sorted roughly, but not completely, alphabetically:

library	6
----------------	-------------------

3 globus gssapi error Module Documentation

3.1 Globus GSSAPI Error API

Collaboration diagram for Globus GSSAPI Error API:



These globus_error functions are motivated by the desire to provide a easier way of generating new error types, while at the same time preserving all features (e.g.

Modules

- [Error Construction](#)
- [Error Data Accessors and Modifiers](#)
- [Error Handling Helpers](#)

3.1.1 Detailed Description

These globus_error functions are motivated by the desire to provide a easier way of generating new error types, while at the same time preserving all features (e.g.

memory management, chaining) of the current error handling framework. The functions in this API are auxiliary to the function in the Globus Generic Error API in the sense that they provide a wrapper for representing GSSAPI errors in terms of a globus_error_t.

Any program that uses Globus GSSAPI Error functions must include "globus_error_gssapi.h".

3.2 Error Construction

Collaboration diagram for Error Construction:



Create and initialize a Globus GSSAPI Error object.

Construct Error

- globus_object_t * [globus_error_construct_gssapi_error](#) (globus_module_descriptor_t *base_source, globus_object_t *base_cause, const OM_uint32 major_status, const OM_uint32 minor_status)

Initialize Error

- globus_object_t * [globus_error_initialize_gssapi_error](#) (globus_object_t *error, globus_module_descriptor_t *base_source, globus_object_t *base_cause, const OM_uint32 major_status, const OM_uint32 minor_status)

Defines

- #define [GLOBUS_ERROR_TYPE_GSSAPI](#)

3.2.1 Detailed Description

Create and initialize a Globus GSSAPI Error object.

This section defines operations to create and initialize Globus GSSAPI Error objects.

3.2.2 Define Documentation

3.2.2.1 #define GLOBUS_ERROR_TYPE_GSSAPI

Error type definition.

3.2.3 Function Documentation

3.2.3.1 `globus_object_t* globus_error_construct_gssapi_error (globus_module_descriptor_t * base_source, globus_object_t * base_cause, const OM_uint32 major_status, const OM_uint32 minor_status)`

Allocate and initialize an error of type GLOBUS_ERROR_TYPE_GSSAPI.

Parameters:

- base_source* Pointer to the originating module.
- base_cause* The error object causing the error. If this is the original error, this parameter may be NULL.
- major_status* The GSSAPI major status
- minor_status* The GSSAPI minor status

Returns:

The resulting error object. It is the user's responsibility to eventually free this object using `globus_object_free()`. A `globus_result_t` may be obtained by calling `globus_error_put()` on this object.

3.2.3.2 `globus_object_t* globus_error_initialize_gssapi_error (globus_object_t * error, globus_module_descriptor_t * base_source, globus_object_t * base_cause, const OM_uint32 major_status, const OM_uint32 minor_status)`

Initialize a previously allocated error of type GLOBUS_ERROR_TYPE_GSSAPI.

Parameters:

- error* The previously allocated error object.
- base_source* Pointer to the originating module.
- base_cause* The error object causing the error. If this is the original error this parameter may be NULL.
- major_status* The GSSAPI major status
- minor_status* The GSSAPI minor status

Returns:

The resulting error object. You may have to call `globus_error_put()` on this object before passing it on.

3.3 Error Data Accessors and Modifiers

Collaboration diagram for Error Data Accessors and Modifiers:



Get and set data in a Globus GSSAPI Error object.

Get Major Status

- OM_uint32 `globus_error_gssapi_get_major_status` (`globus_object_t *error`)

Set Major Status

- void `globus_error_gssapi_set_major_status` (`globus_object_t *error`, const OM_uint32 major_status)

Get Minor Status

- OM_uint32 [globus_error_gssapi_get_minor_status](#) (globus_object_t *error)

3.3.1 Detailed Description

Get and set data in a Globus GSSAPI Error object.

This section defines operations for accessing and modifying data in a Globus GSSAPI Error object.

3.3.2 Function Documentation

3.3.2.1 OM_uint32 globus_error_gssapi_get_major_status (globus_object_t * *error*)

Retrieve the major status from a gssapi error object.

Parameters:

error The error from which to retrieve the major status

Returns:

The major status stored in the object

3.3.2.2 void globus_error_gssapi_set_major_status (globus_object_t * *error*, const OM_uint32 *major_status*)

Set the major status in a gssapi error object.

Parameters:

error The error object for which to set the major status

major_status The major status

Returns:

void

3.3.2.3 OM_uint32 globus_error_gssapi_get_minor_status (globus_object_t * *error*)

Retrieve the minor status from a gssapi error object.

Parameters:

error The error from which to retrieve the minor status

Returns:

The minor status stored in the object

3.4 Error Handling Helpers

Collaboration diagram for Error Handling Helpers:



Helper functions for dealing with Globus GSSAPI Error objects.

Error Match

- globus_bool_t [globus_error_gssapi_match](#) (globus_object_t *error, globus_module_descriptor_t *module, const OM_uint32 major_status)

Wrap GSSAPI Error

- globus_object_t * [globus_error_wrap_gssapi_error](#) (globus_module_descriptor_t *base_source, OM_uint32 major_status, OM_uint32 minor_status, int type, const char *source_file, const char *source_func, int source_line, const char *short_desc_format,...)

3.4.1 Detailed Description

Helper functions for dealing with Globus GSSAPI Error objects.

This section defines utility functions for dealing with Globus GSSAPI Error objects.

3.4.2 Function Documentation

3.4.2.1 globus_bool_t globus_error_gssapi_match (globus_object_t * error, globus_module_descriptor_t * module, const OM_uint32 major_status)

Check whether the error originated from a specific module and match a specific major status.

This function checks whether the error or any of it's causative errors originated from a specific module and contains a specific major status. If the module descriptor is left unspecified this function will check for any error of the specified major_status and vice versa.

Parameters:

- error* The error object for which to perform the check
- module* The module descriptor to check for
- major_status* The major status to check for

Returns:

GLOBALUS_TRUE - the error matched the module and major status GLOBALUS_FALSE - the error failed to match the module and major status

3.4.2.2 globus_object_t* globus_error_wrap_gssapi_error (globus_module_descriptor_t * base_source, OM_uint32 major_status, OM_uint32 minor_status, int type, const char * source_file, const char * source_func, int source_line, const char * short_desc_format, ...)

Allocate and initialize an error of type GLOBALUS_ERROR_TYPE_GLOBALUS which contains a causal error of type GLOBALUS_ERROR_TYPE_GSSAPI.

Parameters:

- base_source* Pointer to the originating module.
- major_status* The major status to use when generating the causal error.
- minor_status* The minor status to use when generating the causal error.
- type* The error type. We may reserve part of this namespace for common errors. Errors not in this space are assumed to be local to the originating module.
- source_file* Name of file. Use __FILE__
- source_func* Name of function. Use _globus_func_name and declare your func with GlobusFuncName(<name>)

source_line Line number. Use `__LINE__`

short_desc_format Short format string giving a succinct description of the error. To be passed on to the user.

... Arguments for the format string.

Returns:

The resulting error object. It is the user's responsibility to eventually free this object using `globus_object_free()`. A `globus_result_t` may be obtained by calling `globus_error_put()` on this object.

4 globus_gssapi error Directory Documentation

4.1 /builddir/build/BUILD/globus_gssapi_error-2.5/library/ Directory Reference



library

Files

- file **globus_error_gssapi.c**
- file **globus_error_gssapi.h**
- file **globus_i_error_gssapi.c**
- file **globus_i_error_gssapi.h**

Index

/builddir/build/BUILD/globus_gssapi_error-
2.5/library/ Directory Reference, [6](#)

Error Construction, [2](#)

Error Data Accessors and Modifiers, [3](#)

Error Handling Helpers, [4](#)

Globus GSSAPI Error API, [1](#)

globus_error_construct_gssapi_error

 globus_gssapi_error_object, [3](#)

globus_error_gssapi_get_major_status

 globus_gssapi_error_accessor, [4](#)

globus_error_gssapi_get_minor_status

 globus_gssapi_error_accessor, [4](#)

globus_error_gssapi_match

 globus_gssapi_error_utility, [5](#)

globus_error_gssapi_set_major_status

 globus_gssapi_error_accessor, [4](#)

globus_error_initialize_gssapi_error

 globus_gssapi_error_object, [3](#)

GLOBUS_ERROR_TYPE_GSSAPI

 globus_gssapi_error_object, [2](#)

globus_error_wrap_gssapi_error

 globus_gssapi_error_utility, [5](#)

globus_gssapi_error_accessor

 globus_error_gssapi_get_major_status, [4](#)

 globus_error_gssapi_get_minor_status, [4](#)

 globus_error_gssapi_set_major_status, [4](#)

globus_gssapi_error_object

 globus_error_construct_gssapi_error, [3](#)

 globus_error_initialize_gssapi_error, [3](#)

 GLOBUS_ERROR_TYPE_GSSAPI, [2](#)

globus_gssapi_error_utility

 globus_error_gssapi_match, [5](#)

 globus_error_wrap_gssapi_error, [5](#)