



15/7/2005

The NorduGrid/ARC User Guide

Advanced Resource Connector (ARC) usage manual

Refers to ARC release series 0.4 and up

Contents

1	Preface	9
2	Roadmap	11
3	Client Installation	13
3.1	Beginner Installation	13
3.1.1	Download	13
3.1.2	Unpack	13
3.1.3	Configure	13
3.2	System-wide installation	14
3.2.1	Globus Toolkit	14
3.2.2	Download the client	16
3.2.3	Build	16
3.2.4	Install the client	17
3.3	Client configuration files	17
3.3.1	.ngrc	17
3.3.2	.ngalias	18
3.3.3	.nggiislist	18
3.3.4	.ngjobs	18
3.3.5	.nghistory	18
4	Grid Certificates	19
4.1	Quick start with certificates	19
4.1.1	Certificates in local standalone client	19
4.1.2	Certificates for system-wide client installation	21
4.1.3	Obtain a personal certificate	21
4.2	Grid Authentication And Certificate Authorities	22
4.2.1	Grid Login, Proxies	22
4.2.2	Certificate Authorities	23
4.2.3	Globus Grid certificates	23
4.2.4	Associating yourself with a proper CA	24
4.2.5	Friendly CAs	25
4.2.6	Certificate Request	26
4.2.7	Working with certificates: examples	27

5	Getting Access to Grid Resources: Virtual Organisations	29
5.1	NorduGrid Virtual Organisation	29
5.2	Other Virtual Organisations	30
6	Grid Session	31
6.1	Logging Into The Grid	31
6.1.1	Proxy Handling Tips	32
6.2	First Grid test	32
6.3	Logging Out	33
7	Describing Grid Tasks	35
7.1	Task Description Language: xRSL	35
7.1.1	URLs	36
7.1.2	Task Description: Attributes	38
7.2	Examples	47
7.2.1	Hello World	48
7.2.2	An Own Executable	48
7.2.3	Many Executables	49
8	Job Management	51
8.1	Working with jobs	51
8.1.1	Submit A Job	51
8.1.2	Querying Job Status	53
8.1.3	Capturing Job Output	54
8.1.4	Retrieving Job Output	55
8.1.5	Killing Jobs	56
8.1.6	Re-submitting Jobs	56
8.1.7	Cleaning Up After Jobs	58
8.1.8	Renewing User Proxy	58
8.1.9	Synchronizing The Job ID List	59
9	Data Management	61
9.1	Working with files	61
9.1.1	Listing Grid Files	61
9.1.2	Copying Grid Files	62
9.1.3	Erasing Grid Files	62
9.2	gsincftp	63
9.3	Replica Catalog in Examples	63
9.3.1	Define who you are	64
9.3.2	Create a collection	64
9.3.3	Add a location to a collection	64
9.3.4	Upload and register a file to a collection	64
9.3.5	Register existing at a location file to a collection	65

CONTENTS	5
9.3.6 Remove and unregister a file	65
9.3.7 Remove a location from a collection	65
9.3.8 Find locations (URL prefixes) for a collection	66
9.3.9 Find a URL prefix for a location known by name	66
10 The Grid Monitor	67
10.1 The Grid Monitor	68
10.2 Cluster Description	69
10.3 Queue Details	70
10.4 Job Information	71
10.5 User Information	72
10.6 Attributes Overview	73
10.7 "Match-it-yourself"	74
10.8 Storage Resources	75
10.9 List of Users	75
11 HOWTO	77
A RPM For Everybody	79
A.1 Listing Contents of an RPM Package	79
A.2 Printing Out an RPM Package Information	79
A.3 Simple Unpacking of an RPM Archive	80
A.4 Creating a Private RPM Database	80
A.5 Installing an RPM Package	81
A.6 Upgrading RPM Packages	81
A.7 Relocating RPM Packages	81
A.8 Dealing with Dependencies	82
A.9 Listing Installed Packages	82
A.10 Uninstalling RPM Packages	83
A.11 Building RPM from Source	83
B Globus Toolkit 2 installation notes	85
C NorduGrid ARC build notes	87
C.1 Dependencies	87
C.2 Basic build with autotools	87
C.3 Building with RPM	88
C.4 Binary RPMs: runtime requirements	89
D Known Grid Certificate Authorities	91

List of Figures

1.1 Architectural components of the ARC middleware.	9
3.1 Downloading standalone client (example for Fedora Core 1 system).	14
3.2 Downloading GPT and Globus packages from the NorduGrid Web site. This example shows which RPM packages to download for the Fedora Core 1 Linux distribution.	15
3.3 Downloading different client packages: (1) binary client RPM, (2) standalone pre-compiled archive, (3) full source RPM. Example shows packages for Mandrake Linux.	16
4.1 Downloading NorduGrid Certificate Authority public keys. Example shows packages for Debian Linux.	20
4.2 Downloading NorduGrid Certificate Authority certificate request configuration package. Example shows packages for Debian Linux.	20
10.1 The Grid Monitor	68
10.2 ARC-enabled cluster details	69
10.3 Grid queue details	70
10.4 Grid job list	71
10.5 Grid job statistics	72
10.6 Grid user information	73
10.7 ARC objects grouped by attribute	73
10.8 Object class selection window	74
10.9 Attribute selection window	74
10.10 Customized cluster information display	75
10.11 List of storage elements	75
10.12 List of the NorduGrid users	76

Chapter 1

Preface

The NorduGrid's [1] Advanced Resource Connector (ARC) is a light-weight Grid solution, designed to support a dynamic, heterogeneous Grid facility, spanning different computing resources and user communities. It provides middleware to interface between user applications and distributed resources.

The NorduGrid ARC middleware is based on the Globus Toolkit® 2 API, libraries and services [2]. The architecture of the ARC middleware pursues stability and robustness of services, which implies complete decentralization and functional independence of the components. In order to support this architecture, several innovative approaches were used, such as the Grid Manager [3] and the User Interface (Section 8). Several Globus components were extended and developed further, such as the Information Model [4] and XRL { Extended Resource Specification Language (Section 7).

ARC main components are (see Figure 1.1):

- Grid services running on the resources: the Grid Manager, the `gridftp` and the information services.
- Indexing services for the resources and data.
- Clients making intelligent use of the distributed information and data available on the Grid.




Figure 1.1: Architectural components of the ARC middleware.

This User Guide puts together descriptions of user-end parts of the ARC middleware, serving as a user manual and a reference. It also includes basic examples and the ARC client installation instructions.

The User Guide does not provide detailed description of third-party tools, such as the Globus Toolkit® 2 , giving only minimal necessary information.

The definitive description of the components and services can be found in separate manuals:

User Interface : "The NorduGrid toolkit user interface", user manual [5]

xRSL : "Extended Resource Specification Language" [6]

Grid Manager : "The NorduGrid Grid Manager", description and administrator's manual [3]

Grid Monitor : "The Grid Monitor", usage manual [7]

Detailed installation and configuration instructions are included into the ARC software distribution, available for download at:

<http://www.nordugrid.org>

Any further questions should be addressed to

nordugrid-support@nordugrid.org

Chapter 2

Roadmap

On your way to start enjoying the power of Grid computing, you will have to pass the following milestones:

1. Client : install the client on your computer, or get access to a computer where the client is installed. See Chapter 3 on client installation.
2. Certificate : obtain your Grid passport: a personal certificate. See Chapter 4 on certificates for details.
3. Access: become a member of a user group, authorized to use a set of resources (also known as Virtual Organisation). See Chapter 5 on Virtual Organisations.
4. Hands-on : start a Grid session and try simple tests. See Chapter 6 for guidance.
5. xRSL : learn how to describe your task and corresponding requirements in Grid parlance. See Chapter 7 for guidelines.
6. User interface : get acquainted with the task and data management on Grid: job submission, status monitoring, cancellation, result retrieval etc.. See Chapters 8 and 9 for complete description.
7. User support : whenever encountering a Grid problem, write to nordugrid-support@nordugrid.org.

Chapter 3

Client Installation

The very first step to get acquainted with ARC-enabled facilities is to download and install the client package. There are several ways to do it, you just have to chose which suits you best. Binary distributions are available for several GNU/Linux avors, such as RedHat, Mandrake, Debian, SuSE, Fedora, Slackware, etc.. Source distributions are available as well.

The client package may be installed system-wide by a system administrator (Section 3.2), or locally, by a non-privileged user (Section 3.1). A multi-user computer may have several client installations, they do not interfere with each other. A full client takes less than 10 MB of disk space.

You may install a client at any computer you use: e.g., on your o ce desktop, a notebook, your home computer etc.. You can even load it on a USB memory. One thing to remember when using di erent clients interchangeably is to keep them in sync, as described in Section 8.1.9.

While client installation procedure itself is trivial, there is a lot of ne tuning that can be done by an advanced user. See Chapter 4 on authorization issues, and Section 3.3 on client con guration.

3.1 Beginner Installation

For a local installation by a user without system administrator privileges, it is advised to download and install a stand-alone distribution of the NorduGrid ARC client. This package is distributed in .tgz format and contains all the required third-party components (Globus Toolkit® 2 components). Scripts provided with the package do all the necessary initial con guration and setup.

3.1.1 Download

Download a pre-compiled stand-alone binary distribution suitable for your operating system from the NorduGrid Downloads area at <http://ftp.nordugrid.org/download>, see Figure 3.1.

3.1.2 Unpack

Put the downloaded package in a directory of your choice and execute

```
tar xvzf nordugrid-standalone- <version>.tgz
```

This will create a new directory `nordugrid-standalone-<version>`, and the downloaded.tgz package can be safely removed.

3.1.3 Con gure

Con gure and set up environment variables (most notably, \$NORDUGRID_LOCATION and \$GLOBUS_LOCATION) doing the following:




Figure 3.1: Downloading standalone client (example for Fedora Core 1 system).

```
cd nordugrid-standalone- <version>
source setup.sh
```

If you are working in a C shell, usesetup.csh instead of setup.sh . In some environments, you will have to do instead

```
./setup.sh
```

in the nordugrid-standalone- <version> directory. Upon first execution, this will print a lot of informational output. Make sure there are no "error" or "failure" messages.

3.2 System-wide installation

This Section is oriented primarily towards users with system administrator privileges. Local installation by any user is described in Section 3.1.

For a system-wide installation, usage of RPMs is recommended for those Linux distributions which support it. Otherwise, the client can be installed from binary tarballs, or built from the source.

For a fully functioning client, the following packages have to be installed:
 gpt
 globus
 nordugrid-client
 Public keys of your Certificate Authority
 Certificate request configuration files

Installation of the certification-related packages is related to security issues and is discussed in Chapter 4.

3.2.1 Globus Toolkit

The Globus Toolkit® 2 must be installed at your machine prior to any system-wide Grid installation. You may get it from the Globus project Web site [2], however, it is strongly recommended to use the distribution available at the NorduGrid download area, as it contains several critical bug fixes.

Case A. If you already have a Globus Toolkit® 2 installed on your system, check that the following variables are defined and point to the proper locations:

```
echo $GLOBUS_LOCATION $GPT_LOCATION
```

If the variables are not defined, set them according to your installation. Typically, GLOBUS_LOCATION /opt/globus and GPT_LOCATION /opt/gpt

Case B. If there is no Globus installation, or you want to profit from the Globus Toolkit® 2 distribution with the most recent bug fixes and patches, download from <http://ftp.nordugrid.org/download> (see Figure 3.2) and install the necessary packages in the following order:

```
rpm -Uvh gpt-<version>.rpm
export GPT_LOCATION=/opt/gpt(or setenv GPT_LOCATION /opt/gptfor a C-shell)
rpm -Uvh globus-<version>.rpm
export GLOBUS_LOCATION=/opt/globus(or setenv GLOBUS_LOCATION /opt/globusfor a C-shell)
```

The screenshot shows the NorduGrid download interface with two main sections: GPT (3.1, 2004-03-25 CET 10:20:38) and Globus Toolkit (2.4.3, 2004-03-25 CET 13:24:17). Both sections have tabs for 'NorduGrid middleware', 'External software', and 'CA certificates'. In the 'External software' tab, the 'gpt' section is highlighted with a red oval around the 'globus', 'globus-config', 'gpt', and 'goap' packages. The 'globus' section is also highlighted with a red oval around the 'globus', 'globus-config', 'gpt', and 'goap' packages. Below each table are 'Reset' and 'Get latest' buttons. The 'GPT' table has columns for 'distribution', 'gpt', and 'source'. The 'Globus Toolkit' table has columns for 'distribution', 'globus', and 'source'.

distribution	gpt	source
debian-3.0	[i386 rpm] [i386 tgz]	
fedora-1	[i386 rpm] [i386 tgz]	
fedora-1.90	[x86_64 rpm] [x86_64 tgz]	

distribution	globus	source
debian-3.0	[i386 rpm] [i386 tgz]	
fedora-1	[i386 rpm] [i386 tgz]	
mandrake-8.0	[i686 rpm] [i686 tgz]	

Figure 3.2: Downloading GPT and Globus packages from the NorduGrid Web site. This example shows which RPM packages to download for the Fedora Core 1 Linux distribution.

You may well want to install the Globus Toolkit® 2 from pre-compiled tarballs provided at the NorduGrid download site. In such a case, take care to execute post-installation procedures:

```
<globus location>/setup/globus-post-install-script
```

```
<globus location>
```

Here <globus location> is the directory to which you unpacked Globus (by default /opt/globus).

NB: on some systems and distributions, certain additional external packages need to be installed in order to make GT2 operational. Some of those are available from the NorduGrid downloads area, "External software" section. See Appendix B for additional information.

3.2.2 Download the client

Download a NorduGrid ARC client package suitable for your operating system and distribution from the NorduGrid Downloads area at <http://ftp.nordugrid.org/download> :

- { If you are installing on top of an older Globus version, download a full source NorduGrid RPM (nordugrid- <version>.src.rpm) or a tarball (nordugrid- <version>.tgz) (see Figure 3.3).
- { If you just have installed Globus as described in Section 3.2.1, download just a binary client RPM nordugrid-client <version>.rpm (see Figure 3.3).

The screenshot shows the NorduGrid Downloads interface. At the top, there are three tabs: "NorduGrid middleware", "External software", and "CA certificates". The "External software" tab is selected. Below the tabs, there is a search bar with placeholder text "Search for packages" and a "Search" button. To the right of the search bar are two buttons: "Reset" and "Get latest". Under the tabs, there is a section titled "Release (0.4.1, 2004-04-14 CEST 00:56:27)". This section contains a table with rows for different distributions. The columns represent package types: ca-utils, client, devel, doc, gridmap-utils, monitor, server, standalone, and source. Each cell in the table contains a link to a specific package. Red circles numbered 1, 2, and 3 point to specific links in the table:

distribution	ca-utils	client	devel	doc	gridmap-utils	monitor	server	standalone	source
debian-3.0	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 tgz]	
fedora-1	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 tgz]	
mandrake-8.0	[i686 rpm] [i686 tgz]	1 [i686 rpm] [i686 tgz]	[i686 tgz]						
mandrake-9.1	[i586 rpm] [i586 tgz]	[i586 rpm] [i586 tgz]	[i586 rpm] [i586 tgz]	[i586 rpm] [i586 tgz]	[i586 rpm] [i586 tgz]	[i586 rpm] [i586 tgz]	[i586 rpm] [i586 tgz]	2 [i586 tgz]	3 [full rpm] [full tgz] [CVS tgz]
redhat-3ES	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 tgz]	
redhat-6.2	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 rpm] [i386 tgz]	[i386 tgz]	

Figure 3.3: Downloading different client packages: (1) binary client RPM, (2) standalone pre-compiled archive, (3) full source RPM. Example shows packages for Mandrake Linux.

3.2.3 Build

If you have installed Globus as described in Section 3.2.1, skip to Section 3.2.4.

If you are installing on top of an older Globus version, you have to rebuild the client from source. Make sure that all the necessary external packages are installed: see Appendix C for details.

When all the external packages are in place, build the NorduGrid ARC from the source RPM:

```
rpmbuild --rebuild nordugrid-<version>.src.rpm
```

This will create several binary RPMs; for the client, you will need only `nordugrid-client <version>.rpm`.

Alternatively, to build from the tarball, do the following:

```
cat README
tar xvzf nordugrid-<version>.tgz
cd nordugrid-<version>
./configure
make
make install
```

3.2.4 Install the client

Install the client RPM:

```
rpm -Uvh nordugrid-client <version>.rpm
```

Set up the environment variables:

```
source /etc/profile.d/nordugrid.sh
```

Or, for a C shell and alike,

```
. /etc/profile.d/nordugrid.sh
```

IMPORTANT! This client will not be functional until you install proper public keys, necessary to establish contact with Grid services. Read Chapter 4 to learn how to do it.

3.3 Client configuration files

There are several files that can be used for configuring the ARC client. They should be located in the user's home directory, and their names start with `.ng`.

3.3.1 .ngrc

This file contains the user's settings for the debug level, the resource lookup timeout and the download directory used by ngget (see Section 8.1.4). A sample file could be the following:

```
# Sample .ngrc file
# Comments start with #
NGDEBUG=1
NGTIMEOUT=10
NGDOWNLOAD=/tmp
```

If the file is absent or some variables are not specified, the default values are used. The default debug level is 0, the default timeout is 40 seconds and the default download directory is the current working directory.

If the environment variables NGDEBUG, NGTIMEOUT and NGDOWNLOAD are defined, they take precedence over the values defined in `.ngrc`. Any corresponding command line option overrides the defaults.

3.3.2 .ngalias

The file `.ngalias` contains user-defined aliases for clusters or groups of such. Quite often, users would decide to submit jobs to a specific resource, or instruct the broker to choose between a limited set of resources. While this can be achieved by listing explicitly the desired resources during the description, usage of aliases often saves a lot of typing. A typical `.ngalias` file can look like this:

```
parallab=fire.ii.uib.no
monolith=login-3.monolith.nsc.liu.se
bluesmoke=bluesmoke.nsc.liu.se
hagrid=hagrid.it.uu.se
ingrid=ingrid.hpc2n.umu.se
sigrid=sigrid.lunarc.lu.se
beppe=sg-access.pdc.kth.se
hive=hive.unicc.chalmers.se
swagrid=hagrid ingrid sigrid bluesmoke beppe hive
redhat73=monolith bluesmoke
```

Conveniently, an alias can be assigned to a group of aliases, as shown in the example above.

3.3.3 .nggiislist

The user can specify a personal list of top-level Grid indices (necessary entry points) by creating the file `.nggiislist` in the home directory. This requires knowledge of contact strings for such services (LDAP databases in current implementation) and should be typically used by very advanced users who know exactly what they are doing. The format of `.nggiislist` file can be as follows:

```
ldap://grid.nbi.dk:2135/Mds-Vo-name=NorduGrid,O=Grid
ldap://quark.hep.lu.se:2135/Mds-Vo-name=NorduGrid,O=Grid
ldap://heppc08.nbi.dk:2135/mds-vo-name=atlas,o=grid
```

3.3.4 .ngjobs

The file `.ngjobs` contains a local list of the user's active jobs. When a job is successfully submitted it is added to this list and when it is removed from the remote cluster it is removed from this list. For information about how to reconstruct this file if it is lost or when switching to a different computer, see Section 8.1.9.

3.3.5 .nghistory

The file `.nghistory` contains the list of jobs the user has submitted through this particular client instance. This file is purely informational and should not normally need any editing.

Chapter 4

Grid Certificates

This Chapter is not an easy reading, but the presented knowledge is essential for newcomers unfamiliar with Grid. Impatient readers can go to Section 4.1 for quick instructions; however, it is strongly recommended to eventually read the entire Chapter.

In a Grid environment such as the NorduGrid/ARC, users normally don't have local password-protected accounts on computing resources they intend to use. You should hold instead an electronic certificate, which ensures unique authentication.

This Chapter gives some basic information on:

- a) what is a Certificate Authority and how to associate yourself with an appropriate one
- b) how to request user certificates
- c) how to use a certificate
- d) why do you have to trust different Certificate Authorities and how to obtain their credentials

Possession of a certificate, however, does not automatically authorize you to use any Grid resource.

Access control for the computing resources is a matter of local policy: site administrators retain full control of choosing which Grid user is allowed to use their resources. Typically, such local authorization process is done by mapping an accepted set of Grid users onto a set of local user accounts. See Chapter 5 on how to get access to the Grid resources and other related information.

4.1 Quick start with certificates

This section is primarily intended for the Nordic countries (Denmark, Finland, Iceland, Norway and Sweden) and Estonia residents (current members of the NorduGrid collaboration). Users from other places should modify instructions accordingly or read further for detailed information.

The amount of setup you have to do regarding certificates depends on the way you installed the client.

4.1.1 Certificates in local standalone client

Luckily, the standalone client (Section 3.1) comes with all the necessary pre-requisites. Continue to Section 4.1.3 to learn how to obtain a personal certificate.

NorduGrid middleware External software CA certificates

nightly releases tags	globus globus-config gpt gsoap	certrequest-config datagrid nordugrid others
-----------------------	---	--

SHIFT- or CTRL-click to select multiple packages Reset Get latest

certificateAuthorities/nordugrid (0.20, 2004-03-25 CET 13:57:13)

	ca_NorduGrid	ca_NorduGridTutorial	source
debian-3.0	[noarch rpm] [noarch tgz]	No build	
fedora-1	[noarch rpm] [noarch tgz]	No build	
mandrake-8.0	[noarch rpm] [noarch tgz]	No build	

Figure 4.1: Downloading NorduGrid Certificate Authority public keys. Example shows packages for Debian Linux.

NorduGrid middleware External software CA certificates

nightly releases tags	globus globus-config gpt gsoap	certrequest-config datagrid nordugrid others
-----------------------	---	--

SHIFT- or CTRL-click to select multiple packages Reset Get latest

certificateAuthorities/certrequest-config (0.1, 2004-04-07 CEST 15:53:12)

	ca_Estonia-certrequest-config	ca_NorduGrid-certrequest-config	source
debian-3.0	[noarch rpm] [noarch tgz]	[noarch rpm] [noarch tgz]	
fedora-1	[noarch rpm] [noarch tgz]	[noarch rpm] [noarch tgz]	
mandrake-8.0	[noarch rpm] [noarch tgz]	[noarch rpm] [noarch tgz]	

Figure 4.2: Downloading NorduGrid Certificate Authority certificate request configuration package. Example shows packages for Debian Linux.

4.1.2 Certificates for system-wide client installation

System-wide client installation from RPMs or tarballs, as described in Section 3.2, does not include files (public keys and configuration templates) necessary for certificate request and usage operations. Therefore, you have to obtain them from the relevant Authority (see Section 4.2 for information on different Certificate Authorities). Examples in this Section refer to the NorduGrid one .

You will have to download and install two packages:
ca_NorduGrid
ca_NorduGrid-certrequest-config

The packages are available as RPM or tarball files from the NorduGrid download area at <http://ftp.nordugrid.org/download> , in the "CA certificates" section. You will need **nordugrid certificates** and **certrequest-config** package, see Figures 4.1 and 4.2 for illustration.

Install the downloaded packages; e.g., for RPMs:

```
rpm -Uvh ca_NorduGrid*
```

You have now all the necessary requisites to request a NorduGrid certificate and to use it for your authentication. Continue to Section 4.1.3 to learn how to request a personal certificate.

4.1.3 Obtain a personal certificate

To obtain a personal certificate, do:

```
grid-cert-request -int -ca
```

Follow carefully the instructions:

1. Select the appropriate Authority from the list: NorduGrid (hash 1f0e8352) or Estonia (hash 566bf40f)
2. Enter the password (called "passphrase") and memorize it
3. If asked, enter the two-letter country code (EE for Estonia) or hit "Return"
4. Enter Grid for Level 0 Organization Name or hit "Return"
5. If asked, enter NorduGrid for Level 1 Organization Name or hit "Return"
6. Enter your domain: typically, the string which follows @ in your official e-mail address, e.g. cd.uit.fi
7. Enter your name using strict Latin alphabet characters , e.g. Goran Mueller
8. Enter your official e-mail address

This procedure will create a new directory called **.globus** in your home directory, and generate several files there. If you already have this directory, make sure it is empty or rename it before issuing **grid-cert-request** , e.g., to **.globus.old** .

Send the certificate request to the corresponding Certificate Authority, NorduGrid CA if you are a Nordic country resident:

Same instructions are valid for the Estonian certificates, replace simply "NorduGrid" with "Estonia" in all the strings

```
cat ~/.globus/usercert_request.pem | mail ca@nbi.dk
```

or the Estonian CA, if you live in Estonia:

```
cat ~/.globus/usercert_request.pem | mail ca@grid.eenet.ee
```

Now you only have to wait: within 2 working days you will receive an e-mail containing your public certificate, signed by the proper authority. Find the part of the message that looks like:

-----BEGIN CERTIFICATE-----

```
MIIIC6zCCAISgAwIBAgICAPAwDQYJKoZIhvcNAQEEBQAwTzENMAsGA1UEChMER3Jp
ZDESMBAGA1UEChMJTm9yZHVHcmIkMSowKAYDVQQDEyFOb3JkdUdyWQgQ2VydGlm
aWNhdGlvbiBBdXR0b3JpdHkwHhcNMDMwNTIxMTkzOTA3WhcNMDQwNTIwMTkzOTA3
WjBQM0wCwYDVQQKEwRHcmIkMRIwEAYDVQQKEwIOb3JkdUdyWQxEjAQBgNVBAst
MFIxDTALBgNVBAoTBEdyaWQxEjAQBgNVBAoTCU5vcmR1R3JpZDEUMBIGA1UECxML
cXVhcmsgsubHUuc2UxFzAVBgNVBAMTDk94YW5hIFNtaXJub3ZhMIGfMA0GCSqGSIb3
DQEBAQUAA4GNADCBiQKBgQC5qAKyKGvO/6G7VC2CnICXWAwvKFX961AcyKeT5zxg
IDXUVxIhrLnHGKh9tIUZxG0NCT1UTQ+W4FVo5EPSPdsHI1MOyoVUF+HNlgII/TNj
AgMBAAGjgdQwgdEwCQYDVR0TBAlwADAsBglghkgBhvCAQ0EHxYdT3BlbINTCBH
ZW5lcmF0ZWQgQ2VydGlmawNhdGUwHQYDVR0OBBYEFLmvMBnYA8BjeeOmtDzmE84y
2fCiMHcGA1UdlwRwMG6AFBgFwPwL0bc69GWSCftZoV/HiMTwoVOkUTBPMQ0wCwYD
VQQKEwRHcmIkMRIwEAYDVQQKEwIOb3JkdUdyWQxEjAoBgNVBAMTIU5vcmR1R3Jp
ZCBDZXJ0aWZpY2F0aW9uIEF1dGhvcml0eYIBADANBgkqhkiG9w0BAQQFAAOBgQC1
VPU8sBArpPAoZKgWOMM7C7EZBQ2xKMAU+uJqWcAHPqGEReGbghCBIwlsQP3onT2Y
SqFWQSHM5gXBZ6sWGw+YrAiGfURgsSsYZwSa9Bs6mJcANxNU8HioyY1ngJwVJMDr
lxco0tWbHZpekWMe9QG8gn/OUKdXz1TKUS9Cx+mBZw==
```

-----END CERTIFICATE-----

Save such text in

```
~/.globus/usercert.pem
```

Check the information stored in the certificate:

```
grid-cert-info
```

Now you can use this certificate as your electronic passport on the Grid and elsewhere. Read Chapter 5 and apply for access to Grid resources, and then go to Chapters 7 and 8 to learn how to work on Grid.

4.2 Grid Authentication And Certificate Authorities

Instructions given in Section 4.1 refer to the NorduGrid Certificate Authority as the body that is appointed to issue Grid certificates in Nordic countries. This section describes basics of Grid security and explains what are Certificate Authorities, what are their functions, and what you should do in a generic case in order to obtain proper certificates.

4.2.1 Grid Login, Proxies

One of the main purposes of the Grid is to provide a transparent access to computing and storage resources. For a user, it means that a single login procedure must give access to all the available Grid resources.

Technically, this is implemented via a system of proxies. A user issues a temporary public proxy, which contains encrypted information about the issuer, and allows Grid services to act on her behalf while the proxy is valid. Thus, when a user wants to contact a resource, her client upon request presents the proxy to the remote server, which saves user from typing in login name and password.

Any Grid operation requires a valid proxy issued by the user. Validity of proxies is time-limited; typically, they expire in 12 hours, although users can issue proxies of any lifetime.

To make such handshake between the user's client and a Grid service happening, the following conditions must be satisfied:

- { the remote server must be able to check the proxy authenticity;
- { the user (her client) in turn must be able to check the remote server authenticity through its credentials.

The Grid utilizes public key, or asymmetric cryptography, for authentication of users, resources and services [8]. According to the basics of the public key cryptography, each actor on the Grid (a user or a service) must have a key pair: a public and a private key. The public key is, quite naturally, made public while the private key must be kept secret.

AVOID STORING YOUR PRIVATE KEY ON A PUBLIC FACILITY, SUCH AS A SHARED ACCESS COMPUTER, KEEP IT ON YOUR PRIVATE COMPUTER INSTEAD. COMPROMISED KEYS ARE REVOKED BY THE AUTHORITY.

Encryption and authorization is performed using the public key, while decryption and digital signature is performed with the private key.

Since Grid services act on behalf of users, such services and all the resources which provide them must have a key pair as well.

4.2.2 Certificate Authorities

Keys are generated by users or service administrators with the help of standard tools (see, e.g, Section 4.2.7). In order to become accepted by other parties, public keys must be signed by trusted authorities of the Grid, called Certificate Authorities (CA).

It is important to note that generating a key pair does not automatically provide you access to the Grid resources. A CA needs to sign your key pair, thus confirming your identity. This signing procedure of the CA is often referred to as "issuing a certificate".

Issuing a certificate is similar to issuing a national passport to a person, and typically, there is one CA per country. There are few exceptions though: for example, NorduGrid CA serves all the Nordic countries, while in bigger countries like USA, France or Germany, there are several CAs. For a non-authoritative list of CA's, refer to Appendix D.

The role of CAs is not only to confirm users identities and certify resources, but also to keep track of abuse of the issued certificates. CA's regularly publish Certificate Revocation Lists (CRL), with which all the Grid services comply. If your private key happened to be in possession of another person, or your identity was used for illegal exploits, your certificate is revoked and you will be unable to work on Grid. The same is true for resource certificates: if a computer is used for repetitive offences, its certificate will be revoked.

4.2.3 Globus Grid certificates

In the Globus framework, the key pair of public-key cryptography consists of the key file (default name userkey.pem) and the public certificate file (default name usercert.pem). This means every Grid user must have these two files every time she has to communicate with Grid resources.

The userkey.pem file (or resourcekey.pem when a Grid resource is concerned) contains the private key encrypted with a password (called "pass phrase" by Globus).

The "pass phrase" is a password to protect a certificate. Any certificate, be it a user, a host, or a service one, must be protected by a separate password DO NOT confuse it with a user or a system administrator log-in password!

The certificate file `usercert.pem` contains your public key together with additional important information such as the Subject Name(SN) of the certificate holder, the name of the signing CA, and a digital signature of this CA. The important role of the CA is to establish a trustful connection between the identity of the user and the public key in the certificate file. The digital signature of the CA in the user's certificate file officially declares that the public key in the file indeed belongs to the specific user (Subject Name). This is similar to the police department stamp in your passport: it confirms that the document indeed contains correct information.

The certificate files are encoded with the x.509 [9] format and need special tools to get decrypted. See Section 4.2.7 for some examples.

4.2.4 Associating yourself with a proper CA

To generate a certificate request, you must know to which CA this request will be submitted. The process is similar to a passport application: you must choose to which country (authority) to apply, and that authority will decide whether to grant your request or not.

Many countries have a CA, or even several { depending on the area of activities these authorities cover. Some countries have one CA for all { like the Nordic countries. Yet most countries have no CA, and citizens of such have to establish a CA and make sure it complies with international rules and is consequently accepted by others. Meanwhile, the French Committee for Scientific Research (CNRS) issues certificates for most academic and educational users, but this is a provisional arrangement. The list of some known CAs can be found in Appendix D. Unfortunately, there is no commonly accepted world-wide body that keeps track of and validates various CAs.

In case you are a Nordic country resident and have no certificate, you should request it from the NorduGrid Certificate Authority. To do this, you should download at <http://ftp.nordugrid.org/download> (section "CA certificates", see Figure 4.2) two packages:

1. Public keys of the NorduGrid Certificate Authority
2. The corresponding `certrequest-config` configuration package

The standalone ARC client installation keeps keys and configuration files in the directory `$NORDUGRID_LOCATION/share/certificates`, which by default contains all the files necessary for the Nordic users.

If you use a centralized ARC installation, install the RPM packages using

```
rpm -Uvh ca_NorduGrid-*
```

or use the provided tarballs. The following files will be installed in `/etc/grid-security/certificates` :

```
1f0e8352.0
1f0e8352.crl_url
1f0e8352.signing_policy
globus-host-ssl.conf.1f0e8352
globus-user-ssl.conf.1f0e8352
grid-security.conf.1f0e8352
```

You may well prefer installing the files in any location other than `/etc/grid-security/certificates`, and point the `$X509_CERT_DIR` variable to such alternative location.

If you reside in any other country, please contact your local CA or the CNRS one (see Appendix D) for public keys and configuration files. They will have the names similar to those shown in the example above, except for the alphanumeric 8-characters hash. Install them either in /etc/grid-security/certificates , or in any other location pointed by the \$X509_CERT_DIR variable.

If you are using the standalone client, the files must be installed in \$NORDUGRID_LOCATION/share/certificates or in any other location pointed by the \$X509_CERT_DIR variable.

You can also install all the necessary keys and configuration files in your private \$HOME/.globus/certificates/ directory; in this case however you will not be able to use those installed centrally.

You may have as many keys and configuration files installed as you wish. Moreover, you must have the public keys of all the CAs that certify the Grid resources you will use, and of all the CAs that certify potential users of your own resource. Section 4.2.5 has some details on such "Friendly CAs".

Please remember that installing a CA key implies that you accept their rules and policies, and trust their judgement of users, { in other words, you establish a trust relationship with the authority.

4.2.5 Friendly CAs

Depending on what is your Grid certificate issuing authority and which Grid resources you intend to use, you will have to install public certificates and other attributes of the necessary authorities. Table 4.1 presents a short check-list, summarizing which certificates you would need.

Your certificate	Will use NorduGrid resources	Will use other Grid resources
NorduGrid certificate	NorduGrid CA certificate and signing policy	
Other Grid certificate	Your issuing CA certificate and signing policy file (if any) and the NorduGrid CA certificate and signing policy	Certificates, signing policies and other attributes (if any) of all the CAs that certified the resources
No Grid certificate	NorduGrid CA certificate and signing policy, and certificate request configuration files	

Table 4.1: Check-list of needed certificates

The recommended procedure to obtain other CA certificates and attributes is to fetch them directly from the CAs in question. They are typically available from their respective Web sites (for a non-authoritative list, see Appendix D).

If for some reason it is impossible to fetch your CA attributes (e.g., Web site unavailable, holiday season etc.), you may download the necessary files from the NorduGrid downloads area at <http://ftp.nordugrid.org/download>. The attributes are platform- and system-independent. Install the CA attributes either from RPMs:

```
rpm -Uvh <your CA name> *
```

or from the provided tarballs.

IMPORTANT! The rule of thumb when installing the NorduGrid ARC middleware is always to check the contents of the /etc/grid-security/certificates and/or \$X509_CERT_DIR folder and to make sure that it does contain certificates and signing policy files of your certificate issuer CA and the friendly CAs. A typical listing of the folder should look as follows:

```
> ls -1 $X509_CERT_DIR
1f0e8352.0
1f0e8352.signing_policy
bc870044.0
```

```
bc870044.signing_policy
d64ccb53.0
```

Here 8-symbol file names with extension ".0" are the certificates containing public keys of different CAs.

Different users may trust different CAs, not necessarily those centrally accepted. In such a case, they should collect the keys of CAs they trust either in the \$HOME/.globus/certificates/ directory, or in any other place they define as \$X509_CERT_DIR. In such a case, Grid utilities will look for the keys only in the user-specified directory.

If you have a \$HOME/.globus/certificates/ directory, make sure it contains your own CA key, as well as other friendly CA keys. If your central system installation is missing a key, you always can install it in your \$HOME/.globus/certificates/ directory, but then you must copy all the other needed keys to this directory.

In general, the certificates and configuration files can be located in any of the following directories:

```
/etc/grid-security/certificates
$NORDUGRID_LOCATION/share/certificates
$X509_CERT_DIR
$HOME/.globus/certificates
```

The latter has the precedence, as each user is free to choose whom to trust.

4.2.6 Certificate Request

In order to obtain a valid "passport" on the Grid, you need to create a key pair and submit your public key to your local CA to get an approval. This process is called "certificate request". The CA will follow its certificate policy and upon successful evaluation of your request your public key will be signed and sent back to you. This may involve communication between the CA and your employer, or any other adequate procedure.

As it was mentioned before, all the resources (i.e. gatekeepers, storage facilities or other services) require a CA-signed key pair as well, in order to be able to operate on the Grid. In this case, resource owners create host key pairs and send them to be validated by the local CA. This is similar to registering a car and obtaining a license plate.

Please always remember that a Grid passport consists of two files, the private key file and the public certificate file. You need to have both of them, the certificate file (usercert.pem) alone is not enough for the Grid. If you lose one of your key files, you will have to generate a new CA-signed key pair.

To request a personal or a host certificate, you must decide to which authority you want to submit such a request. Appendix D lists some known authorities and their contact addresses. Each CA has its own procedure, which you have to follow. Typically, you must request a certificate from the CA of your country of residence. If your country has no CA, you may ask the CNRS "catch-all" CA to provide you with one.

If you are not a Nordic country resident, you may well try (upon consulting the NorduGrid personnel at nordugrid-support@nordugrid.org) to use the procedures described here to request a certificate from another Certificate Authority. However, most of them have their own established procedures (see Appendix D for a reference), and you are strongly advised to follow them.

Before requesting the certificate, please make sure that your CA public keys and configuration files are installed as described in Section 4.2.4.

The certificate request should be prepared by doing the following:

```
grid-cert-request -int -ca
```

From the presented list, select the appropriate CA (for example, NorduGrid, if you are a Nordic country resident), and then enter the requested information at each interactive prompt. Typically, you should use the suggested default values, and your proper data: domain, name, e-mail etc. Upon request, type and confirm your certificate protection password.

NOTE: the certificate protection password is not related to any other password, and must be different from, e.g., your system login password. Memorize well the password, as it can not be reset! Although you can change the password any time (see Section 4.2.7), if you forget the password, you will have to request a new certificate.

Follow the printed suggestions strictly, e.g., for the Nordic certificate, do the following:

```
cat $HOME/.globus/usercert_request.pem | mail ca@nbi.dk
```

Alternatively, simply send the file `$HOME/.globus/usercert_request.pem` to the contact e-mail address of your CA (`ca@nbi.dk` in case of a Nordic certificate).

For detailed step-by-step instructions, check Section 4.1.3.

The certificate request procedure creates the new directory `globus` in your `$HOME` area, and places there three files^Y:

<code>usercert_request.pem</code>	the official certificate request, to be mailed to your CA
<code>userkey.pem</code>	your private key
<code>usercert.pem</code>	your public certificate placeholder (initiated with zero size)

The `userkey.pem` holds your private key encoded with your pass phrase (you are prompted to supply this pass phrase during the key pair generation). This file must only be readable by its owner, that is, you. The `usercert_request.pem` file contains your unsigned public key together with your Subject Name and the name of your CA. The `grid-cert-request` creates also an empty `usercert.pem` file, just as a placeholder, which later must be overwritten with your CA-signed certificate that you will receive by e-mail.

When and if the CA fulfills your request, they will send you the actual public certificate, which you must store as `$HOME/.globus/usercert.pem`, overwriting the placeholder.

You can use the `openssl` [10] cryptography toolkit and the Globus provided commands to create, check and convert between different formats, and to manipulate your certificate files (actually, the Globus commands are just a friendly interface to the `openssl` toolkit). For further information, please read the manpages for `openssl`, `verify` and `x509` commands, or use the Globus commands with the `help` option. Section 4.2.7 describes some most often used commands.

4.2.7 Working with certificates: examples

Certificate request: the following command creates a key pair for a user or a gatekeeper and prepares a formal certificate request

```
grid-cert-request -int
```

^YKeys and certificates, as well as their locations, can have different names. In the instructions above, the default naming scheme was used. If you would like to use different names, feel free to contact `nordugrid-support@nordugrid.org` for further directions.

Change pass phrase of the certificate: use this command to change the pass phrase (password) of the private key file userkey.pem:

```
grid-change-pass-phrase -file userkey.pem
```

Please note that once you forget the pass phrase, the certificate has to be requested anew, as there is no way to re-generate a password.

Inspect a certificate: to print all the information from the public certificate file usercert.pem, do the following

```
grid-cert-info -file usercert.pem -all
```

In particular, the line starting `Subject:` contains your certificate Subject Name (SN), that has to be communicated to a VO manager or a site administrator in order to get access to the Grid (see Section 5).

Duplicate a certificate with a new pass phrase: using this tool, your private key is encoded with a new pass phrase and stored in the new_userkey.pem file (first it asks for your old pass phrase, then twice for the new).

```
openssl rsa -in userkey.pem -des3 -out new_userkey.pem
```

Verify the certificate: to verify the usercert.pem certificate using the public key of the issuing CA, which is supposed to be located in the specified CApath, do this:

```
openssl verify -CApath /etc/grid-security/certificates/ usercert.pem
```

Dump contents of the certificate: with this command you can display the contents of the usercert.pem certificate

```
openssl x509 -noout -text -in usercert.pem
```

Convert your Grid certificate into a Web one: you can use your Grid certificate to authenticate yourself on the Web via Internet browsers. Before importing your certificate into a browser, you must convert it from the original pemformat to pkcs12 one:

```
openssl pkcs12 -export -in usercert.pem -inkey userkey.pem -out cert.p12
```

Here cert.p12 can be any name you like (preferably with the .p12 extension). This file can be imported into any modern browser and serve as a Web certificate. Use your Grid passphrase to manage it.

Chapter 5

Getting Access to Grid Resources: Virtual Organisations

NB: possession of a Grid certificate, even signed by a legal CA, does not automatically allow you to use any Grid resources!

As it was mentioned above, in order to be able to do such things as copy files over the Grid, or submit Grid jobs, your identity should be mapped to a local account on each resource { be it a computing cluster or a storage facility. As long as this mapping is done, you are authorized to use a resource as any local user.

5.1 NorduGrid Virtual Organisation

To facilitate and automate such mapping for the Nordic Grid users, NorduGrid has set up a collective authorization method, the NorduGrid Virtual Organization (VO),, following practices of other Grid testbeds. This VO maintains a list of people which are authorized to use the Nordic Grid resources. The VO tools provide an automatic method for the sites to easily maintain the "VO member" \$ "local Unix user" mappings. These tools periodically query the VO user database and automatically generate the `grid-map` files following the local policy formulated in the VO-tools configuration file. The automatic mapping does not violate the site autonomy, because the site administrators retain a full control over their systems thanks to the possibility of denying access to "unwished" Grid users in the NorduGrid VO-tools configuration file.

The database of the VO is maintained by the VO managers. Their responsibility is to add, delete or modify user entries.

The NorduGrid VO is limited to the users affiliated with the Nordic organisations. To become a member, you must send a request containing your certificate Subject Name (see Section 4.2.7) to nordugrid-support@nordugrid.org. If you are not a Nordic countries resident, you may be added to the Guests VO.

The NorduGrid VO supports the creation of groups. A group is a subset of the a VO and is maintained by an appointed group manager. The group manager selects members of the group out of the full VO database. With the existence of the user groups, the site administrators can implement group-based mappings, such that all the members of a certain group are mapped to the same local Unix user, in addition to the default user-based mappings.

Technically, the VO database is stored in an LDAP [11] database. For this purpose, a GSI [12] enabled OpenLDAP server is used, providing an entry and attribute level access control, based on the Grid certificates. The database managers, being authenticated and authorized through their certificates, make use of the OpenLDAP command line tools in order to add, delete or modify entries in the VO database. The Nordic Grid sites periodically (4 times a day) run the `nordugridmap` utility in order to query the VO LDAP

server and automatically create/update local user mappings according to a site policy (as defined in a `nordugridmap.conf` configuration file).

5.2 Other Virtual Organisations

Except of the core Nordic VO, NorduGrid maintains a Guests VO, similar in organisation and implementation to the NorduGrid one. Every user willing to try NorduGrid/ARC facilities can be added to the Guests VO upon contacting nordugrid-support@nordugrid.org.

Many other VOs are operating on the Grid, typically consisting of people involved in the same research project. Each such VO has a manager who maintains the database and negotiates resources available for the members. It is recommended for every user to join a VO in order to get access to the Grid.

In case you do not belong to or do not qualify for any existing VO, you always can establish your own VO and be your own manager. You will have to contact the Grid resource owners one by one and negotiate resource allocation with them. Feel free to contact nordugrid-support@nordugrid.org for initial instructions or possible assistance.

Chapter 6

Grid Session

Before starting your first Grid session, check whether the following have been accomplished:

1. You have the ARC client installed (see Chapter 3)
2. You have a valid Grid certificate (see Section 4)
3. You are authorised at at least one Grid site (see Section 5)

6.1 Logging Into The Grid

Access to the Grid resources in the Globus world is made via a so-called proxy { a kind of a temporary token, which you pass to the Grid services, allowing them to act on your behalf.

Initialization of the proxy is done via the standard Globus command:

```
grid-proxy-init
```

This command searches for your public certificate and private key in the default directory (`$HOME/.globus`), and upon a pass phrase confirmation, creates a file containing your Grid proxy in the `/tmp` directory of your computer. The proxy file name typically starts with "x509up_u", which is followed by your UNIX/Linux UID.

Your Globus proxy is public, hence anybody having access to it can impersonate you. To minimize this risk, proxies have limited lifetime. By default, a proxy is valid for 24 hours. This, however, means that if your Grid task will last longer than the proxy validity, it will not be able to finish correctly because of the proxy expiration. Either for this reason, or, on the contrary, if you'd like to have your proxy short-lived, it is possible to create a proxy with a user-defined lifetime:

```
grid-proxy-init -valid 27:45
```

In this example, a proxy will live 27 hours and 45 minutes.

The `grid-proxy-init` command has several options: e.g., you can select a location of the newly generated proxy, or specify another location for your Grid certificate and/or key. For detailed information on these options, use `grid-proxy-init -help`.

If you are using different computers to log in to the Grid, it is strongly advised NOT TO COPY your private key across the systems. Instead, use a dedicated machine to generate a proxy, and then copy the proxy file to another computer, preferably into your `$HOME` directory, and describe the new proxy location in the `X509_USER_PROXY` environment variable:

```
scp /tmp/x509up_u230 another.machine.org:myproxy
ssh another.machine.org
export X509_USER_PROXY=$HOME/myproxy
```

6.1.1 Proxy Handling Tips

To avoid troubles, please always try to make sure that your proxy has a validity period sufficient for your task to come to completion. However, it is not advised to generate proxies with lifetimes of several days.

6.2 First Grid test

ARC comes with a test suite that allows users to quickly test their installation and most of the Grid functionality. The very first test can be performed by issuing

```
ngtest 1
```

This will produce some informative output, and upon a successful test job submission will print out the job handle, or job ID, which may look like:

```
gsiftp://site.it.uni.org:2812/jobs/10308913211503407485
```

This will mean that your test job is sent for execution to the site site.it.uni.org and the output is available via this gsiftp:// URL. gsiftp is the Grid analogue of FTP, and uses your proxy instead of login/password authentication.

To see what is the status of the job, do

```
ngstat gsiftp://site.it.uni.org:2812/jobs/10308913211503407485
```

A typical output will look like:

```
Job gsiftp://site.it.uni.org:2812/jobs/10308913211503407485
Jobname: ngtest-job-1
Status: ACCEPTED
```

You can check what the job sent to the standard output by doing

```
ngcat gsiftp://site.it.uni.org:2812/jobs/10308913211503407485
```

If ngcat displays the wordshello,grid , the first test has completed successfully! You can now clean up by deleting all the job traces:

You can check what the job sent to the standard output by doing

```
ngclean gsiftp://site.it.uni.org:2812/jobs/10308913211503407485
```

For more test options, check

```
ngtest --list
```

All the job manipulation commands (ngstat , ngcat , ngclean etc) can work with a bulk of jobs, with a specific cluster, and otherwise have many other options. Check Section 8 for the complete description.

To learn how to describe and submit your own job, proceed to Section 7.

6.3 Logging Out

Logging out is performed by destruction of the proxy. You can either physically erase the corresponding file, or issue

```
grid-proxy-destroy
```


Chapter 7

Describing Grid Tasks

To describe a task to be submitted to the NorduGrid/ARC resources, a special scripting language is used. It is strongly based on the Resource Specification Language (RSL) developed by the Globus project [13]. RSL allows job options and definitions to be parsed to resource management systems. The ARC architecture requires certain extensions to the RSL. This concerns not only introduction of new attributes, but also differentiation between two levels of the job options specifications:

User-side RSL , i.e., the set of attributes specified by a user in a job-specification file. This file is interpreted by the User Interface (UI) [5], and after the necessary modifications is passed to the Grid Manager (GM) [3]

GM-side RSL , i.e., the set of attributes pre-processed by the UI, and ready to be interpreted by the GM

As a user, you have to know only the user-side part, and utilize it to describe your Grid tasks.

In what follows, the description of the NorduGrid-extended RSL, further denoted as xRSL , is given, using the following notations:

<xxxx>	parameter to be substituted with a corresponding string or a number
[xxxx]	optional parameter
xxx yyy zzz	list of possible values of a parameter
"-	"same as above"

7.1 Task Description Language: xRSL

For a complete description of Globus RSL, see reference [13]. xRSL uses the same syntax conventions, but changes the meaning and interpretation of some attributes.

A Grid task is described by the means of xRSL attributes, which can be either passed via a command-line, or, more conveniently, be collected in a so-called xRSL-file (suggested extension `xrsl`). Such a file contains a plain list of attribute assignment strings (relations) and boolean operands "&" (for AND) and " | " (for OR). Attribute names are case-insensitive.

A relation associates an attribute name with a value:

```
executable="a.out"
```

Here `executable` is an attribute name, and `a.out` is its value. An attribute can have several values (blank-separated list):

```
arguments="abc" "123" "dir/file"
```

or even correspond to pairs of values:

```
inputFiles=("thescript" "http://my.site.org/taskX/script1.sh")
          ("my.idx" $HOME/index/the_index.bin)
          ("thescript" "")
```

In the examples above, some strings are quoted, while some are not. When explicitly quoted, a string may contain any character. However, most literals used in job description (e.g. attribute names themselves, file names etc) don't have to be quoted, if they don't contain special characters .

The special characters are:

```
+ & | ( ) = < > ! " ' ^ # $
```

To quote a string containing special characters, you can use pairs of either single or double quotes. If your string, however, contains both such characters, you can define any character as an own delimiter, by preceding it with the "carat" (^) character: jobName=^*My "good" job^* makes use of a carat-escaped asterisk as a delimiter.

Typically, an xRSL job description starts with an ampersand ("&") , to indicate implicit conjunction (boolean ANDstyle) of all the attribute relations, enclosed in parentheses:

```
&(attribute1="value1")(attribute2="value2")...
```

Whenever a disjunct -request (booleanORstyle) of two or more attributes is needed, the following construction can be used:

```
(|(attribute="value1")(attribute="value2")...)
```

In expressions, the following operands are allowed:

```
= != > < >= <=
```

Commented lines should start with "("* and be closed with "*)" :

```
(*attribute="value1"*)
```

Comments can not be nested.

Multiple job descriptions in one file are realized via a standard Globus RSL multi-request operand "+", which should precede the multiple job descriptions:

```
+(&(...))(&...)(&...))
```

The xRSL attributes can be written in a single string, or split in lines arbitrary; blank spaces between (attribute="value") pairs and inside relations are ignored.

7.1.1 URLs

File locations in ARC can be specified both as local file names, and as Internet standardUniform Resource Locators (URL). However, there are some additional options, used by the Grid Manager. Detailed information is maintained in the ARC URL documentation [14].

The following transfer protocols and metadata servers are supported:

- ftp { ordinary File Transfer Protocol (FTP)}

- gsiftp { GridFTP, the Globus-enhanced FTP}
- http { ordinary Hyper-Text Transfer Protocol (HTTP)}
- https { HTTP with SSL v3}
- httpg { HTTP with Globus GSI}
- ldap { ordinary Lightweight Data Access Protocol (LDAP) [11]}
- rc { Globus Replica Catalog (RC) [15]}
- rls { Globus/EDG Replica Location Service (RLS) [16]}
- se { ARC Smart Storage Element service [17]}
- file { local file access}

An URL can be used in a standard form, i.e.

```
<protocol>://host[:port]/<file>
```

Or, to enhance the performance, it can have additional options:

```
<protocol>://host[:port][;option[;option[...]]]/<file>
```

For a metadata service URL, construction is the following:

```
rc://[location|[location[...]]@]<host>[:port]/<DN>/<lfn>
rls://[url|[url[...]]@]<host>[:port]/<lfn>
```

For the Smart Storage Element service, the syntax is

```
se://host[:port][;options]/path[?file_id]
```

Here the URL components are:

location	<location_name_in_RC>[;option[;option[...]]]
host[:port]	IP address of a server
DN	Distinguished Name (as in LDAP) of an RC collection
lfn	Logical File Name
url	URL of the file as registered in RLS
file	local to the host file name with a full path

The following options are supported:

threads=<number>	specifies number of parallel streams to be used by GridFTP or HTTP(s,g); default value is 1, maximal value is 20
cache=yes no	indicates whether the GM should cache the file; default is yes for transfers to local destinations
readonly=yes no	for transfers to local destinations (e.g., cache), specifies whether the file should be read-only (unmodifiable); default is yes
secure=yes no	indicates whether the GridFTP data channel should be encrypted; default is no
blocksize=<number>	specifies size of chunks/blocks/buffers used in GridFTP or HTTP(s,g) transactions; default is protocol dependent
checksum=cksum md5	specifies the algorithm for checksum to be computed (e.g. provided to the indexing server)

Local files are referred by specifying either location relative to the job submission working directory, or by an absolute path (the one that starts with "/"), preceded with a file:// prefix.

Examples of URLs are:

```
http://grid.domain.org/dir/script.sh
gsiftp://grid.domain.org:2811;threads=10/dir/input_12378.dat
ldap://grid.domain.org:389/lc=collection1,rc=Nordugrid,dc=nordugrid,dc=org
rc://grid.domain.org/lc=collection1,rc=Nordugrid,dc=nordugrid,dc=org/zebra/f1.zebra
file:///home/auser/griddir/steer.cra
```

7.1.2 Task Description: Attributes

A task is typically described by a binary executable to be processed by a computer, parameters passed to that executable, and requirements which must be met by a system to be able to execute the task. For example, a simple "Hello World" task description would specify /bin/echo as the executable and "Hello World" as the argument. In xRSL language it will look as follows:

```
&(executable="/bin/echo")(arguments="Hello World")
```

You can actually use this description from the command line, i.e., your first Grid job should be submitted as:

```
ngsub &(executable="/bin/echo")(arguments="Hello World")
```

In a more complex case, a binary executable may have to be downloaded from a remote location, process an input data and create an output file. This task specification will have to include locations of all three files: executable, input and output, and perhaps few other requirements, e.g., the necessary disk space and an e-mail address to which the notification of the task completion should be sent. Such an xRSL file may be written like the following:

```
&
(executable="myprog")
(inputFiles=
 ("myprog" "http://www.myserver.org/myfiles/myprog")
 ("myinput" "gsiftp://www.mystorage.org/data/file007.dat")
)
(outputFiles=
 ("myoutput" "gsiftp://www.mystorage.org/results/file007.res")
)
(disk=1000)
(notify="e myname@mydomain.org")
```

As you can see, the xRSL attribute names are largely self-explanatory. xRSL handles most possible task description attributes, and the next Section contains the comprehensive list of them, complete with usage examples.

Attributes

The following attributes can be specified in a user's xRSL file or string for job description.

executable

Usage: (executable=<string>
Example: (executable=local_to_job.exe)

The executable to be submitted as the main task to a Local Resource Management System (LRMS).

string le name (including path), local to the computing element (CE)

The executable is a le that has to be executed as the main process of the task. It could be either a pre-compiled binary, or a script. Users may submit their own executables, or use the ones known to be already installed on the remote system (CE).

If an executable is provided by the user and has to be transferred from the submission node, it has to be speci ed in the inputFiles list, otherwise it will be added to that list by the UI.

If the le name starts with a leading slash (" / "), it is considered to be the full path to the executable at a CE ; otherwise the location of the le is relative to the session directory (where job input and les are stored). If the attribute's value starts with an environment variable (" \$... "), the value of this variable is resolved locally, but if it is enclosed in double quotes, it will be resolved at the remote computing element: (executable=\$ROOT_DIR/myprog.exe) { \$ROOT_DIR is resolved locally (will cause errors if the path does not exist at the execution machine)
(executable="\$ROOT_DIR/myprog.exe") { \$ROOT_DIR will be resolved remotely

For more discussion on the practical use of this attribute, see Section 7.2.2.

arguments

Usage: (arguments=<string> [string] ...)

Example: (arguments="10000" \$(ATLAS)/input.dat)

List of the arguments for the executable.

string an argument

inputFiles

Usage: (inputFiles=<filename> <location> ...)

Example: (inputFiles=("local_to_job" "gsiftp://grid.quark.lu.se/scratch/remote_one")
 ("local_to_job.dat" "/scratch/local_to_me.dat")
 ("same_name_as_in_my_current_dir" ""))

List of les to be copied to the computing element before the execution.

filename le name, local to the computing element and always relative to the session directory(job's current working directory on a remote CE)

location location of the le: URL (see Section 7.1.1), or a path, local to the submission node. If void (" ", use the quotes!), the input le is taken from the submission directory.

If the list does not contain the standard input le (as speci ed by stdin) and/or the executable le (as speci ed by executable if the given name), the UI appends these les to the list.

Please note that the inputFiles attribute is not meant to operate with directories: you must specify a pair ("<local_to_job>" "[local_to_me]") for each le.

executables

Usage: (executables=<string> [string] ...)

Example: (executables=myscript.sh myjob.exe)

List of files from the inputFiles set, which will be given executable permissions.

string file name, local to the computing element and relative to the session directory

If the executable file (as specified in executable and is relative to the session directory) is not listed, it will be added to the list by the UI.

cache

Usage: (cache=yes|no)

Example: (cache=yes)

Specifies whether input files specified in the inputFiles should be placed by default in the cache or not. This does not affect files described by the executable , which will be placed in the session directory always.

If not specified, default value is "yes".

outputFiles

Usage: (outputFiles=(<string> <URL>) ...)

Example: (outputFiles=("local_to_job.dat" "gsiftp://grid.uio.no/storage/stored.dat")

("local_to_job.res" "rc://grid.fi.uib.no/group1/stored_and_registered.res")

("local_to_job_dir/" ""))

List of files to be retrieved by the user or uploaded by the GM and registered in a Replica Catalog or RLS.

string file name, local to the Computing Element (CE). If this string ends with a backslash \ and <URL> is empty, the entire directory is being kept at the execution site. If however this string ends with a backslash \ but the <URL> starts with gsiftp or ftp , the whole directory is transferred to the destination.

URL URL for the remote file (see Section 7.1.1); if void ("", use the quotes!), the file is kept for manual retrieval. Note that this can not be a local file:// URL.

Using a RC pseudo-URL (see Section 7.1.1), you should make sure that the collection location (see Appendix 9.3) is already defined in the RC. If more than one such location is specified, only those found in the RC for this collection will be used. GM will store output files in one location only: the first randomly picked location that exists. If no locations are specified, all found in the RC for this collection will be tried.

If in a RC pseudo-URL the component host[:port]/DN is not specified, the one given in the replicaCollection attribute is used.

If the list does not contain standard output and/or standard error files (as specified by stdout/stderr), the UI appends these file names to the list. If the <URL> is not specified (void, "", use the quotes!), files will be downloaded by the user via the UI.

A convenient way to keep the entire job directory at the remote site for a manual retrieval is to specify (outputfiles=("/" "")) .

Please note that the outputFiles attribute is not meant to operate with directories: you must specify a pair ("<local_to_job>" "[local_to_me]") for each file. One exception is when you want to preserve an

entire directory at the remote computer for later manual download via ngget. In that case, simply add the trailing backslash "/" at the end of the remote directory name. You can not upload a directory to a URL location, only to your local disk.

cpuTime

Usage: (cpuTime=<time>)

Example: (cpuTime=240)

Maximal CPU time request for the job.

time time (minutes)

If only number is specified, the time is assumed to be minutes. Otherwise, a free format is accepted, i.e., any of the following will be interpreted properly (make sure to enclose such strings in quotes!):

"1 week"
"3 days"
"2 days, 12 hours"
"1 hour, 30 minutes"
"36 hours"
"9 days"
"240 minutes"

This attribute should be used to direct the job to a system with sufficient CPU resources, typically, a batch queue with the sufficient upper time limit. Jobs exceeding this maximum most likely will be terminated by remote systems! If thecpuTime is not specified, the limit is not set and jobs can run as long as the system settings allow (note that in this case you can not avoid queues with too short time limits).

gridTime

Usage: (gridTime=<time>)

Example: (gridTime="2 h")

Maximal CPU time request for the job scaled to the 2.8 GHz Intel® Pentium® 4 processor.

time time (minutes)

The attribute is completely analogous to cpuTime, except that it will be recalculated to the actual CPU time request for each queue, depending on the published processor clock speed.

memory

Usage: (memory=<integer>)

Example: (memory>=500)

Memory required for the job.

Just like cpuTime, this attribute should be used to direct a job to a resource with a sufficient capacity. Jobs exceeding this memory limit will most likely be terminated by the remote system.

integer size (Mbytes)

disk

Usage: (disk=<integer>)

Example: (disk=500)

Disk space required for the job.

integer disk space ,Mbytes

This attribute is used at the job submission time to find a system with sufficient disk space. However, it does not guarantee that this space will be available at the end of the job, as most known systems do not allow for disk space allocation. Eventually, a remote system can terminate a job that exceeds the requested disk space.

runTimeEnvironment

Usage: (runTimeEnvironment=<string>)

Example: (runTimeEnvironment=Atlas-1.1.0)

Required runtime environment

string environment name

The site to submit the job to will be chosen by the UI among those advertising specified runtime environments. Before starting the job, the GM will set up environment variables and paths according to those requested.

To request several environments, repeat the attribute string:

(runTimeEnvironment=ENV1)(runTimeEnvironment=ENV2) etc. To make a disjunct-request, use a boolean expression:

((runTimeEnvironment=env1)(runTimeEnvironment=env2)) .

Runtime environment string interpretation is case-insensitive. If a runtime environment string consists of a name and a version number, a partial specification is possible: it is sufficient to request only the name.

Use the ">=" operator to request a version "equal or higher".

middleware

Usage: (middleware=<string>)

Example: (middleware=NorduGrid-0.3.99)

Required middleware.

string Grid middleware name

The site to submit the job to will be chosen by the UI among those advertising specified middleware. Usage is identical to that of the runTimeEnvironment. Use the ">=" operator to request a version "equal or higher". The request (middleware=nordugrid) defaults to (middleware>=nordugrid-0.0.0.0) .

stdin

Usage: (stdin=<string>)

Example: (stdin=myinput.dat)

The standard input ie.

string le name, local to the computing element

The standard input le should be listed in the inputFiles attribute; otherwise it will be forced to that list by the UI.

stdout

Usage: (stdout=<string>)

Example: (stdout=myoutput.txt)

The standard output ie.

string le name, local to the computing element and relative to the session directory.

The standard output le should be listed in the outputFiles attribute; otherwise it will be forced to that list by the UI. If the standard output is not defined, the UI assigns a name.

stderr

Usage: (stderr=<string>)

Example: (stderr=myjob.err)

The standard error ie.

string le name, local to the computing element and relative to the session directory.

The standard error le should be listed as an outputFiles attribute; otherwise it will be forced to that list by the UI. If the standard error is not defined, the UI assigns a name.

join

Usage: (join=yes|no)

Example: (join=yes)

If "yes", stderr and stdout les are joined into stdout . The default is no.

gmlog

Usage: (gmlog=<string>)

Example: (gmlog=myjob.log)

A name of the directory containing grid-specific diagnostics per job.

string a directory, local to the computing element and relative to the session directory

This directory is kept in the session directory to be available for retrieval (UI forces it to the list if outputFiles)

jobName

Usage: (jobName=<string>)

Example: (jobName=MyJob)

User-specified job name.

string job name

This name is meant for convenience of the user. It can be used to select the job while using the UI. It is also available through the Information System.

ftpThreads

Usage: (ftpThreads=<integer>)

Example: (ftpThreads=4)

Defines how many parallel streams will be used by the GM during file transfer, if the specified protocol supports parallel streams.

integer a number from 1 to 10

If not specified, parallelism is not used.

acl

Available in ARC v0.5.12 and higher

Usage: (acl=<xml>)

Example: (acl=<?xml version=""1.0""?>

```
<gACL version=""0.0.1""><entry><any-user></any-user>
<allow><write/><read/><list/><admin/></allow></entry></gACL>")
```

Makes use of GACL [18] rules to list users who are allowed to access and control job in addition to job's owner. Access and control levels are specified per user. any-user tag refers to any user authorized at the execution cluster. To get more information about GACL please refer to <http://www.gridsite.org>.

xml a GACL-compliant XML string defining access control list

Following job control levels can be specified via acl :

write {	allows to modify contents of job data (job directory) and control job flow (cancel, clean, etc.)
read {	allows to read content of job data (contents of job directory)
list {	allows to list files available for the job (contents of job directory)
admin {	allows to do everything { full equivalence to job ownership}

cluster

Usage: (cluster=<string>)

Example: (cluster=nbi)

The name of the execution cluster.

string known cluster name, or a substring of it

Use this attribute to explicitly force job submission to a cluster, or to avoid such. The job will not be submitted if the cluster does not satisfy other requirements of your job. Disjunct-requests of the kind `(|(cluster=clus1)(cluster=clus2))` are supported. To exclude a cluster, use `(cluster!=clus3)`.

queue

Usage: `(queue=<string>)`

Example: `(queue=pclong)`

The name of the remote batch queue.

string known queue name

Use this attribute to explicitly force job submission to a queue.

startTime

Usage: `(startTime=<time>)`

Example: `(startTime="2002-05-25 21:30")`

Time to start job execution at a worker node (CE).

time time string, YYYY-MM-DD hh:mm:ss

Unless you have computing nodes pre-allocated by some other means, this does not guarantee that the job will actually start running at the specified time; however it guarantees that it will not be launched before.

lifeTime

Usage: `(lifeTime=<time>)`

Example: `(lifeTime=60)`

Maximal time to keep job files (the session directory) on the gatekeeper upon job completion.

time time (days)

Typical life time is 1 day (24 hours). Specified life time can not exceed local settings.

notify

Usage: `(notify=<string> [string] ...)`

Example: `(notify="be your.name@your.domain.com")`

Request e-mail notifications on job status change.

string string of the format: `[b][q][f][e][c] user1@domain1 [user2@domain2] ...`

here tags indicating the job status are:

`b` { begin (PREPARING)

`q` { queued (INLRMS)

`f` { finalizing (FINISHING)

`e` { end (FINISHED)

`c` { cancellation (CANCELED)

`d` { deleted (DELETED)

No more than 3 e-mail addresses per status change are accepted.

replicaCollection

Usage: (replicaCollection=<URL>)

Example: (replicaCollection="ldap://grid.uio.no:389/lc=TestCollection,
rc=NorduGrid,nordugrid,dc=org")

Location of a logical collection in the Replica Catalog.

URL LDAP directory specified as an URL (ldap://host[:port]/dn)

rerun

Usage: (rerun=<integer>)

Example: (rerun=2)

Number of reruns (if a system failure occurs).

integer an integer number

If not specified, the default is 0. Default maximal allowed value is 2.

architecture

Usage: (architecture=<string>)

Example: (architecture=i686)

Request a specific architecture.

string architecture (e.g., as produced by uname -a)

nodeAccess

Usage: (nodeAccess=inbound|outbound)

Example: (nodeAccess=inbound)

Request cluster nodes with inbound or outbound IP connectivity. If both are needed, a conjunct request should be specified.

dryRun

Usage: (dryRun=yes|no)

Example: (dryRun=yes)

If "yes", do dry-run: RSL is parsed, resource matching is performed and job is submitted, but it does not go further than ACCEPTED state. Use for xRSL validation and connection test.

rsl_substitution

Usage: (rsl_substitution=(<string1> <string2>))

Example: (rsl_substitution=(ATLAS /opt/atlas))

Substitutes <string2> with <string1> for internal RSL use.

string1 new internal RSL variable

string2 any string, e.g., existing combination of variables or a path

Use this attribute to simplify xRSL editing. Only one pair per substitution is allowed. To request several substitution, concatenate such requests. Bear in mind that substitution must be done prior to actual use of a new variable string1 .

environment

Usage: (environment=(<VAR> <string>) [<VAR> <string>] ...)

Example: (environment=(ATLSRC /opt/atlas/src)
 (ALISRC /opt/alice/src))

Defines execution shell environment variables.

VAR new variable name

string any string, e.g., existing combination of variables or a path

Use this to define variables at an execution site.

count

Usage: (count=<integer>)

Example: (count=4)

Specifies number of sub-jobs to be submitted for parallel tasks.

integer a number (default is 1)

jobreport

Usage: (jobreport=<URL>)

Example: (jobreport="https://grid.uio.no:8001/logger")

Specifies an URL for a logging service to send reports about job to. The default is set up in the cluster configuration.

URL URL

It is up to a user to make sure the requested logging service accepts reports from the set of clusters she intends to use.

7.2 Examples

In this section you can find some examples of xRSL job description.

While the xRSL specifications can be passed to ngsu (see Section 8.1.1) as a single string on the command line, it is much more convenient to create a file with an arbitrary name, containing the xRSL string, and pass this file to ngsu, e.g. `ngsu -f filename`. The format of the file is not important (see Section 7.1), as long as it does not contain Microsoft/DOS linefeeds.

Attribute names are case-insensitive, that is, you can use `CPUTime` or `cputime` interchangeably. The only attribute which must be specified is `executable`, others can be added by the user depending on the needs, in no particular order.

7.2.1 Hello World

The simplest way to say "Hello World" is to assume that any cluster on the Grid has the Unix `echo` executable in the `/bin/` directory. In most cases it will work, so the following xRSL file can be composed:

```
&
(* main executable of the task *)
(executable=/bin/echo)
(* arguments for the main executable *)
(arguments="Hello World" )
(* standard output will be redirected to this file: *)
(stdout="hello.txt")
(* standard error will be redirected to this file: *)
(stderr="hello.err")
(* Grid Manager auxilliary logs will be stored in this directory: *)
(gmlog="gridlog")
(* give job a distinct name for easy monitoring *)
(jobname="My Hello Grid")
(* instruct cluster that your job should be placed in a queue with *)
(* the sufficient time limit for the job to get completed *)
(cputime=5)
(* chose only those clusters which have a proper ARC installation *)
(middleware>="nordugrid-0.3.24")
```

In this example, strictly speaking, only the `executable` and `arguments` are needed to describe the task. However, as the job will be executed in batch (like everything on the Grid), you will never see the message "Hello World" on your screen. Instead, you should instruct the Grid Manager to capture the standard output to a file, which you can later retrieve. This is how `stdout` attribute appears in the xRSL. It may happen that something goes wrong (e.g. `echo` is located in `/usr/bin/`), and an error will be produced. To be able to analyze the errors, users are advised to use `stderr` and `gmlog` attributes, which instruct the Grid Manager where to store possible error messages.

The job name is a convenient way to identify the task. Although every job is assigned a unique Grid ID, this ID is far from intuitive. As soon as you plan to submit more than one job, you should think of a set of good names for them { this will save you a lot of time. The attribute `jobname` should be used to associate every job with a user-defined name.

Since the Grid will parse the task to a batch system, it is always a good idea to specify the needed CPU time. Some clusters are known to have the default execution time set to 0, which effectively kills any job. The `cputime` attribute takes the time value (in minutes) and passes it to the Grid Manager. Do not overestimate the time, as your job may end up in a "long" queue, and wait an unnecessarily long time before being executed.

The last attribute in this example is `middleware`. This may be quite helpful in an environment where some clusters run untested versions of the middleware. When you are not sure what to specify, `d ngsu b -v`, and use the printed version number.

7.2.2 An Own Executable

In the previous Section, the `executable` attribute had the value `/bin/echo`.

A very important thing to understand is that the Grid Manager always expects the file specified by the executable attribute to be at the execution machine, not the user's machine.

This means that if a user wants to submit a job executing an own tool say_hello and specifies in the xRSL text (executable=say_hello) , the Grid Manager will attempt to execute a file say_hello in the temporary session directory, local to the job. Naturally, this file will not appear there by magic. Instead, the User Interface, prior to job submission, will interpret such a request as if a user has the executable file say_hello in the current directory at the submission machine, and will upload the file to the destination. Absence of the leading slash () makes the User Interface assume that the file in question resides locally in the path relative to the current directory.

So far, so good, but what if the executable resides not in the current directory, but elsewhere on your computer, or, even better, at a remote location? If this is the case, you have to instruct the User Interface how to get the file by using the inputfiles attribute:

```
&
(* main executable of the task *)
(executable=say_hello)
(* arguments for the main executable *)
(arguments="Hello again" )
(* where does the executable reside *)
(inputfiles=(say_hello file:///home/john/bin/say_hello))
(* standard output will be redirected to this file: *)
(stdout="hello.txt")
```

The inputfiles attribute instructs the User Interface to copy the file from /home/john/bin/say_hello on your local computer to say_hello in the session directory at the execution machine. If the file resides at an GridFTP or HTTP server, use gsiftp:// or http:// respectively instead of file:// to specify the protocol.

7.2.3 Many Executables

The Grid Manager is capable of managing more than one executable file, and xRSL provides means for users to specify such files. A typical example is when a user script prepares and starts a pre-compiled binary. In this case, both files must be given executable permissions, but only the "main" script should be submitted for execution by the local system. To make this working, users must list all the files which need executable permissions in the executables attribute, as shown below:

```
&
(executable=run.sh)
(arguments=1664900 100000)
(executables=ffungen)
(inputFiles=(ffungen ""))
(outputFiles=(ffun.hbook gsiftp://hathi.hep.lu.se/test/flong/flong1.hbook))
(jobName=flong1)
(stdout=flong1.out)
(join=yes)
(notify="e oxana.smirnova@hep.lu.se")
(ftpThreads=6)
(middleware="NorduGrid-0.4.1")
```


Chapter 8

Job Management

8.1 Working with jobs

Job submission on the NorduGrid/ARC is made via the User Interface (UI) part of the ARC [5]. The UI provides a set of command line tools that submit jobs, trace their status, kill jobs, retrieve job output, and perform some other related functions. For a complete description, please refer to the UI manual [5].

8.1.1 Submit A Job

The `ngsub` command is the most essential one, as it is used for submitting jobs to the Grid resources. The jobs are described using the extended resource description language (xRSL), see Chapter 7. . This description is matched by `ngsub` to the information collected from the Grid, and the best matching site is being selected for job submission. The job description is then being forwarded to that site, in order to be submitted to the Local Resource Management System (LRMS), which can be, e.g., PBS or Condor or SGE etc.

ngsub [options] [xrs]

Options:

-c, -cluster	[-]	textemname	explicitly select or reject a specific cluster
-C, -clustlist	[-]	textem lename	list of clusters to select or reject
-g, -giisurl		url	URL of a central Information System server
-G, -giislist		lename	list of GIIS URLs
-f, -file		lename	xrsl file describing the job to be submitted
-o, -joblist		lename	file where the job IDs will be stored
	-dryrun		add dryrun option to the xRSL
	-dumpxrsl		do not submit { dump transformed xRSL to stdout
-t, -timeout		time	timeout for queries (default 40 sec)
-d, -debug		debuglevel	0 = none, 1 = some, 2 = more, 3 = a lot
-x, -anonymous			use anonymous bind for queries
-X, -gsi			use GSI-GSSAPI bind for queries
-v, -version			print version information
-h, -help			print this help

Arguments:

xrsl ... xrsl strings describing the jobs to be submitted

A simple "Hello World" job would look like:

```
ngsub '&(executable="/bin/echo")(arguments="Hello World")(stdout="hello.txt")'
```

Use single quotes for the xRSL string and double quotes for attribute values.

Such a request would submit the task to any available cluster, as there are no specific requirements specified. The job will be executed in a batch mode, and the standard output will be written to a file hello.txt at the execution cluster. You will have to retrieve this file manually, using the ngget command (Section 8.1.4).

If a submission was successful, the job ID will be printed byngsub.

If a job is successfully submitted, a job identifier (job ID) is printed to standard output. This job ID uniquely identifies the job while it is being executed. A typical job ID looks like follows:

```
gsiftp://site.it.uni.org:2812/jobs/10308913211503407485
```

You should use this as a handle to refer to the job when doing other job manipulations, such as querying job status (ngstat , Section 8.1.2), killing it (ngkill , Section 8.1.5), re-submitting (ngresub, Section 8.1.6), or retrieving the result (ngget, Section 8.1.4).

Every job ID is a valid URL for the job session directory. You can always use it to access the files related to the job, by using data management tools (see Section 9.1 and Chapter 9).

The job description in the xRSL format can be given either as an argument on the command line, as in the example above, or can be read from a file by using the -f option. Several jobs can be requested at the same time by giving more than one xRSL argument, or by repeating the -f option. It is also possible to mix xRSL arguments and -f options in the samengsub command.

To validate your xRSL script without actually submitting a job, use the -dryrun option: it will capture possible syntax or other errors, but will instruct the GM not to submit the job for execution.

If the -o option is given, the job identifier is also written to a file with the specified filename. This file can later be used with the corresponding -i option of the other job manipulating User Interface commands.

```
ngsub -o my_jobid_list -f myjob.xrsl ngkill -i my_jobid_list
```

The -c option can be used to force a job to be submitted to a particular cluster, or to reject submission to a cluster. The matching is done by case insensitive substring match to the cluster name (i.e. hostname) or to the cluster alias name, as defined in the Information System. The -c option can be repeated several times, for example:

```
ngsub -c grid.nbi.dk -c grid.tsl.uu.se -f myjob.xrsl
```

This will submit a job to either grid.nbi.dk or grid.tsl.uu.se . For convenience, you may list the sites in a file, and use the -C option to refer to the whole list:

```
ngsub -C preferred_sites -f myjob.xrsl
```

If a cluster name or file name is preceded with a minus sign (" - "), this cluster (or the list) will be avoided during the submission. This gives a possibility to blacklist unwanted sites:

```
ngsub -C -blacklist -f myjob.xrsl
```

The nbsub command locates the available clusters by querying the Information System. By default, a list of the ARC Information System servers is distributed with the middleware and is stored in \$NORDUGRID_LOCATION/etc/giislist . However, a user is free to choose another set of servers, either by storing them in \$HOME/.nggiislist file, or by specifying them via the -g option:

```
ngsub -g ldap://hostname[:port]/DN -f myjob.xrsl
```

You may prefer to store the list of GIIS servers in a file other than the default one, and use the-G option to instruct ngsub to contact those servers instead:

```
ngsub -G my_GIIS_list -f myjob.xrsl
```

If you would like to trace the process of resource discovery and requirements matching, a very useful option is -d . The following command:

```
ngsub -d 2 -f myjob.xrsl
```

will print out the steps taken by the User Interface to find the best cluster satisfying your job requirements.

It often happens that some sites thatngsub has to contact are slow to answer, or are down altogether. This will not prevent you from submitting a job, but will slow down the submission. To speed it up, you may want to specify a shorter timeout (default is 40 seconds) with the-t option:

```
ngsub -t 5 -f myjob.xrsl
```

8.1.2 Querying Job Status

The ngstat command is used for obtaining the status of jobs that have been submitted to NorduGrid/ARC.

```
ngstat [options] [job ...]
```

Options:

-a, -all		all jobs
-i, -joblist	filename	file containing a list of jobids
-c, -clusters		show information about clusters
-C, -clustlist [-]	textfile filename	list of clusters to select or reject
-s, -status	statusstr	only select jobs whose status isstatusstr
-g, -giisurl	url	URL of a central Information System server
-G, -giislist	filename	list of GIIS URLs
-q, -queues		show information about clusters and queues
-l, -long		long format (extended information)
-t, -timeout	time	timeout for queries (default 40 sec)
-d, -debug	debuglevel	0 = none, 1 = some, 2 = more, 3 = a lot
-x, -anonymous		use anonymous bind for queries
-X, -gsi		use GSI-GSSAPI bind for queries
-v, -version		print version information
-h, -help		print this help

Arguments:

job ...	list of job IDs and/or jobnames
---------	---------------------------------

Typically, one should usengstat with the job ID as printed by ngsub. If the job IDs were saved to file filename , ngstat -i filename will give the status of all the jobs listed in the file. Many users prefer to usengstat -a to display the status of all the jobs they ever submitted . To check the status of jobs being on a particular stage of execution (e.g., only running jobs), use thes option:

Or, more precisely, since they last ran ngclean or ngsync

```
ngstat -s "INLRMS: R"
```

The list of basic job status codes:

ACCEPTED	job submitted but not yet processed
PREPARING	input files are being retrieved
SUBMITTING	interaction with LRMS ongoing
INLRMS: Q	job is queued by LRMS
INLRMS: R	job is running
FINISHING	output files are being transferred
FINISHED	job is finished
CANCELING	job is being cancelled
DELETED	job is removed due to expiration time

Most of the states can be prepended with the PENDING: message, if the job can not move from the state: for example, if the limit of jobs in the next state is reached. That is, PENDING:PREPARING means that the job exited the PREPARING state and is pending transfer to the next state, SUBMITTING. The FINISHED state may be followed by an error message if the job failed, starting with '! FAILURE' string.

The jobs are normally removed from the clusters if they were not retrieved within 24 hours after job end.

A standard output produced by ngstat is rather short, informing the user only about the job status. Use ngstat -l to receive the complete job information as stored in the system.

8.1.3 Capturing Job Output

It is often useful to monitor the job progress by checking what it prints on the standard output or error. The command ncat assists here, extracting the corresponding information from the execution cluster and pasting it on the user's screen. It works both for running tasks and for the finished ones. This allows a user to check the output of the finished task without actually retrieving it.

```
ncat [options] [job ...]
```

Options:

-a, -all		all jobs
-i, -joblist	filename	file containing a list of job IDs
-c, -clusters		show information about clusters
-C, -clustlist	[-] textfile filename	list of clusters to select or reject
-s, -status	statusstr	only select jobs whose status is \$statusstr
-o, -stdout		show the stdout of the job (default)
-e, -stderr		show the stderr of the job
-l, -gridlog		show the grid error log of the job
-t, -timeout	time	timeout for queries (default 40 sec)
-d, -debug	debuglevel	0 = none, 1 = some, 2 = more, 3 = a lot
-x, -anonymous		use anonymous bind for queries
-X, -gsi		use GSI-GSSAPI bind for queries
-v, -version		print version information
-h, -help		print this help

Arguments:

job ...	list of job IDs and/or jobnames
---------	---------------------------------

As one can see ngcat can capture not only the standard output (-o option), but also the standard error (-e option) and the errors reported by the Grid Manager (-l option).

8.1.4 Retrieving Job Output

To retrieve the results of a finished job, the ngget command should be used. It will download the files specified by the outputfiles xRSL attribute (see Section 7.1.2) to the user's computer.

```
ngget [options] [job ...]
```

Options:

-a, -all		all jobs
-i, -joblist	lename	file containing a list of jobids
-c, -cluster	[-] textemname	explicitly select or reject a specific cluster
-C, -clustlist	[-] textem lename	list of clusters to select or reject
-s, -status	statusstr	only select jobs whose status is statusstr
-dir	dirname	download directory (the job directory will be created in this directory)
-j, -usejobname		use the jobname instead of the digital ID as the job directory name
-keep		keep files on gatekeeper (do not clean)
-t, -timeout	time	timeout for queries (default 40 sec)
-d, -debug	debuglevel	0 = none, 1 = some, 2 = more, 3 = a lot
-x, -anonymous		use anonymous bind for queries
-X, -gsi		use GSI-GSSAPI bind for queries
-v, -version		print version information
-h, -help		print this help
Arguments:		
job ...		list of job IDs and/or jobnames

The files to be retrieved by ngget should be described by the xRSL as follows:

```
(output files=( file1 "")( file2 "") )
```

That is, while the filenames must be listed, no output destination should be requested. This will tell the Grid Manager not to erase the files after job's end and allow the User Interface to download them.

Files specified as stdout, stderr and the gmlog directory are always treated as outputfiles by the UI, which means you don't have to add them to the output files list.

By default, ngget will create in your current directory a new folder, by the same name as the remote session directory (typically, a numerical string). This new directory will contain all the files listed for download in your xRSL. If you would like to store the files in another location, use the -dir option. The option -j will assign your job name to the local directory with the output files (be careful not to call all the jobs same name when using this option).

It is handy to set a default download directory location in your ~/.ngrc file:

```
sample .ngrc file
NGDOWNLOAD=/tmp
UI does not clean up such download areas, so please take care of doing this yourself.
```

When the job result is retrieved, the session directory is erased from the execution machine, and the job ID is removed from your list of submitted jobs. If you however want to keep the job for a while, use the `-k` option.

Beware that the job results will be removed by the Grid Manager at the execution machine 24 hours after job completion independently of whether you retrieved the results or not.

8.1.5 Killing Jobs

It happens that a user may wish to cancel a job. This is done by using the `ngkill` command. A job can be killed practically on any stage of processing through the Grid.

`ngkill [options] [job ...]`

Options:

-a, -all		all jobs
-i, -joblist	lename	le containing a list of jobids
-c, -clusters		show information about clusters
-C, -clustlist	[-] textem lename	list of clusters to select or reject
-s, -status	statusstr	only select jobs whose status is\$statusstr
	-keep	keep les on gatekeeper (do not clean)
-t, -timeout	time	timeout for queries (default 40 sec)
-d, -debug	debuglevel	0 = none, 1 = some, 2 = more, 3 = a lot
-x, -anonymous		use anonymous bind for queries
-X, -gsi		use GSI-GSSAPI bind for queries
-v, -version		print version information
-h, -help		print this help

Arguments:

job ... list of job IDs and/or jobnames

Job cancellation is an asynchronous process, such that it may take a few minutes before the job is actually cancelled.

8.1.6 Re-submitting Jobs

Quite often it happens that a user would like to re-submit a job, but has difficulties recovering the original job description xRSL le. This happens when xRSL les are created by scripts on- y, and matching of xRSL to the job ID is not straightforward. The utility called `ngresub` helps in such situations, allowing users to resubmit jobs known only by their IDs.

Only jobs where the gmlog attribute was given in the xRSL description (see Section 7.1.2) can be resubmitted.

`ngresub [options] [job ...]`

Options:

-a, -all		all jobs
-i, -joblist	lename	le containing a list of jobids
-c, -cluster	[-] textemname	explicitly select or reject a specific cluster
-C, -clustlist	[-] textem lename	list of clusters to select or reject
-s, -status	statusstr	only select jobs whose status is statusstr
-k, -kluster	[-] textemname	explicitly select or reject a specific cluster as re-submission target
-K, -Klustlist	[-] textem lename	list of clusters to select or reject as re-submission target
-g, -giisurl	url	URL of a central Information System server
-G, -giislist	lename	list of GIIS URLs
-o, -joblist	lename	le where the job IDs will be stored
-dryrun		add dryrun option to the xRSL
-dumpxrsi		do not submit { dump transformed xRSL to stdout
-keep		keep les on gatekeeper (do not clean)
-t, -timeout	time	timeout for queries (default 40 sec)
-d, -debug	debuglevel	0 = none, 1 = some, 2 = more, 3 = a lot
-x, -anonymous		use anonymous bind for queries
-X, -gsi		use GSI-GSSAPI bind for queries
-v, -version		print version information
-h, -help		print this help
Arguments:		
job ...		list of job IDs and/or jobnames

If the original job description contained input le locations specified as relative paths (non-URLs), the command must be issued in the same directory as the original `ngsub` instruction.

It is important to distinguish `-c` and `-k` options (as well as `-C` and `-K`). The former stands for `-cluster` and is used to instruct `ngresub` to look for jobIDs and descriptions only at a given cluster (or exclude a cluster). This is convenient to use together with the `-a` option, in case you would like to re-submit all the jobs which were originally sent to a specific cluster. The latter option, `-k`, stands for `-kluster`, and should be used to specify preferred re-submission target. Important examples:

```
ngresub -c fire.ii.uib.no myjob1
```

will resubmit all jobs on `fire.ii.uib.no` and the job `myjob1` to any cluster (except the cluster at which the job is currently), while

```
ngresub -k fire.ii.uib.no myjob1
```

will resubmit the job `myjob1` from wherever it was to `fire.ii.uib.no` (note the usage of `-c` and `-k` options).

```
ngresub -c grid1.ua.org -k grid2.ub.org
```

will resubmit all your jobs from cluster `grid1.ua.org` to `grid2.ub.org`.

If the re-submission was successful, the original job will be removed from the remote cluster unless you specify the `-keep` option.

8.1.7 Cleaning Up After Jobs

If a job fails, or you are not willing to retrieve the results for some reasons, a good practice for users is not to wait for the Grid Manager to clean up the job leftovers, but to use `ngclean` to release the disk space and to remove the job ID from the list of submitted jobs and from the Information System.

```
ngclean [options] [job ...]
```

Options:

-a, -all		all jobs
-i, -joblist	lename	le containing a list of jobids
-c, -cluster	[-] textemname	explicitly select or reject a speci c cluster
-C, -clustlist	[-] textem lename	list of clusters to select or reject
-s, -status	statusstr	only select jobs whose status is\$statusstr
-f, -force		removes the job ID from the local list even if the job is not found on the Grid
-t, -timeout	time	timeout for queries (default 40 sec)
-d, -debug	debuglevel	0 = none, 1 = some, 2 = more, 3 = a lot
-x, -anonymous		use anonymous bind for queries
-X, -gsi		use GSI-GSSAPI bind for queries
-v, -version		print version information
-h, -help		print this help
Arguments:		
job ...		list of job IDs and/or jobnames

The `ngclean` should also be used whenever you wish to clean up the local list of submitted jobs, removing entries of old jobs removed by the Grid Managers. In this case, use the `-f` option.

8.1.8 Renewing User Proxy

Quite often, the user proxy expires while the job is still running (or waiting in a queue). In case such job has to upload output files to a Grid location (Storage Element), it will fail. By using the `ngrenew` command, users can upload a new proxy to the job. This can be done while a job is still running, thus preventing it from failing, or whithin 24 hours after the job end. In the latter case, the Grid Manager will attempt to finalize the job by uploading the output files to the desired location.

```
ngrenew [options] [job ...]
```

Options:

-a, -all		all jobs
-i, -joblist	lename	le containing a list of jobids
-c, -cluster	[-] textemname	explicitly select or reject a speci c cluster
-C, -clustlist	[-] textem lename	list of clusters to select or reject
-s, -status	statusstr	only select jobs whose status is statusstr
-t, -timeout	time	timeout for queries (default 40 sec)
-d, -debug	debuglevel	0 = none, 1 = some, 2 = more, 3 = a lot
-x, -anonymous		use anonymous bind for queries
-X, -gsi		use GSI-GSSAPI bind for queries
-v, -version		print version information
-h, -help		print this help

Arguments:

job ...	list of job IDs and/or jobnames
---------	---------------------------------

Prior to using ngrernew, be sure to actually create the new proxy:

```
grid-proxy-init -valid 24:00
```

Here -valid specifies for how long the proxy will be valid (see Section 6.1 for more details).

8.1.9 Synchronizing The Job ID List

If you are using User Interface installations on di erent machines, your local lists of submitted jobs will be di erent. To synchronise these lists with the information in the Information System, use the ngsync command.

```
ngsync [options]
```

Options:

-c, -cluster	[-] textemname	explicitly select or reject a speci c cluster
-C, -clustlist	[-] textem lename	list of clusters to select or reject
-g, -giisurl	url	URL of a central Information System server
-G, -giislist	lename	list of GIIS URLs
-f, -force		don't ask for con rmation
-t, -timeout	time	timeout for queries (default 40 sec)
-d, -debug	debuglevel	0 = none, 1 = some, 2 = more, 3 = a lot
-x, -anonymous		use anonymous bind for queries
-X, -gsi		use GSI-GSSAPI bind for queries
-v, -version		print version information
-h, -help		print this help

As the Information System has a certain latency, do not usengsync immediately after submitting or killing a job, rst wait a few minutes.

Chapter 9

Data Management

At this stage, data management possibilities in an ARC-enabled system are rather limited. The basic operations are simple, one-by-one, like copy and removal (as explained in Section 9.1), with the eventual use of the Replica Catalog (Section 9.3) to assist in arranging files in logical collections, keep track of their replicas, and simplify storage resource discovery. The GSI-enabled `gsiftp` client by Globus can also be used to interact with files on the Grid, available via GridFTP servers.

9.1 Working with files

9.1.1 Listing Grid Files

The `ncls` is a simple utility that allows to list contents and view some attributes of objects of a specified (by an URL) remote directory.

```
ncls [options] <URL>
```

Options:

-h	short help
-v	print version information
-d	debuglevel 0 = some, 1 = more, 2 = a lot
-l	detailed listing
-L	detailed listing including URLs from which file can be downloaded and temporary cached locations

Arguments:

URL	file or directory URL
-----	-----------------------

This tool is very convenient not only because it allows to list files at a GridFTP Storage Element or records in a replica service, but also because it can give a quick overview of a job's working directory, which is explicitly given by job ID.

Usage examples can be as follows:

```
ncls rc://rc.host/lc=Collection,rc=Catalog  
ncls -l gsiftp://lscf.nbi.dk:2811/jobs/1323842831451666535
```

Refer to Section 7.1.1 for the list of URLs accepted by this tool, but keep in mind that `ncls` won't be able to list a directory at an HTTP server, as they normally do not return directory listings.

9.1.2 Copying Grid Files

The `ngcopy` is a powerful tool to copy files over the Grid. It is a part of the Grid Manager, but can be used by the User Interface as well.

```
ngcopy [options] <source> <destination>
```

Options:

-h	short help
-v	print version information
-d	debuglevel 0 = some, 1 = more, 2 = a lot
-c	cache_path use cache
-C	cache_data_path store cached data

Arguments:

source	source URL
destination	destination URL

Users can use `ngcopy` to copy files between a variety of different sources and destinations. Refer to Section 7.1.1 for the list of URLs accepted by this tool. Source URL can end with "/" . In that case, the whole dataset (directory) will be copied. Also, if the destination ends with "/" , it is extended with part of source URL after last "/" , thus allowing users to skip the destination file or directory name if it is meant to be identical to the source.

Since the job ID is in fact a `gsiftp://` URL of the job top directory, you can use `ngcopy` to copy files from the job directory at any time.

Usage examples of `ngcopy` are:

```
ngcopy gsiftp://lscf.nbi.dk:2811/jobs/1323842831451666535/job.out file:///home/myname/job2.out
ngcopy gsiftp://aftpexp.bnl.gov;threads=10/rep/my.file rc://;threads=4@grid.uio.no/lc=Collection,rc=Catalog/zebra4.f
ngcopy http://www.nordugrid.org/data/somefile gsiftp://hathi.hep.lu.se/data/otherfile
```

9.1.3 Erasing Grid Files

The counterpart to the `ngcopy` command, the `ngremove` command allows users to erase files at any location specified by a valid URL (see Section 7.1.1).

```
ngremove [options] <source>
```

Options:

-h	short help
-v	print version information
-d	debuglevel 0 = some, 1 = more, 2 = a lot
-c	continue with meta-data even if it failed to delete real file
-C	cache_data_path store cached data

Arguments:

source	source URL
--------	------------

The most common use for `ngremove` is to erase the files in the Replica Catalog (see Section 9.3, as it will not only remove the physical instance, but also will clean up the logical record).

Here is an `ngremove` example:

```
ngremove rc://grid.uio.no/lc=Collection,rc=Catalog/badfile
```

9.2 gsincftp

`gsincftp` is an attempt by Globus to create a basic GSI-enabled FTP client. It was never meant to be the Grid data management tool of choice, and does not include all possible protocol extensions needed for a Grid file transfer application. However, as no other similar client for the GridFTP server exists, people find it convenient to use `gsincftp` for basic data movement and remote file access operations.

To use the `gsincftp` client, you first need to ensure you have a valid proxy. Then you can log in to any ARC-enabled cluster or Storage element by issuing

```
gsincftp cluster.dept.uni.org
```

This will open an interactive session, where a typical basic set of FTP client commands can be executed. For example, you can list the directory, browse through the directories tree, download, upload or remove files.

Do not use `gsincftp` unless you know exactly what are you doing. Be particularly careful when uploading and deleting files: chances are that you destroy your own or others' work.

Every job you submit can be accessed via the `gsincftp` tool: simply use the host part of your job ID to log in and browse down the rest of the path. For example, if your job ID is `gsiftp://site.it.uni.org:2812/jobs/2115427105241848111`, you can perfectly have a following session:

```
gsincftp site.it.uni.org
cd jobs/2115427105241848111
dir
get myfile
exit
```

Conveniently enough, tools `gsincftpput` and `gsincftpget` are available to upload and download files from a command line, thus allowing for scripting and bulk file movement. For example, the session above can be shortened to a single command (given you know there is a file named `myfile` in the job directory):

```
gsincftpget gsiftp://site.it.uni.org:2812/jobs/2115427105241848111/myfile
```

9.3 Replica Catalog in Examples

The NorduGrid Replica Catalog is nothing but slightly patched Globus Replica Catalog [15]. The support for it has been discontinued by Globus a while ago, and NorduGrid uses it just as a temporary solution for the distributed data catalogue. This Section only presents some usage examples and does not go into details of the Replica Catalog implementation, installation and support.

Only authorised RC managers can perform operations which require write access. For details, contact nordugrid-support@nordugrid.org.

The Globus RC is an hierarchical database: the catalogue consists of collections, each collection consists of logical file names which correspond to one or more physical files at predefined locations. To register an arbitrary file in a RC, the following steps should be performed:

1. Ensure the collection exists
2. Ensure the physical location of the file is registered as one of the locations for the collection
3. Enter the file record into the RC, specifying the location and the file name RELATIVE TO THE LOCATION

The limitation of the Globus RC is that it is impossible to assign arbitrary logical file names: a logical file name must be the actual file name, eventually prepended with the path relative to the registered location.

9.3.1 Define who you are

This is the strongly recommended first step, simplifying authentication at the NorduGrid Replica Catalog

```
export GLOBUS_REPLICA_CATALOG_MANAGER="/O=Grid/O=NorduGrid/OU=nordugrid.org/CN=Jane Doe"
```

Or, for C shells:

```
setenv GLOBUS_REPLICA_CATALOG_MANAGER "/O=Grid/O=NorduGrid/OU=nordugrid.org/CN=Jane Doe"
```

The quoted string /O=Grid/O=NorduGrid/OU=nordugrid.org/CN=Jane Doe is your identity, as specified in the Subject of your Grid certificate. Use grid-cert-info command (Section 4.2.7) to find it.

9.3.2 Create a collection

```
globus-replica-management \
    -collection ldap://grid.uio.no/lc=A_Collection,rc=NorduGrid,dc=nordugrid,dc=org \
    -create
```

Here, grid.uio.no is the server address for the NorduGrid catalogue, and A_Collection is your new collection name. Since the RC is an LDAP database, collection URL must contain the LDAP-complying Distinguished Name, which includes the full NorduGrid RC name space (dc=nordugrid,dc=org). Default port number is 389, but if it is different, it should be specified in a standard IP manner: after the server address, separated by a colon.

9.3.3 Add a location to a collection

```
globus-replica-management \
    -collection ldap://grid.uio.no/lc=A_Collection,rc=NorduGrid,dc=nordugrid,dc=org \
    -location CASTOR \
    -create gsiftp://wacdr002d.cern.ch/castor/cern.ch/atlas/transfer/dc1/
```

The location name CASTOR should later be used as a mount point, instead of the physical URL gsiftp://...

9.3.4 Upload and register a file to a collection

You must have a valid Grid proxy (see Section 6.1) to perform this operation

```
nccopy \
  gsiftp://grid.quark.lu.se/ATLAS/mydata.zebra \
  rc://grid.uio.no/lc=A_Collection,rc=NorduGrid,dc=nordugrid,dc=org/yourdata.zebra
```

In the example above, the first available registered location will be used to store the file. To specify an explicit destination, do:

```
nccopy \
  gsiftp://grid.quark.lu.se/ATLAS/mydata.zebra \
  rc://CASTOR@grid.uio.no/lc=A_Collection,rc=NorduGrid,dc=nordugrid,dc=org/yourdata.zebra
```

9.3.5 Register existing at a location file to a collection

File registration includes three steps:

1. Create a logical file entry in the collection:

```
globus-replica-catalog \
  -host ldap://grid.uio.no/lc=A_collection,rc=NorduGrid,dc=nordugrid,dc=org \
  -logicalfile path/file1.zebra \
  -create size 0
```

2. Verify that file location (mount point) is registered in the collection (see Sections 9.3.8 and 9.3.9), otherwise it has to be added (see Section 9.3.3).

3. Register the physical location(s):

```
globus-replica-management \
  -collection ldap://grid.uio.no/lc=A_collection,rc=NorduGrid,dc=nordugrid,dc=org \
  -location CASTOR \
  -files filelist \
  -register
```

If the file size is unknown, specify "0" as shown above. Logical entries can only be added one by one, while physical location(s) must be added via a filelist , one line per file:

```
path/file1.zebra
path/file2.zebra
```

Note the prepended path , relative to the registered location: it should be possible to construct a correct URL as \${LOCATION}\${FILENAME}

9.3.6 Remove and unregister a file

```
ngremove \
  rc://grid.uio.no/lc=A_Collection,rc=NorduGrid,dc=nordugrid,dc=org/yourdata.zebra
```

9.3.7 Remove a location from a collection

```
globus-replica-management \
    -collection ldap://grid.uio.no/lc=A_collection,rc=NorduGrid,dc=nordugrid,dc=org \
    -location CASTOR \
    -delete
```

9.3.8 Find locations (URL prefixes) for a collection

```
ldapsearch -h grid.uio.no -p 389 \
    -b "lc=A_Collection,rc=NorduGrid,dc=nordugrid,dc=org" \
    "(&(objectclass=GlobusReplicaLocation)(uc*))" uc
```

or, using the Globus interface to LDAP:

```
globus-replica-catalog \
    -host ldap://grid.uio.no:389/lc=A_Collection,rc=NorduGrid,dc=nordugrid,dc=org \
    -collection \
    -list-locations uc
```

9.3.9 Find a URL prefix for a location known by name

```
globus-replica-catalog \
    -host ldap://grid.uio.no:389/lc=A_Collection,rc=NorduGrid,dc=nordugrid,dc=org \
    -location CASTOR \
    -list-attributes uc
```

Chapter 10

The Grid Monitor

The Grid Monitor is perhaps the most convenient utility that allows users and sysadmins alike to check and monitor the status of the ARC Grid facility, status of each job, display user-specific information and otherwise obtain in an intuitive way the information stored in the Information System [4]. It is implemented as a set of pop-up Web pages, connected by hyperlinks, making it easy to browse and navigate. Some limited searching capacity is also available, through the "Match-it-yourself" module.

The structure of the Grid Monitor to great extent follows that of the Information System [4]. The basic objects are defined by the following schema's objectclasses:

```
{ nordugrid-cluster a cluster
{ nordugrid-queue a queue at the cluster, accessible by the ARC users
{ nordugrid-job a Grid job, associated with a queue
{ nordugrid-authuser a user, authorized to submit jobs to a given queue
```

The Grid Monitor also uses the NorduGrid Virtual Organisation (VO) organisationalPerson and Storage Element nordugrid-se objectclasses, and their attributes.

For each objectclass, either an essential subset of attributes, or the whole list of them, is presented in an easily accessible inter-linked manner. This is realized as a set of windows, each being associated with a corresponding module. There are nine major modules :

- 1) An overall Grid Monitor
- 2) Cluster Description
- 3) Queue Details
- 4) Job Information
- 5) User Information
- 6) Attributes Overview
- 7) Customizeable Display Tool ("Match-it-yourself")
- 8) List of Storage Facilities
- 9) List of Users

Each module displays both dynamic and static information: for example, a queue name is static, while the amount of running jobs in this queue is dynamic. Most of the displayed objects are linked to appropriate modules, such that with a simple mouse click, a user can launch another module, expanding the information about the corresponding object or attribute. Each such module opens in an own window, and gives access to other modules in turn, providing thus rather intuitive browsing.

In what follows, these modules are described in detail, an overview of their functionality is given and usage hints are provided.

10.1 The Grid Monitor

The basic module, providing access to the most required information, is the Grid Monitor, showing the overall status of the system. It serves as a starting point for browsing the system information. The purpose of this module is to give a quick overview of the current status of the ARC Grid by showing the list of the available clusters and the most essential information about them: an alias, number of working processors, number of occupied processors and number of queueing jobs. In the current implementation, the main Grid Monitor window contains also the link to the user base of the ARC Grid. Figure 10.1 shows a screenshot of the running monitor. All the information shown is dynamic, including organizational names (countries in this case).




Figure 10.1: The Grid Monitor


In Figure 10.1, the numbered tags indicate clickable objects as explained below:

- 1) Cluster a cluster alias, linked to the cluster description module (Section 10.2), which provides complete information about the current status of a cluster.
- 2) Load a graphical and numeric representation of the cluster load, showing both Grid- and non-Grid (submitted locally) running processes. Red bar shows percentage of Grid processes, while the grey bar shows total relative occupancy of a cluster. Numbers indicate the absolute amount of running processes, with first figure corresponding to the Grid, and second - to the non-Grid ones. It should

be noted that number of processes does not necessarily correspond to the number of running jobs: a parallel job can occupy several processors. By clicking on a bar, a user accesses the list of all Grid jobs running on a cluster (Section 10.4).

- 3) Queueing number of queueing jobs, which includes jobs queued in an LRMS as well as those being pre-processed by the Grid Manager [3]. Only jobs which can be potentially executed in a Grid queue are counted. The number is linked to the same module as the Load item, with the only difference that it displays the list of the Grid-queued jobs. Note that although non-Grid jobs are counted in the total number of queued jobs, they can not be listed by the Grid Monitor, as they do not provide any information to the Grid Information System.
- 4) Match-it-yourself link to the "Match-it-yourself" interface (Section 10.7) which allows users to compose non-standard monitor requests.
- 5) Storage resources link to the list of available storage resources (Section 10.8).
- 6) User base several auxiliary links, providing an access to the VO-listing module (Section 10.9). The main purpose of this link is to provide an easy access to the user-specific information, such as the list of submitted jobs and available resources.

10.2 Cluster Description



NorduGrid Cluster Details - Netscape

NorduGrid Cluster Details for grid.quark.lu.se

Attribute	Value
Distinguished name	nordugrid-cluster-name=grid.quark.lu.se,Mds-Vo-name=local,o=grid
objectClass	Mds
Front-end domain name	nordugrid-cluster
Cluster alias	grid.quark.lu.se
Contact string	Lund Grid Cluster
E-mail contact	gsiftp://grid.quark.lu.se:2811/jobs
	grid.siteadmin@quark.lu.se
	grid.support@quark.lu.se
LRMS type	OpenPBS
LRMS version	2.3.12
LRMS details	FIFO scheduler, single job per processors
Architecture	i686
Operating sys 1	Linux 2.4.3-20mdk
Homogeneous cluster	True
CPU type (slowest)	Pentium III (Coppermine) 1001 MHz
Memory (MB, smallest)	256
Total CPUs	4
CPU:machines	2cpu:2
Occupied CPUs	3
Queued jobs	2
Total amount of jobs	5
Local Storage Element	nordugrid-se-name=grid.quark.lu.se,Mds-Vo-name=Sweden,o=grid
Session directories area	/jobs
Unallocated disk space (MB)	27834
Grid middleware	globus-2.0-9ng
	nordugrid-HEAD
Runtime environment	ATLAS-3.0.1
	ATLAS-3.2.1
	DC1-ATLAS-3.2.1
Mds-validfrom	05-08-2002 19:23:44
Mds-validto	05-08-2002 19:24:14

Queue	Status	CPU (min)	CPUs	Running	Queueing
pc 2	active	0 to 120	N/A	0 (Grid: 0)	0 (Grid: 0)
pclong	active	120 to inf	N/A	3 (Grid: 3)	2 (Grid: 2)

Figure 10.2: ARC-enabled cluster details


The cluster description module displays all the cluster attributes stored in the MDS, as well as most relevant information about the queues, accessible by the Grid users. The window thus contains two lists, as shown in Figure 10.2:

- 1) Attributes: this is a dump of all the attributes of the `nordugrid-clusterobjectclass`, dynamic and static ones. Such attributes as cluster alias, or domain name, are static; others are dynamic, with the values obtained by the MDS from the information providers: e.g., total CPU number, amount of jobs, or available disk space. More details about these attributes can be found in the Grid Information System description [4]. Each attribute (apart of the MDS time stamps) is linked to the Attributes Overview module (Section 10.6), such that clicking on an attribute name brings the list of the values of this particular attribute on all the ARC-enabled clusters. For instance, this is the most convenient way to browse available disk space or runtime environment values over the system.
- 2) Queues the list of queues at a given cluster, accessible by the Grid users. While the detailed list of queue attributes and corresponding jobs can be obtained by clicking on a queue name (see Queue Details module description, Section 10.3), the most essential parameters are listed already in the Cluster Description module. They are: queue name, queue status, queue length (minimal and maximal), number of CPUs assigned to a queue (if available), and number of running and queued jobs. Since queues can be shared between Grid and local users, the total number of jobs is shown, with the number of Grid jobs in parentheses.

The Cluster Description module is linked from most other modules (except List of Users): clicking on the domain name of a cluster opens the Cluster Description window.

10.3 Queue Details

In the Grid Information System, the `nordugrid-queueobjectclass` is described by a set of queue-specific attributes, and has two sub-trees: `nordugrid-job` and `nordugrid-authuser`. This structure reflects the fact that users are not implicitly authorized to submit jobs to any queue. However, the list of users allowed to a specific queue is a fairly static information, and thus is beyond the scope of the Grid Monitor.



The screenshot shows a web browser window titled "NorduGrid Queue Details - Netscape". The main content area displays a table of queue attributes. At the top right are buttons for "Force refresh", "Print", and "Close". The table has columns for "Attribute" and "Value". The attributes listed are: Distinguished name (nordugrid-queue-name=dque, nordugrid-cluster-name=fire.ii.uib.no, Mds-Vo-name=local, o=grid), objectClass (Mds, nordugrid-queue), Queue name (dque), Queue status (active), Running jobs (12), Running Grid jobs (4), Queued jobs (0), Queued Grid jobs (0), Mds-validfrom (2002-11-17 20:05:43), and Mds-validto (2002-11-17 20:06:13). Below this table is another table showing a list of 15 jobs. The columns are Job name, Owner, Status, CPU (min), and Memory (KB). The jobs are: 1 SpinS/Run28/tra512_1r28, 2 SpinS/Run29/tra512_1r29, 3 SpinS/Run32/tra512_1r32, 4 SpinS/Run69/rm256_01r69, 5 SpinS/Run70/rm256_01r70, 6 SpinS/Run77/tra512_01r77, 7 SpinS/Run80/tra512_01r80, 8 SpinS/Run81/tra512_01r81, 9 SpinS/Run84/tra512_01r84, 10 SpinS/Run85/tra512_01r85, 11 SpinS/Run87/tra512_01r87, 12 SpinS/Run103/tra1024_01r103, 13 SpinS/Run102/tra1024_01r102, 14 SpinS/Run82/tra512_01r82, 15 SpinS/Run86/tra512_01r86. The owner for all jobs is O. Syljuåsen. The status for most jobs is FINISHED, while job 12 is INLRMS: R. The CPU and memory values are mostly N/A or 1439, except for job 12 which uses 539 CPU and 434456 KB memory.

Attribute	Value
Distinguished name	nordugrid-queue-name=dque, nordugrid-cluster-name=fire.ii.uib.no, Mds-Vo-name=local, o=grid
objectClass	Mds nordugrid-queue
Queue name	dque
Queue status	1 active
Running jobs	12
Running Grid jobs	4
Queued jobs	0
Queued Grid jobs	0
Mds-validfrom	2002-11-17 20:05:43
Mds-validto	2002-11-17 20:06:13

Job name	Owner	Status	CPU (min)	Memory (KB)
1 SpinS/Run28/tra512_1r28	O. Syljuåsen	FINISHED at: 2002-11-17 16:25:40	N/A	N/A
2 SpinS/Run29/tra512_1r29	O. Syljuåsen	FINISHED at: 2002-11-17 16:27:03	1439	N/A
3 SpinS/Run32/tra512_1r32	O. Syljuåsen	FINISHED at: 2002-11-17 16:35:40	1439	N/A
4 SpinS/Run69/rm256_01r69	O. Syljuåsen	FINISHED at: 2002-11-17 16:37:15	1439	N/A
5 SpinS/Run70/rm256_01r70	O. Syljuåsen	FINISHED at: 2002-11-17 16:41:40	1439	N/A
6 SpinS/Run77/tra512_01r77	O. Syljuåsen	FINISHED at: 2002-11-17 16:39:40	1439	N/A
7 SpinS/Run80/tra512_01r80	O. Syljuåsen	FINISHED at: 2002-11-17 16:41:40	1439	N/A
8 SpinS/Run81/tra512_01r81	O. Syljuåsen	FINISHED at: 2002-11-17 16:41:40	1439	N/A
9 SpinS/Run84/tra512_01r84	O. Syljuåsen	FINISHED at: 2002-11-17 16:41:40	1439	N/A
10 SpinS/Run85/tra512_01r85	O. Syljuåsen	FINISHED at: 2002-11-17 16:43:40	1439	N/A
11 SpinS/Run87/tra512_01r87	O. Syljuåsen	FINISHED at: 2002-11-17 16:47:28	1439	N/A
12 SpinS/Run103/tra1024_01r103	O. Syljuåsen	INLRMS: R	539	434456
13 SpinS/Run102/tra1024_01r102	O. Syljuåsen	INLRMS: R	541	434456
14 SpinS/Run82/tra512_01r82	O. Syljuåsen	INLRMS: R	514	102652
15 SpinS/Run86/tra512_01r86	O. Syljuåsen	INLRMS: R	514	102644

Figure 10.3: Grid queue details

The Queue Details module provides the list of the queue attributes and of all the jobs scheduled (running or waiting) to this queue. Figure 10.3 shows the Grid queue description window, with clickable fields marked by numbered tags as follows:

List of queues available for a given user can be obtained through the User Information module.

- 1) Attributes: the dump of the queue attributes. Just like the cluster attributes (Section 10.2), they can be both static and dynamic. Every attribute is linked to the Attributes Overview module (Section 10.6), which allows the values of each attribute across the entire ARC system to be browsed.
- 2) Cluster name each queue is associated with the cluster whose name is shown at the top of the window. Clicking the cluster name brings up the Cluster Description window (Section 10.2).
- 3) Job name from the Queue Details window, users can get access to detailed information about every job in the queue by clicking the job name. Each job name is linked to the Job Information module, described in Section 10.4.
- 4) Owner: The Grid authentication mechanism allows every job to be associated to a corresponding user, even though an actual Unix account owner may be a generic "griduser". The Grid Monitor uses this feature to display explicitly each job owner. In the Queue Details window (as in all other modules), the user's name is linked to the User Information module (Section 10.5), which displays all the resources available for a given user, as well as the list of the user's jobs.

The Queue Information module is accessible via links to queue names in the Cluster Information (Section 10.2), Job Information (Section 10.4), User Information (Section 10.5) and Attributes Overview (Section 10.6) modules.

10.4 Job Information

The Job Information module is activated on three different occasions:

- { To display a list of all running Grid jobs on a cluster
- { To display a list of all queued Grid jobs on a cluster
- { To show the full information on a given job

Lists of running and queued jobs are accessible from the top Grid Monitor window (Section 10.1) by clicking the corresponding links (marked 2 and 3 in Figure 10.1). As shown in Figure 10.4, such a list contains not only job names, but also their respective owners, status (as returned by the Grid Manager), execution time (in case of running jobs), and the submission queue.

Running jobs at lscf.nbi.dk					Force refresh	Print	Close
Job name	Owner	Status	CPU (min)	Queue			
1 SpinS/Run27/tra512_1r27	O. Syljuåsen	INLRMS: R	519	gridlong			
2 SpinS/Run31/tra512_1r31	O. Syljuåsen	INLRMS: R	519	gridlong			
3 SpinS/Run71/tra256_01r71	O. Syljuåsen	INLRMS: R	510	gridlong			

Figure 10.4: Grid job list

Most of the links in a job list window are linked to the corresponding monitor modules, giving access to more detailed information:

- 1) Job name just like in the Queue Details window (Section 10.3), the job name is linked to the Job Information window, described below. However, while the Queue Details module lists the jobs in a given queue, the Job Information window gives an overview of all the Grid jobs on a cluster.
- 2) Owner: this link is also identical to the one in the Queue Details window: the user's name is linked to the User Information module (Section 10.5), which displays all the resources available for a given user and the list of the user's jobs.
- 3) Queue: the name of the queue is linked to the Queue Details window (Section 10.3), which gives a snapshot of the queue status, including all the Grid jobs submitted to a particular queue { running or waiting.
- 4) Cluster name: clicking on the cluster name brings up the Cluster Description window (Section 10.2), which gives a general overview of a given cluster and the status of its queues (those available for the Grid users).

NorduGrid Jobs - Netscape	
Job ID:	gsiftp://lscf.nbi.dk:2811/jobs/17462021731217695386
	Force refresh Print Close
Attribute	Value
Distinguished name	nordugrid-pbsjob-globalid=gsiftp://lscf.nbi.dk:2811/jobs/1746202
objectClass	Mds
nordugrid-pbsjob	
ID	gsiftp://lscf.nbi.dk:2811/jobs/17462021731217695386
Owner	/O=Grid/O=NorduGrid/OU=nbi.dk/CN=Jakob Langgaard Nielsen
Job name	dc1.002000.simul.01217.hlt.pythia_jet_17
Job submit time (GMT)	05-08-2002 12:21:11
Execution queue	gridlong
Execution cluster	lscf.nbi.dk
Job status	INLRMS: R
Used CPU time	421
Used wall time	422
Used memory (KB)	94764
Requested CPU time	2000
PBS comment	Job started on Mon Aug 05 at 14:21
Standard output file	dc1.002000.simul.01217.hlt.pythia_jet_17.log
Standard error file	dc1.002000.simul.01217.hlt.pythia_jet_17.log
Submission machine	130.225.212.51:47832;lscf.nbi.dk
Mds-validfrom	05-08-2002 19:25:41
Mds-validto	05-08-2002 19:26:11

Figure 10.5: Grid job statistics

The job information window is invoked by clicking on a job name in any Grid Monitor window which lists jobs. It is handled by the same module which produces running/queued job list, and contains simple dump of all the available job attributes (see Figure 10.5). Just like in the Cluster Description and Queue Description windows, each attribute is clickable (as indicated by a tag numbered 1 in Figure 10.5), and is linked to the Attributes Overview module (Section 10.6). This is a convenient way to compare jobs that reside on the system.

10.5 User Information

The User Information module of the Grid Monitor gives access to all the available information related to a given user. This includes the list of available resources (queues, processors and disk space), and the list of user jobs residing on the system at the time of query. To collect this information, the whole system has to be queried, therefore invocation of this module typically takes quite a bit of time (at least compared to most other modules).

Figure 10.6 shows a typical User Information window, where the numbered elds are linked to other Grid Monitor modules:

- 1) Job name this eld is linked to the Job Information window (Section 10.4), providing access to the detailed information on a given job. Unlike the Job Information or Queue Information modules, which list jobs local to a cluster, the User Information module collects all the jobs submitted by a given user to the whole system.
- 2) Cluster since the User Information window displays all the jobs associated with a given user, the description of each respective cluster is available by clicking the cluster name. This brings up a cluster description window, described in Section 10.2.
- 3) Queue this eld is linked to the Queue Details module (Section 10.3), thus giving access to the information about the status of the relevant queue.
- 4) Cluster the upper part of the User Information window lists the Grid resources, available for a user. Each cluster, to which a user is authorized to submit jobs, is indicated by its name. Cluster names are linked to the Cluster Description window (Section 10.2), giving detailed information on available resources.

Information for J. Klem			
Cluster:queue	Free CPUs	Exp. queue length	Free disk (MB)
pc30.hip.helsinki.fi:gridlong	0	0	21983
pc30.hip.helsinki.fi:gridshort	0	0	21983
pc30.hip.helsinki.fi:verylong	0	0	21983
grid.tio.no:default	3	0	5004
grid.tio.no:veryshort	3	0	5004
grid.fi.uib.no:default	3	0	6905
fire.ii.uib.no:dque	50	0	509832
lscf.nbi.dk:gridlong	30:4320	0	101968
lscf.nbi.dk:gridshort	30:60	0	101968
grid.nbi.dk:long	3	0	28224
grid.nbi.dk:short	3:60	0	28224
hepax1.nbi.dk:long	1:4320	0	1724
hepax1.nbi.dk:short	1:60	0	1724
sleipner/byggmek.lth.se:long	4:2880	0	67755
sleipner/byggmek.lth.se:short	4:120	0	67755
grendel.it.uu.se:nordugrid	5	0	30439
seth.hpc2n.umu.se:fque	0	2	251717
grid.quark.lu.se:pc	3:120	0	33034
grid.quark.lu.se:pclong	3	0	33034

Job name	Status	CPU (min)	Cluster	Queue
1 BeamBeam_slim	INLRMS: R	1575	2 pc30.hip.helsinki.fi	3 verylong

Figure 10.6: Grid user information

- 5) Queue since users authorization may be not only cluster-based, but also queue-based, the allowed queue information can be accessed by clicking a queue name. This brings up the Queue Details window, described in Section 10.3.

The simplest way to access the User Information window is via the List of Users (Section 10.9), although it can be invoked from any Grid Monitor window where a user name is displayed (e.g., a Job Information or a Queue Details window).

10.6 Attributes Overview

As it was mentioned above, every ARC objectclass attribute, appearing in a Grid Monitor window, is linked to the Attributes Overview module, which queries all the relevant objects on the system and delivers a comparative list of the attributes. Similarly to the User Information module, querying all the Grid resources takes somewhat long time, as the Grid Monitor does not have its own cache.

This module can also be accessed via the "Match-it-yourself" interface (Section 10.7). In this case, it can list as many attributes as specified by a user request, eventually applying the user selection criteria.

Attribute List	
Name	Jobs, total amount
1 Cluster lscf.nbi.dk	1
2 Cluster seth.hpc2n.umu.se	69
3 Cluster login-3.monolith.nsc.liu.se	426
4 Cluster grendel.it.uu.se	6
5 Cluster farm.hep.lu.se	31
6 Cluster ingvar.nsc.liu.se	6
7 Cluster fire.ii.uib.no	39

Figure 10.7: ARC objects grouped by attribute

Figure 10.7 shows a typical result of the Attributes Overview query: in this example, the nordugrid-cluster attribute "Jobs, total amount" was queried, and a comparative list of results returned. The ResourceId

(indicated by the tag 1) depends on the nature of the attribute, and can be either of:

- { cluster name, linked to the Cluster Description module,
- { cluster name and queue name, linked to the Cluster Description and Queue Details modules respectively,
- { job ID string (see ref.[3] for details), linked to the Job Information module.

10.7 "Match-it-yourself"

The "Match-it-yourself" display tool is a customizable interface to the Attributes Overview module (Section 10.6). It allows users to chose which attributes of an object to display, optionally applying Iters. While the other Monitor windows display a pre-defined set of data, this module gives an advanced user the possibility to build a customized request to the Information System.

An example use case for this interface could be a user desiring to view a list of his running (but not queued or finished) jobs, complete with used CPU and wall time, memory and job name. The "Match-it-yourself" tool would be then invoked for the job object, and the display request would containName Used CPU time Used wall time Used memory (KB) and Status{ the latter with a Iter Status = INLRMS: R.




Figure 10.8: Object class selection window

Figure 10.8 shows the first screen of the "Match-it-yourself" interface, which welcomes users to select the object class to work with, and the amount of attributes to be displayed. When not sure about the latter, users should specify a top estimate { unused fields will be ignored in further searches.




Figure 10.9: Attribute selection window

Figure 10.9 is a snapshot of the screen where the attributes to display and their selection criteria are specified. If a user wishes to display an attribute for all the objects, independently of its value, the rightmost field may be either kept empty, or filled with an asterisk (*), while the middle field should be set to "="". Whenever a Iter has to be applied, an operator should be selected in the middle column, and a match string

Attribute List					
Name	Cluster alias	Operating system	CPUs, total	Postal code	
1 Cluster lscf.nbi.dk	LSCF (NBI)	RedHat 7.2 Linux 2.4.20-13.7smp	28	DK-2100	
2 Cluster toornaarsuk.distlab.diku.dk	DistLab (DIKU)	RedHat 9 Linux 2.4.20-20.9	17	DK-2100	

Figure 10.10: Customized cluster information display

specified in the rightmost field. For example, if only clusters containing "NBI" in their domain names have to be shown, the attribute filter would be `Front-end domain name nbi`. Matches are case-insensitive.

Figure 10.10 is the result of the search according to the criteria defined in the example in Figure 10.9. Three filters were applied: on operating system attribute, total number of CPUs and postal code (in this case we were selecting any cluster which is not in Sweden). Since we wanted to display each cluster's alias as well, this attribute was added to the selection, but with a "match everything" scope. The attribute matching method is exactly the same as used by the Attributes Overview module (Section 10.6), and it re-uses the screen layout shown in Figure 10.7.

10.8 Storage Resources

Although there is no well-defined Storage Element concept in the NorduGrid, some information about the storage resources can be found in the Information System. The Storage Resources module, linked from the main Monitor window, displays all the available information for those Storage Elements which publish it. Particularly important is the base URL, which specifies the Grid mount point that could be used in job descriptions.

NorduGrid Storage Elements					
Name	Space (MB)	Address	Base URL	Type	
LSCF SE	3393	lscf.nbi.dk	gsiftp://lscf.nbi.dk:2811/	gridftp-based	
Oslo SE dc2	845	dc2.uio.no	gsiftp://dc2.uio.no:2811/dc1/	gridftp-based	
Oslo SE dc4	616169	dc4.uio.no	gsiftp://dc4.uio.no:2811/dc1/	gridftp-based	
Oslo SE dc3	974856	dc3.uio.no	gsiftp://dc3.uio.no:2811/dc1/	gridftp-based	
Oslo SE dc1	0	dc1.uio.no	gsiftp://dc1.uio.no:2811/dc1/	gridftp-based	
HPC2N SE DC1	52881	seth.hpc2n.umu.se	gsiftp://seth.hpc2n.umu.se:2811/dc1/	gridftp-based	
Linkoping stora	819604	login-3.monolith.nsc.liu.se	gsiftp://login-3.monolith.nsc.liu.se:2811/se1/	gridftp-based	
Uppsala Atlas M	461	grid.tsl.uu.se	gsiftp://grid.tsl.uu.se:2811/atlas	gridftp-based	
Lund SE 1	1380731	hathi.hep.lu.se	gsiftp://hathi.hep.lu.se:2811/nordugrid	gridftp-based	

Figure 10.11: List of storage elements

10.9 List of Users

The List of Users module is different from the rest of the Grid Monitor modules because it does not deal with the NorduGrid MDS. Instead, it retrieves lists of users from the NorduGrid VO database [19]. It serves as a link between the two databases (MDS and VO), by interfacing each user record to the User Information module (Section 10.5). Figure 10.12 shows a screenshot of a typical VO user list, with numbered tags indicating clickable links as follows:

- 1) Name user name as given in the corresponding Grid certificate field, linked to the User Information module (Section 10.5).

- 2) E-mail E-mail address of a user, if available. It is linked to an e-mail URL, allowing a message to be sent to a user directly from the browser (if such an option is enabled in a browser).

The screenshot shows a window titled "NorduGrid User Base - Netscape". The window contains a table with three columns: "Name", "Affiliation", and "E-mail". The "Name" column lists ten users, each with a small circular icon containing a number (1 through 10). The "Affiliation" column provides the institution for each user. The "E-mail" column shows the email address for each user, with the last two entries (labeled 9 and 10) having their addresses partially obscured by a red box. At the top right of the window are buttons for "Force refresh", "Print", and "Close".

Name	Affiliation	E-mail
Chafik Driouichi	Elementary Particle Physics, Lund University, Sweden	chafik.driouichi@cern.ch
Paula Eerola	Elementary Particle Physics, Lund University, Sweden	paula.eerola@cern.ch
Mattias Ellert	Department of Radiation Sciences, Uppsala University, Sweden	mattias.ellert@cern.ch
Borge Kile Gjelsten	Department of Physics, University of Oslo, Norway	b.k.gjelsten@cern.ch
Nils Gollub	Department of Radiation Sciences, Uppsala University, Sweden	nils.gollub@cern.ch
Lars Melwyn Jensen	Nordita, Copenhagen, Denmark	melwyn.jensen@cern.ch
Aleksandr Konstantinov	Department of Physics, University of Oslo, Norway	aleksandr.konstantinov@cern.ch
Balazs Konya	Elementary Particle Physics, Lund University, Sweden	balazs.konya@cern.ch
Ulf Minnmark	Elementary Particle Physics, Lund University, Sweden	ulf.minnmark@cern.ch

Figure 10.12: List of the NorduGrid users

The List of Users is available only from the top Grid Monitor window.

Chapter 11

HOWTO

UNDER CONSTRUCTION

How to list all the jobs submitted by a user?

Click a user name in any window, e.g., in the List of Users (Figure 10.12, item 1). The List of Users is available from the top Grid Monitor window (Figure 10.1, item 4).

Why the jobs finished two days ago do not show up?

Job results are being kept in the Grid session directory only for a limited period, typically 24 hours. After a session directory is erased, { either by a user request or after its lifetime expiration { all the job information disappears from the system.

How to list all jobs on the NorduGrid/ARC? Bring up any window containing list of jobs (e.g., click

a "Load" bar in the top Grid Monitor window (Figure 10.1, item 2); then click on a job name to bring up a job information window (Figure 10.5); then click any job attribute, like job name or job owner. This will activate the attributes list window (Figure 10.7), containing the list of all the jobs.

How to list all jobs running on a cluster?

Click a "Load" bar in the top Grid Monitor window (Figure 10.1, item 2).

How to list all jobs in a queue?

Click a queue name in any window, e.g., the cluster information (Figure 10.2, item 2), the job information (Figure 10.4, item 3), or the user information (Figure 10.6, item 5).

How to list available runtime environments?

Click any "Cluster" field in the top Grid Monitor window (Figure 10.1, item 1) to bring up the Cluster Details window. Then click "Runtime environment" link in the "Attribute" column (Figure 10.2, item 1).

Appendix A

RPM For Everybody

You've been told that working with RPMs needs system administrator privileges? You've been misled.

RPM stands for "RedHat Package Manager" [20] and is a sophisticated archiving format, allowing not only to pack a set of files and directories in a single archive, but also to install them in an easy-to-manage manner. While a Tape Archive (.tar) or a ZIP archive, with which you may be familiar with, simply packs files with their relative paths, RPM stores entire directory information starting from the root. RPM also relies on a system-wide database to register software version numbers, dependencies and other relevant data. Naturally, directory structures are different on different systems, and not every user has proper permissions to modify them. Also, not everybody is allowed to write into the main RPM database. Evidently, RPM format was created having system administrators in mind. Nevertheless, even if you are a regular user with no special privileges, you can make a fair use of the RPM packages, especially so if creators of such packages made them relocatable i.e., user-friendly. Luckily, most NorduGrid packages are relocatable, including the distributed Globus Toolkit® 2 RPMs. Below are some quick instructions on how to work with RPM packages without having system administrator privileges.

A.1 Listing Contents of an RPM Package

To list files archived in an RPM package, issue an RPM query command:

```
rpm -qlp myfile.rpm
```

Here command line parameters have the following meaning:

- q { perform a query
- l { list files
- p { use the specified package file (myfile.rpm in this example)

A.2 Printing Out an PM Package Information

To retrieve general information about a given RPM package, issue the following RPM query:

```
rpm -qip myfile.rpm
```

Here command line parameters have the following meaning:

- q { perform a query
- i { print out package information
- p { use the specified package file (myfile.rpm in this example)

This query will print out all the essential information stored by the creator of the RPM package in question. This may contain such fields as package name and version, creator's name, build date and { what's most important for users { relocations . Section A.7 explains how to make use of this information.

A.3 Simple Unpacking of an RPM Archive

In many cases you would only need to extract files from an RPM archive, without performing complex operations with an RPM database. There is a simple way to do it:

```
rpm2cpio < myfile.rpm | cpio -i --make-directories
```

This method makes use of the generic GNU CPIO utility, which deals with copying files to and from archives. The rpm2cpio command converts from RPM to CPIO format, and the output of this conversion is redirected to the cpio command. Command line parameters for the latter have the following meaning:

i { extract contents
make-directories { create directories when necessary

As a result, all the contents of the RPM package will be extracted into the current directory, creating relative paths.

A.4 Creating a Private RPM Database

To achieve higher flexibility and to get access to more RPM functionality, you may want to make a step forward and create your own RPM database. You only have to do it once, by issuing the following instructions:

```
mkdir $HOME/myrpmdbs
rpmbuild --initdb --dbpath $HOME/myrpmdbs
```

Mentioned in this example directory \$HOME/myrpmdbs can of course be substituted with any other location which suits you best. The only requirement is that you must have write permissions in this location.

Having such a personal RPM database allows you to perform more complex operations with RPM packages, without resorting to simple unpacking and manual installation. To simplify your life even further, do the following:

```
echo '%_dbpath /home/yourname/myrpmdbs' | cat >> $HOME/.rpmmacros
```

This will create a file .rpmmacros in your \$HOME directory , and add there the line specifying the database location. In this example, /home/yourname/myrpmdbs should be substituted with your RPM database path. This will instruct RPM to use always your personal database. If you don't want to use this feature (for example, if you have several databases), take care to append

```
--dbpath $HOME/myrpmdbs
```

to each RPM instruction which refers to such a database (e.g., package installation or removal).

It may be useful to copy the system-wide database into your own one. RPM does not provide any tool for database synchronization (yet?), thus you have to do it hard way:

```
cp /var/lib/rpm/* $HOME/myrpmdbs.
```

Here /var/lib/rpm/ is a typical default location of the system-wide database (it could be different though on different systems). Having thus your private database initialized with the existing system information may help you in dealing with dependencies(see Section A.8), but only for a while, since any system-wide upgrades will not be registered in your database, and there is no way to synchronize RPM databases in a clever manner.

On some systems, you should use > instead of >> if the file .rpmmacros did not exist before.

A.5 Installing an RPM Package

Having defined your private database (Section A.4), you can attempt to install any RPM package by doing the following:

```
rpm -ivh myfile.rpm
```

Here command line parameters have the following meaning:

- i { perform an installation procedure
- v { print extra information
- h { print progress bar with hash-marks

Keep in mind that if you didn't define a default database in `$HOME/.rpmmacros` you'll have to append `--dbpath $HOME/myrpmd` (or whatever is your private database location) to the directive.

Most likely, however, such a simple installation instruction will fail. There are two main reasons:

- a) RPM packages attempt to install themselves in locations defined by their creators, not by you. How to get around this is described in Section A.7.
- b) RPM checks for other software needed by the package `{dependencies}` in your private database; however, most likely, such software was not installed by you and can not be found in your database. How to deal with this is described in Section A.8.

A.6 Upgrading RPM Packages

If you happened to have a package installed and simply want to upgrade it, issue the following instruction:

```
rpm -Uvh myfile.rpm
```

Here command line parameters have the following meaning:

- U { upgrade the installation
- v { print extra information
- h { print progress bar with hash-marks

Since this operation needs to access a database, you either have to have the default database location specified in the `$HOME/.rpmmacros`, or to append `--dbpath $HOME/myrpmd` (or whatever is your private database location) to the directive (see Section A.4 for details).

A.7 Relocating RPM Packages

As it was mentioned in Section A.2, an RPM package may contain information on relocatable directories. Such directories are listed as `locations`, meaning that their contents can be relocated during the installation in another directory. To perform such an installation, do the following:

```
rpm -ivh myfile.rpm --relocate /oldlocation=/newlocation
```

Here `/oldlocation` is one of the relocatable directories of the original package as listed by the `rpm -qip myfile.rpm` command, and `/newlocation` is your preferred destination, specified as an absolute path (starting with `/`). The command line parameters have the following meaning:

- i { perform an installation procedure
- v { print extra information
- h { print progress bar with hash-marks
- relocate { instruct RPM to install files from `/oldlocation` into `/newlocation`

As of RPM version 4.2.1, multiple relocations are possible. To use this option, specify several relocation pairs on the command line, i.e.,

```
--relocate /old=/new --relocate /old/subdir=/new/subdir .
```

The order of such pairs in the line is important, as RPM will attempt to create new directories and, quite naturally, can not skip a level.

If the package information (as listed by rpm -qip) contains several relocations, you must specify a relocate pair for all of them.

It may turn out that the package creator forgot to describe some pathes as "relocateable", so that they do not appear in the relocations list of the RPM, and yet the package attempt to install in such directory. There's little you can do about it, except attempting to use the --badrelloc option:

```
rpm -ivh myfile.rpm --relocate /oldlocation=/newlocation --badrelloc
```

As in the case of installation, you either have to have the default database location specified in the \$HOME/.rpmmacros or to append --dbpath \$HOME/myrpmd (private database location) to the directive (see Section A.4 for details).

A.8 Dealing with Dependencies

Even when relocations proceeded smoothly, your package may still fail to get installed due to unsatisfied dependencies (this is the name for any other software needed by the package), which are absent from your private database (Section A.4). A bold way to deal with it is to force the installation, e.g.:

```
rpm -ivh myfile.rpm --relocate /oldlocation=/newlocation --nodeps
```

The command line parameters have the following meaning:

- i { perform an installation procedure
- v { print extra information
- h { print progress bar with hash-marks
- relocate { instruct RPM to install files from /oldlocation into /newlocation
- nodeps { ignore dependencies

This is an admittedly non-elegant way. A better solution may be to enter the necessary information into the database by installing "virtual" RPMs which only register a database record without actually installing software; however this is clearly package-dependent, thus you should request such a "fake" RPM from the package provider.

A.9 Listing Installed Packages

To list all the packages installed via an RPM mechanisms, do:

```
rpm -qai
```

Here command line parameters have the following meaning:

- q { perform a query
- a { query all installed packages
- i { print out package information

^ySome older versions can also do multiple relocations, but most have one or another bug.

This command prints out the information stored in your RPM database, hence you either have to have the default database location specified in the \$HOME/.rpmmacros file, or to append --dbpath \$HOME/myrpmd (or whatever is your private database location) to the directive (see Section A.4 for details).

A.10 Uninstalling RPM Packages

Whenever you'll have to uninstall a package, issue the instruction:

```
rpm -e mypackage
```

Here mypackage is the name of the package as listed by the rpm -qai command. Command line parameter has the following meaning:

e { uninstall packages

This command removes the files associated with the package from your system and erases the corresponding record from your RPM database. You either have to have the default database location specified in the \$HOME/.rpmmacros file, or to append --dbpath \$HOME/myrpmd (or whatever is your private database location) to the directive (see Section A.4 for details).

A.11 Building RPM from Source

It may happen so that binary RPM packages for your system are unavailable, but a source RPM or a tarball is provided. You can build a binary RPM yourself from such sources, but some extra manipulations should be made first.

The default RPM top directory is /usr/src/redhat (for a RedHat system). Naturally, as a user, you have no write permission there. To solve the problem, start by creating a new directory structure in any place which has enough disk space and write permission:

```
mkdir -p rpmtop/RPMS/i386; mkdir rpmtop/SRPMS; mkdir rpmtop/SOURCES;
mkdir rpmtop/BUILD; mkdir rpmtop/SPEC
```

Now you should instruct RPM to use this directory instead of the system-wide one (assuming you created the rpmtop structure above in /home/yourname/):

```
echo '%_topdir /home/yourname/rpmtop' | cat >> $HOME/.rpmmacros
```

Next thing you should take care of, is the temporary directory for RPM builds, which by default is /var/tmp/ , also unavailable for mere mortals. The solution is similar to the above, to create your own directory in any place which has enough disk space and write permission:

```
mkdir mytmp
```

This directory should also be specified in your .rpmmacros file:

```
echo '%_tmppath /home/yourname/mytmp' | cat >> $HOME/.rpmmacros
```

That's it; from now on you should be able to build binary RPMs from source by using the command:

```
rpmbuild -ba mypackage.src.rpm
```

or

```
rpmbuild -ta mypackage.tar.gz
```

depending whether the sources are provided as source RPM(`mypackage.src.rpm`) or as a tarball (`mypackage.tar.gz`). The command line options are, correspondingly:

```
ba  {  build binary and source packages from a source RPM  
ta  {  build binary and source packages from (gzipped) tarball
```

Your RPMs will be placed in `/home/yourname/rpmtop/RPMS/i386/` directory of the example above. In case your architecture is different from i386, please take care of creating a corresponding subdirectory in `rpmtop/RPMS`(e.g., `rpmtop/RPMS/alpha`). If you do not know what is the architecture, use

```
uname -m
```

This command will typically print out a string like "i386" or "i586" or "i686" and such, which is the hardware architecture name of your machine.

Appendix B

Globus Toolkit 2 installation notes

The NorduGrid middleware (ARC) builds on top of the Globus Toolkit ® 2 (GT2). Although any reasonably stable release of GT2 can be used, NorduGrid exploits many features which are often out of scope of the Globus developers. As a result, several patches and bug fixes for GT2 are applied by the NorduGrid. Such patched version of Globus is strongly recommended, since it allows users to avoid several shortcomings. It is packed as a single RPM distribution and is available for download from the NorduGrid downloads area at <http://ftp.nordugrid.org/download> as binaries as well as the source.

Installation of GT2 from binary RPMs requires only the Grid Packaging Tools (GPT) [21] as a runtime dependency. GPT RPMs are available in the NorduGrid downloads area for your convenience.

In case a pre-built GT2 binary RPM or a tarball for your system is not available, NorduGrid provides a source RPM for the patched GT2 (`globus-<x.y.z-N>ng`). Re-building a single `globus-<x.y.z-N>ng` RPM requires a functional RPM build environment and prior installation of the following software:

- gpt (RPM available from <http://ftp.nordugrid.org/download> area)
- ncurses-devel (normally comes with your Linux distribution)
- Development packages of either Berkeley DB (<= 4.0, not newer) or GNU dbm which should normally come with your Linux distribution. The choice depends on your distribution. Possible package names are:

```
{ gdbm2-devel  
{ gdbm-devel  
{ db4-devel
```

Corresponding runtime packages also need to be in place, since the above depend on them:

```
{ gdm2  
{ gdbm  
{ db4
```


Appendix C

NorduGrid ARC build notes

This section describes the build procedure of the NorduGrid middleware (ARC) from tarball or from source RPM.

C.1 Dependencies

Before trying to compile the ARC tools, make sure you have installed the following software packages:

- GNU make GNU autotools
- C++ compiler and library
- Grid Packaging Tools (GPT) [21]
- Globus Toolkit 2.4.3 [2] which contains
 - { OpenSSL
 - { OpenLDAP
 - { Cyrus SASL
 - { Globus Replica Catalog
 - { Globus RLS
- gSOAP[22]
- GAC[18]
- VOMS[23]
- MySQLclient libraries
- libxml2

Note that NorduGrid provides packaged versions of GPT, Globus,gSOAPand VOMSwhile GACis distributed within the NorduGrid source. The rest of the dependencies are available in any standard Linux distributions.

C.2 Basic build with autotools

The build is using the GNU autotools . This means that a standard installation can be made with:

```
./configure  
make  
make install
```

The configure script accepts the usual options with the addition of:

--enable-experimental	Enable experimental code
--enable-rpath-hack	Do not rpath Globus libraries in binaries
--enable-docs	Build the documentation
--with sysv-scripts-location=<PATH>	Location of the SYSV init scripts (e.g. /etc/init.d)
--with-monitor-prefix=<PATH>	Specify the location of the Grid Monitor PHP scripts
--with-monitor-local-prefix=<PATH>	Specify the relative location of the Grid Monitor PHP scripts
--with-gsoap-location=<PATH>	Specify the gSOAP installation path
--with-mysql-location=<PATH>	Specify the MySQL installation path
--with-libxml-location=<PATH>	Specify the libxml installation path
--with-nordugrid-location=<PATH>	Specify the ARC installation path
--with-globus-location=<PATH>	Specify the Globus installation path
--with-gpt-location=<PATH>	Specify the GPT installation path
--with-globus-makefile-header	Use globus-makefile-header to generate makefile stubs
--with-flavor=<flavor>	Specify the Globus build flavor or without-flavor for a flavor independent build

Note that using --with-nordugrid-location=/opt/nordugrid switch will install the software using the /opt/nordugrid prefix and place the software in subdirectories:

```
/opt/nordugrid/bin
/opt/nordugrid/lib
/opt/nordugrid/libexec
..
```

For a "standard" install the --prefix=/usr/local will place the software in nordugrid subdirectories:

```
/usr/local/bin
/usr/local/lib/nordugrid
/usr/local/libexec/nordugrid
..
```

Please note that as of the 0.4 Release the "standard install" is not fully supported yet, we recommend to use the --with-nordugrid-location switch. Furthermore, makebuilds the full middleware containing server, client, monitor and documentation; modular builds (such as make client , or make server) are not supported yet.

C.3 Building with RPM

NorduGrid can be built using RPM. From a tar.gz file, do:

```
rpmbuild -ta nordugrid-<version>.tar.gz
```

Or, from a .src.rpm do:

```
rpmbuild --rebuild nordugrid-<version>.src.rpm
```

Source RPMs are configured with the --with-nordugrid-location switch and binary builds are fully relocatable.

In terms of RPMs the build requirements can be satisfied with the following packages:

- gpt >= 3
- globus >= 2.4.3-9ng
- gsoap >= 2.5.2
- voms = 1.1.39
- voms-devel = 1.1.39
- libxml2-devel
- MySQL-devel

Note that the naming convention above might not correspond exactly to the naming used on your system. Also be aware that on some systems the RPM dependencies are broken. This means for example that libxml2 may not be explicitly required by libxml2-devel while it should be.

C.4 Binary RPMs: runtime requirements

The RPMs created by rpmbuild as in Section C.3 are:

- nordugrid-client { Client programs
- nordugrid-server { Server-side programs
- nordugrid-gridmap-utils { Utilities for managing gridmap-les
- nordugrid-ca-utils { Utilities for maintaining CA les
- nordugrid-devel { Development les (headers, static libs)
- nordugrid-monitor { Grid monitor web interface (should be installed on a Web server)
- nordugrid-doc { Documentation

The strict runtime RPM dependencies are:

- nordugrid-client -> globus
- nordugrid-server -> globus, globus-config, voms = 1.1.39, libxml2
- nordugrid-gridmap-utils -> perl-perl-ldap, perl-libwww-perl
- nordugrid-ca-utils -> wget

Dependencies not expressed in the RPM requirements:

- nordugrid-server -> standard Perl environment
- nordugrid-ca-utils -> openssl (native or globus-provided)
- nordugrid-gridmap-utils -> openssl (native or provided with Globus) and optional (preferably curl >= 7.9.8

Special requirements of the Grid Monitor (not expressed in RPM requirements are described in the README file of the nordugrid-monitor RPM.

Appendix D

Known Grid Certificate Authorities

This list of Certificate Authorities is non-authoritative, as the authorities and links are subject to change.

Country	CA	URL
Albania	SEE-Grid	http://www.grid.auth.gr/pki/seagrid-ca/
Armenia	ArmeSFo	http://www.escience.am/ca
Belgium	BEGrid	https://gridra.belnet.be/pub
Bosnia and Herzegovina	SEE-Grid	http://www.grid.auth.gr/pki/seagrid-ca/
Bulgaria	SEE-Grid	http://www.grid.auth.gr/pki/seagrid-ca/
Canada	GridCanada	http://www.gridcanada.ca/ca
CERN	CERN	http://cern.ch/service-grid-ca
Croatia	SEE-Grid	http://www.grid.auth.gr/pki/seagrid-ca/
Cyprus	CyGrid	http://www.cs.ucy.ac.cy/cygrid-ca
Czech Republic	CESNET	http://www.cesnet.cz/pki
Denmark	NorduGrid	http://www.nbi.dk/HEP/CA
Estonia	Eesti Grid	http://grid.eenet.ee/en
Finland	NorduGrid	http://www.nbi.dk/HEP/CA
France	CNRS	http://igc.services.cnrs.fr/Datagrid-fr
Germany	GridKa	http://grid.fzk.de/ca
Greece	Hellas Grid	http://pki.physics.auth.gr/hellasgrid-ca
Hungary	SEE-Grid	http://www.grid.auth.gr/pki/seagrid-ca/
Ireland, Republic of	Grid-Ireland	http://www.cs.tcd.ie/grid-ireland/gi-ca
Italy	INFN	http://security.fi.infn.it/CA
Korea, Republic Of	KISTI	http://gridtest.gridcenter.or.kr
Macedonia	SEE-Grid	http://www.grid.auth.gr/pki/seagrid-ca/
The Netherlands	NIKHEF	http://certificate.nikhef.nl
Norway	NorduGrid	http://www.nbi.dk/HEP/CA
Pakistan	PK-Grid	http://www.ncp.edu.pk/pk-grid-ca
Poland	Polish Grid	http://www.man.poznan.pl/plgrid-ca
Portugal	LIP	http://ca.lip.pt
Romania	SEE-Grid	http://www.grid.auth.gr/pki/seagrid-ca/
Russia	Russian DataGRID	http://lhc.sinp.msu.ru/CA
Serbia and Montenegro	SEE-Grid	http://www.grid.auth.gr/pki/seagrid-ca/
Slovakia	SlovakGrid	http://ups.savba.sk/ca

Slovenia	SiGNET	http://signet-ca.ijs.si
Spain	Datagrid-ES	http://www.ifca.unican.es/datagrid/ca
Sweden	NorduGrid	http://www.nbi.dk/HEP/CA
Switzerland	CERN	http://cern.ch/service-grid-ca
Taipei	ASCCG	http://ca.grid.sinica.edu.tw
Turkey	SEE-Grid	http://www.grid.auth.gr/pki/seegrid-ca/
United Kingdom	e-Science Grid	http://www.grid-support.ac.uk/ca
United States	DOE Science Grid	http://www.doegrids.org
	ESnet	http://www.es.net/CA
	FNAL	http://computing.fnal.gov/security/pki

Bibliography

- [1] The NorduGrid Collaboration. [Online]. Available: <http://www.nordugrid.org>
- [2] The Globus Alliance. [Online]. Available: <http://www.globus.org>
- [3] A. Konstantinov. The NorduGrid Grid Manager. [Online]. Available: <http://www.nordugrid.org/documents>
- [4] B. Konya. The NorduGrid Information System. [Online]. Available: <http://www.nordugrid.org/documents/ng-infosys.pdf>
- [5] M. Ellert. The NorduGrid toolkit user interface. [Online]. Available: <http://www.nordugrid.org/documents/NorduGrid-UI.pdf>
- [6] O. Smirnova. Extended Resource Specification Language. [Online]. Available: <http://www.nordugrid.org/documents/xrsl.pdf>
- [7] ||. The Grid Monitor. [Online]. Available: <http://www.nordugrid.org/documents/monitor.pdf>
- [8] RSA Labs. RSA Cryptography FAQ. [Online]. Available: <http://www.nordugrid.org/documents/rsalabs\protect\unhbox\voidb@x\kern.06em\vbox{\hrulewidth.3em}faq41.pdf>
- [9] Public-Key Infrastructure (X.509) (pkix). [Online]. Available: <http://www.ietf.org/html.charters/pkix-charter.html>
- [10] The Open Source toolkit for SSL/TLS. [Online]. Available: <http://www.openssl.org/>
- [11] Open source implementation of the Lightweight Directory Access Protocol. [Online]. Available: <http://www.openldap.org>
- [12] Grid Security Infrastructure (GSI). [Online]. Available: <http://www.globus.org/security/>
- [13] The Globus Resource Specification Language RSL v1.0. [Online]. Available: <http://www-fp.globus.org/gram/rsl\protect\unhbox\voidb@x\kern.06em\vbox{\hrulewidth.3em}spec1.html>
- [14] A. Konstantinov. Protocols, Uniform Resource Locators (URL) And Extensions Supported In ARC. [Online]. Available: <http://www.nordugrid.org/documents>
- [15] Globus Replica Catalog Service. [Online]. Available: <http://www-fp.globus.org/datagrid/relica-catalog.html>
- [16] Replica Location Service. [Online]. Available: <http://grid-data-management.web.cern.ch/grid-data-management/relica-location-service/index.html>
- [17] A. Konstantinov. The NorduGrid Smart Storage Element. [Online]. Available: <http://www.nordugrid.org/documents>
- [18] The Gridsite. [Online]. Available: <http://www.gridsite.org>
- [19] Description of the NorduGrid Virtual Organisation. [Online]. Available: <http://www.nordugrid.org/NorduGridVO/vo-description.html>
- [20] RedHat Package Manager. [Online]. Available: <http://www.rpm.org>
- [21] Grid Packaging Tools. [Online]. Available: <http://www.gridpackagingtools.org>

- [22] gSOAP. [Online]. Available: <http://www.cs.fsu.edu/~engelen/soap.html>
- [23] Virtual Organisation Management Service. [Online]. Available: <http://datagrid.in2p3.fr/cgi-bin/cvsweb.cgi/>

Index

Symbols	
.ngalias	16
.nggiislist	16
.nghistory	16
.ngjobs	16
.ngrc	15
A	
access control	27
attributes	71
authentication	17
authorization	27
B	
blacklist	50
C	
CA	17, 20, 21
cerificate	
password	21
certificate	17, 17
convert	26
inspect	26
issuing	21
personal	
request	19
request	24, 25, 25
revocation	21
verify	26
Certificate Authority	21
Certificate Authority	17, 20
certificate.change password	26
client	11
configuration files	15
download	11, 14
install	
RPM	15
installation	11
rebuild	15
cluster	68
alias	66
attributes	68
load	66
Computing Element	38
D	
data management	59
disk space	68
dry run	50
E	
E-mail	74
executable	47
executables	47
G	
giislist	50
Globus Toolkit	7, 12
installation	
RPM	13
tarball	13
GLOBUS_LOCATION	11
GLOBUS_REPLICA_CATALOG_MANAGER	62
gmlog	54
Grid Manager	7
grid monitor	66
gsincftp	61
gsincftpget	61
gsincftpput	61
J	
job	
by user	70
in a queue	69
information	70
name	69
on cluster	69
owner	69
parallel	67
queued	69
queueing	67
running	67, 69
status	52
job ID	50
K	
key	
pair	21
private	21, 25
public	21
L	
lifetime	75
M	
Match it yourself	67, 72
middleware	7
modules	65
N	
ngcat	52

ngclean	56
ngcopy	60
ngget	53
ngkill	54
ngls	59
ngremove	60
ngrenew	56
ngresub	54
ngstat	51
ngsub	49
ngsync	57
ngtest	30
nordugrid-authuser	65
nordugrid-cluster	65
nordugrid-job	65
nordugrid-queue	65
NORDUGRID_LOCATION	11
 O	
objectclass	65
 P	
password	21, 25
change	26
proxy	20, 29
initialization	29
 Q	
queue	68
attributes	69
length	68
list	68
queue.name	68
 R	
Replica Catalog	61
collection	62
location	62
resources	70
RSL	33
runtime environment	68
 S	
signature	
digital	21
SN	22, 26
storage	67
Storage Element	73
Storage resources	73
Subject Name	22, 26
submit job	49
support	8
 U	
UI	49
commands	49
ngcat	52
ngclean	56
ngcopy	60
ngget	53
ngkill	54
ngls	59
ngremove	60
ngrenew	56
ngresub	54
ngstat	51
ngsub	49
ngsync	57
ngtest	30
URL	34
options	35
User Interface	49
user information	70
User Interface	7
user list	73
 V	
Virtual Organization	27
VO	27
managers	27
 W	
Web site	8
 X	
X509_USER_PROXY	29
xRSL	33
attributes	36
acl	42
architecture	44
arguments	37
cache	38
cluster	42
count	45
cpuTime	39
disk	40
dryRun	44
environment	45
executable	36
executables	38
ftpThreads	42
gmlog	41
gridTime	39
inputFiles	37
jobName	42
jobreport	45
join	41
lifeTime	43
memory	39
middleware	40
nodeAccess	44
notify	43
outputFiles	38
queue	43
replicaCollection	44
rerun	44
rsl_substitution	44
runTimeEnvironment	40
startTime	43

stderr	41
stdin	41
stdout	41