

VOMS CC API

1.5.0

Generated by Doxygen 1.5.7.1

Tue Jun 30 05:31:37 2009

Contents

1	Data Structure Index	1
1.1	Data Structures	1
2	File Index	3
2.1	File List	3
3	Data Structure Documentation	5
3.1	attribute Struct Reference	5
3.1.1	Detailed Description	5
3.1.2	Field Documentation	5
3.1.2.1	name	5
3.1.2.2	qualifier	5
3.1.2.3	value	5
3.2	attributelist Struct Reference	7
3.2.1	Detailed Description	7
3.2.2	Field Documentation	7
3.2.2.1	attributes	7
3.2.2.2	grantor	7
3.3	contactdata Struct Reference	8
3.3.1	Detailed Description	8
3.3.2	Field Documentation	8
3.3.2.1	contact	8
3.3.2.2	host	8
3.3.2.3	nick	8
3.3.2.4	port	8
3.3.2.5	version	8
3.3.2.6	vo	9
3.4	data Struct Reference	10
3.4.1	Detailed Description	10

3.4.2	Field Documentation	10
3.4.2.1	cap	10
3.4.2.2	group	10
3.4.2.3	role	10
3.5	voms Struct Reference	11
3.5.1	Detailed Description	11
3.5.2	Constructor & Destructor Documentation	12
3.5.2.1	voms	12
3.5.2.2	voms	12
3.5.2.3	~voms	12
3.5.3	Member Function Documentation	12
3.5.3.1	GetAC	12
3.5.3.2	GetAttributes	12
3.5.3.3	GetTargets	12
3.5.3.4	operator=	12
3.5.4	Friends And Related Function Documentation	12
3.5.4.1	TranslateVOMS	12
3.5.4.2	vomsdata	12
3.5.5	Field Documentation	12
3.5.5.1	custom	12
3.5.5.2	date1	12
3.5.5.3	date2	12
3.5.5.4	fqn	13
3.5.5.5	serial	13
3.5.5.6	server	13
3.5.5.7	serverca	13
3.5.5.8	siglen	13
3.5.5.9	signature	13
3.5.5.10	std	13
3.5.5.11	type	13
3.5.5.12	uri	13
3.5.5.13	user	14
3.5.5.14	userca	14
3.5.5.15	version	14
3.5.5.16	voname	14
3.6	vomsdata Struct Reference	15

3.6.1	Detailed Description	16
3.6.2	Constructor & Destructor Documentation	16
3.6.2.1	vomsdata	16
3.6.2.2	~vomsdata	16
3.6.2.3	vomsdata	16
3.6.3	Member Function Documentation	16
3.6.3.1	AddTarget	16
3.6.3.2	Contact	16
3.6.3.3	ContactRaw	17
3.6.3.4	DefaultData	17
3.6.3.5	ErrorMessage	17
3.6.3.6	Export	17
3.6.3.7	FindByAlias	17
3.6.3.8	FindByVO	18
3.6.3.9	Import	18
3.6.3.10	ListTargets	18
3.6.3.11	LoadCredentials	18
3.6.3.12	LoadSystemContacts	18
3.6.3.13	LoadUserContacts	19
3.6.3.14	Order	19
3.6.3.15	ResetOrder	19
3.6.3.16	ResetTargets	19
3.6.3.17	Retrieve	19
3.6.3.18	Retrieve	20
3.6.3.19	Retrieve	20
3.6.3.20	RetrieveFromCred	20
3.6.3.21	RetrieveFromCtx	20
3.6.3.22	RetrieveFromProxy	21
3.6.3.23	ServerErrors	21
3.6.3.24	SetLifetime	21
3.6.3.25	SetRetryCount	21
3.6.3.26	SetVerificationTime	21
3.6.3.27	SetVerificationType	21
3.6.4	Field Documentation	21
3.6.4.1	data	21
3.6.4.2	error	21

3.6.4.3	extra_data	22
3.6.4.4	workvo	22
4	File Documentation	23
4.1	voms_api.h File Reference	23
4.1.1	Typedef Documentation	24
4.1.1.1	check_sig	24
4.1.1.2	gss_cred_id_t	24
4.1.1.3	gss_ctx_id_t	24
4.1.2	Enumeration Type Documentation	24
4.1.2.1	data_type	24
4.1.2.2	recurse_type	25
4.1.2.3	verify_type	25
4.1.2.4	verror_type	25
4.1.3	Function Documentation	26
4.1.3.1	getMajorVersionNumber	26
4.1.3.2	getMinorVersionNumber	26
4.1.3.3	getPatchVersionNumber	26

Chapter 1

Data Structure Index

1.1 Data Structures

Here are the data structures with brief descriptions:

attribute	5
attributelist	7
contactdata	8
data (User's characteristics: can be repeated)	10
voms	11
vomsdata	15

Chapter 2

File Index

2.1 File List

Here is a list of all files with brief descriptions:

voms_api.h	23
----------------------------	----

Chapter 3

Data Structure Documentation

3.1 attribute Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string [name](#)
- std::string [qualifier](#)
- std::string [value](#)

3.1.1 Detailed Description

Definition at line 45 of file voms_api.h.

3.1.2 Field Documentation

3.1.2.1 std::string attribute::name

attribute's group

Definition at line 46 of file voms_api.h.

3.1.2.2 std::string attribute::qualifier

attribute's qualifier

Definition at line 47 of file voms_api.h.

3.1.2.3 std::string attribute::value

attribute's value

Definition at line 48 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.2 attributelist Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string [grantor](#)
- std::vector< [attribute](#) > [attributes](#)

3.2.1 Detailed Description

Definition at line 51 of file voms_api.h.

3.2.2 Field Documentation

3.2.2.1 std::vector<attribute> attributelist::attributes

The attributes themselves.

Definition at line 53 of file voms_api.h.

3.2.2.2 std::string attributelist::grantor

Who granted these attributes.

Definition at line 52 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.3 contactdata Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string [nick](#)
- std::string [host](#)
- std::string [contact](#)
- std::string [vo](#)
- int [port](#)
- int [version](#)

3.3.1 Detailed Description

Definition at line 65 of file voms_api.h.

3.3.2 Field Documentation

3.3.2.1 std::string contactdata::contact

The subject of the server's certificate

Definition at line 71 of file voms_api.h.

3.3.2.2 std::string contactdata::host

The hostname of the server

Definition at line 70 of file voms_api.h.

3.3.2.3 std::string contactdata::nick

< You must never allocate directly this structure. Its sizeof() is subject to change without notice. The only supported way to obtain it is via the FindBy* functions. The alias of the server

Definition at line 69 of file voms_api.h.

3.3.2.4 int contactdata::port

The port on which the server is listening

Definition at line 73 of file voms_api.h.

3.3.2.5 int contactdata::version

The version of globus under which the server is running

Definition at line 75 of file voms_api.h.

3.3.2.6 std::string contactdata::vo

The VO served by this server

Definition at line 72 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.4 data Struct Reference

User's characteristics: can be repeated.

```
#include <voms_api.h>
```

Data Fields

- `std::string` [group](#)
- `std::string` [role](#)
- `std::string` [cap](#)

3.4.1 Detailed Description

User's characteristics: can be repeated.

Definition at line 37 of file `voms_api.h`.

3.4.2 Field Documentation

3.4.2.1 `std::string data::cap`

user's capability

Definition at line 40 of file `voms_api.h`.

3.4.2.2 `std::string data::group`

user's group

Definition at line 38 of file `voms_api.h`.

3.4.2.3 `std::string data::role`

user's role

Definition at line 39 of file `voms_api.h`.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.5 voms Struct Reference

```
#include <voms_api.h>
```

Public Member Functions

- [voms](#) (const [voms](#) &)
- [voms](#) ()
- [voms](#) & [operator=](#) (const [voms](#) &)
- [~voms](#) ()
- AC * [GetAC](#) ()
- std::vector< [attributelist](#) > & [GetAttributes](#) ()
- std::vector< std::string > [GetTargets](#) ()

Data Fields

- int [version](#)
- int [siglen](#)
- std::string [signature](#)
- std::string [user](#)
- std::string [userca](#)
- std::string [server](#)
- std::string [serverca](#)
- std::string [voname](#)
- std::string [uri](#)
- std::string [date1](#)
- std::string [date2](#)
- [data_type](#) type
- std::vector< [data](#) > [std](#)
- std::string [custom](#)
- std::vector< std::string > [fqan](#)
- std::string [serial](#)

Friends

- class [vomsdata](#)
- int [TranslateVOMS](#) (struct vomsdatar *vd, std::vector< [voms](#) > &v, int *error)

3.5.1 Detailed Description

Definition at line 78 of file voms_api.h.

3.5.2 Constructor & Destructor Documentation

3.5.2.1 `voms::voms (const voms &)`

3.5.2.2 `voms::voms ()`

3.5.2.3 `voms::~~voms ()`

3.5.3 Member Function Documentation

3.5.3.1 `AC* voms::GetAC ()`

3.5.3.2 `std::vector<attributelist>& voms::GetAttributes ()`

Generic attributes

3.5.3.3 `std::vector<std::string> voms::GetTargets ()`

3.5.3.4 `voms& voms::operator= (const voms &)`

3.5.4 Friends And Related Function Documentation

3.5.4.1 `int TranslateVOMS (struct vomsdatar * vd, std::vector< voms > & v, int * error)`
[friend]

3.5.4.2 `friend class vomsdata` [friend]

Definition at line 79 of file voms_api.h.

3.5.5 Field Documentation

3.5.5.1 `std::string voms::custom`

The [data](#) returned by an S command

Definition at line 93 of file voms_api.h.

3.5.5.2 `std::string voms::date1`

Beginning of validity of the user info

Definition at line 89 of file voms_api.h.

3.5.5.3 `std::string voms::date2`

End of validity of the user info

Definition at line 90 of file voms_api.h.

3.5.5.4 `std::vector<std::string> voms::fqan`

Keeps the [data](#) in the compact format

Definition at line 95 of file voms_api.h.

3.5.5.5 `std::string voms::serial`

Serial number. "0" if coming from non-ac

Definition at line 96 of file voms_api.h.

3.5.5.6 `std::string voms::server`

The VOMS server DN, as from its certificate

Definition at line 85 of file voms_api.h.

3.5.5.7 `std::string voms::serverca`

The CA which signed the VOMS certificate

Definition at line 86 of file voms_api.h.

3.5.5.8 `int voms::siglen`

The length of the VOMS server signature

Definition at line 81 of file voms_api.h.

3.5.5.9 `std::string voms::signature`

The VOMS server signature

Definition at line 82 of file voms_api.h.

3.5.5.10 `std::vector<data> voms::std`

User's characteristics

Definition at line 92 of file voms_api.h.

3.5.5.11 `data_type voms::type`

The type of [data](#) returned

Definition at line 91 of file voms_api.h.

3.5.5.12 `std::string voms::uri`

The URI of the VOMS server

Definition at line 88 of file voms_api.h.

3.5.5.13 std::string voms::user

The user's DN, as from his certificate

Definition at line 83 of file voms_api.h.

3.5.5.14 std::string voms::userca

The CA which signed the user's certificate

Definition at line 84 of file voms_api.h.

3.5.5.15 int voms::version

0 means [data](#) didn't originate from an AC

Definition at line 80 of file voms_api.h.

3.5.5.16 std::string voms::voname

The name of the VO to which the VOMS belongs

Definition at line 87 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.6 vomsdata Struct Reference

```
#include <voms_api.h>
```

Data Structures

- class **Initializer**

Public Member Functions

- [vomsdata](#) (std::string voms_dir="", std::string cert_dir="")
- bool [LoadSystemContacts](#) (std::string dir="")
- bool [LoadUserContacts](#) (std::string dir="")
- std::vector< [contactdata](#) > [FindByAlias](#) (std::string alias)
- std::vector< [contactdata](#) > [FindByVO](#) (std::string vo)
- void [Order](#) (std::string att)
- void [ResetOrder](#) (void)
- void [AddTarget](#) (std::string target)
- std::vector< std::string > [ListTargets](#) (void)
- void [ResetTargets](#) (void)
- std::string [ServerErrors](#) (void)
- bool [Retrieve](#) (X509 *cert, STACK_OF(X509)*chain, [recurse_type](#) how=RECURSE_CHAIN)
- bool [Contact](#) (std::string hostname, int port, std::string servsubject, std::string command)
- bool [ContactRaw](#) (std::string hostname, int port, std::string servsubject, std::string command, std::string &raw, int &version)
- void [SetVerificationType](#) ([verify_type](#) how)
- void [SetLifetime](#) (int lifetime)
- bool [Import](#) (std::string buffer)
- bool [Export](#) (std::string &data)
- bool [DefaultData](#) ([voms](#) &)
- std::string [ErrorMessage](#) (void)
- bool [RetrieveFromCtx](#) ([gss_ctx_id_t](#) context, [recurse_type](#) how)
- bool [RetrieveFromCred](#) ([gss_cred_id_t](#) credential, [recurse_type](#) how)
- bool [Retrieve](#) (X509_EXTENSION *ext)
- bool [RetrieveFromProxy](#) ([recurse_type](#) how)
- bool [Retrieve](#) (FILE *file, [recurse_type](#) how)
- [~vomsdata](#) ()
- [vomsdata](#) (const [vomsdata](#) &)
- void [SetRetryCount](#) (int retryCount)
- void [SetVerificationTime](#) (time_t)
- bool [LoadCredentials](#) (X509 *cert, STACK_OF(X509)*chain, EVP_PKEY *key)

Data Fields

- [verror_type](#) error
- std::vector< [voms](#) > data
- std::string workvo
- std::string extra_data

3.6.1 Detailed Description

Definition at line 169 of file voms_api.h.

3.6.2 Constructor & Destructor Documentation

3.6.2.1 vomsdata::vomsdata (std::string *voms_dir* = "", std::string *cert_dir* = "")

Parameters:

voms_dir The directory which contains the certificate of the VOMS server

cert_dir The directory which contains the certificate of the CA

If *voms_dir* is empty, the value of the environment variable X509_VOMS_DIR is taken.

If *cert_dir* is empty, the value of the environment variable X509_CERT_DIR is taken.

3.6.2.2 vomsdata::~vomsdata ()

3.6.2.3 vomsdata::vomsdata (const vomsdata &)

3.6.3 Member Function Documentation

3.6.3.1 void vomsdata::AddTarget (std::string *target*)

Adds a target to the AC.

Parameters:

target The target to be added. it should be a FQDN.

3.6.3.2 bool vomsdata::Contact (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*)

Contacts a VOMS server to get a certificate

It is the equivalent of the voms_proxy_init command, but without the --include functionality.

Parameters:

hostname FQDN of the VOMS server

port the port on which the VOMS server is listening

servsubject the subject of the server's certificate

command the command sent to the server

Returns:

failure (F) or success (T)

3.6.3.3 `bool vomsdata::ContactRaw (std::string hostname, int port, std::string servsubject, std::string & command, std::string & raw, int & version)`

Same as `Contact`, however it does not start the verification process, and the message received from the server is not parsed.

Parameters:

hostname FQDN of the VOMS server
port the port on which the VOMS server is listening
servsubject the subject of the server's certificate
command the command sent to the server
raw OUTPUT PARAMETER the answer from the server
version OUTPUT PARAMETER the version of the answer

Returns:

failure (F) or success (T)

3.6.3.4 `bool vomsdata::DefaultData (voms &)`

Get the default `data` extension from those present in the pseudo certificate

3.6.3.5 `std::string vomsdata::ErrorMessage (void)`

Gets a textual description of the error.

Returns:

A string containing the error message.

3.6.3.6 `bool vomsdata::Export (std::string & data)`

Exports `data` from `vomsdata::data` to the format used for inclusion into a certificate.

The function doesn't verify the `data`

Parameters:

`data` The certificate extension

Returns:

Failure (F) or Success (T)

3.6.3.7 `std::vector<contactdata> vomsdata::FindByAlias (std::string alias)`

Finds servers which share a common alias.

Parameters:

alias The alias to look for.

Returns:

The servers found. The order in which they are returned is unspecified.

3.6.3.8 `std::vector<contactdata> vomsdata::FindByVO (std::string vo)`

Finds servers which serve a common VO

Parameters:

vo The VO name to look for.

Returns:

The servers found. The order in which they are returned is unspecified.

3.6.3.9 `bool vomsdata::Import (std::string buffer)`

Converts [data](#) from the format used for inclusion into a certificate to the internal format

The function does verify the [data](#).

Parameters:

buffer contains the [data](#) to be converted

Returns:

Failure (F) or Success (T)

3.6.3.10 `std::vector<std::string> vomsdata::ListTargets (void)`

Returns the list of targets.

3.6.3.11 `bool vomsdata::LoadCredentials (X509 * cert, STACK_OF(X509)* chain, EVP_PKEY * key)`**3.6.3.12 `bool vomsdata::LoadSystemContacts (std::string dir = " ")`**

Loads the system wide configuration files.

Parameters:

dir The directory in which the files are stored.

If dir is empty, defaults to /opt/edg/etc/vomses.

Returns:

True if all went OK, false otherwise.

3.6.3.13 bool vomsdata::LoadUserContacts (std::string *dir* = " ")

Loads the user-specific configuration files.

Parameters:

dir The directory in which the files are stored.

If *dir* is empty, defaults to \$VOMS_USERCONF. If this is empty too, defaults to \$HOME/.edg/vomses, or to ~/.edg/vomses as a last resort.

Returns:

True if all went OK, false otherwise.

3.6.3.14 void vomsdata::Order (std::string *att*)

Sets up the ordering of the results.

Defines the ordering of the [data](#) returned by [Contact\(\)](#). Results are ordered in the same order as the calls to this function.

Parameters:

att The [attribute](#) to be ordered.

3.6.3.15 void vomsdata::ResetOrder (void)

Resets the ordering.

3.6.3.16 void vomsdata::ResetTargets (void)

Resets the target list.

3.6.3.17 bool vomsdata::Retrieve (FILE **file*, recurse_type *how*)

Gets VOMS information from a proxy saved as a file.

Parameters:

the file

how Recursion type

Returns:

failure (F) or success (T)

Note: Does NOT verify that the proxy is valid. Such verification must be obtained through other means.

3.6.3.18 **bool vomsdata::Retrieve (X509_EXTENSION * *ext*)**

Gets VOMS information from the given extension

Parameters:

ext The extension to parse.

Returns:

failure (F) or success (T)

3.6.3.19 **bool vomsdata::Retrieve (X509 * *cert*, STACK_OF(X509)* *chain*, recurse_type *how* = RECURSE_CHAIN)**

Extracts the VOMS extension from an X.509 certificate. The function doesn't check the validity of the certificates, but it does check the content of the user [data](#).

Parameters:

cert The certificate with the VOMS extensions

chain The chain of the validation certificates (only the intermediate ones)

how Recursion type

Returns:

failure (F) or success (T)

3.6.3.20 **bool vomsdata::RetrieveFromCred (gss_cred_id_t *credential*, recurse_type *how*)**

Gets VOMS information from the given globus credential

Parameters:

credential The credential from which to retrieve the certificate.

how Recursion type

Returns:

failure (F) or success (T)

3.6.3.21 **bool vomsdata::RetrieveFromCtx (gss_ctx_id_t *context*, recurse_type *how*)**

Gets VOMS information from the given globus context

Parameters:

context The context from which to retrieve the certificate.

how Recursion type

Returns:

failure (F) or success (T)

3.6.3.22 bool vomsdata::RetrieveFromProxy (recurse_type *how*)

Gets VOMS information from an existing globus proxy

Parameters:

how Recursion type

Returns:

failure (F) or success (T)

3.6.3.23 std::string vomsdata::ServerErrors (void)

Gets the error message returned by the server

3.6.3.24 void vomsdata::SetLifetime (int *lifetime*)

Set requested lifetime for the [Contact\(\)](#) call.

Parameters:

lifetime Requested lifetime, in seconds

3.6.3.25 void vomsdata::SetRetryCount (int *retryCount*)**3.6.3.26 void vomsdata::SetVerificationTime (time_t)****3.6.3.27 void vomsdata::SetVerificationType (verify_type *how*)**

Sets the type of verification done on the [data](#).

Parameters:

how The type of verification.

3.6.4 Field Documentation**3.6.4.1 std::vector<voms> vomsdata::data**

User's info, as in the certificate extension. It may contain [data](#) gathered from more than one VOMS server, Definition at line 316 of file voms_api.h.

3.6.4.2 verror_type vomsdata::error

Error code

Definition at line 188 of file voms_api.h.

3.6.4.3 `std::string vomsdata::extra_data`

The [data](#) specified by the user with the `--include` switch.

Note that this field doesn't contain the result of a request to the VOMS server, but instead [data](#) specified by the user.

The reason for the introduction of this extension is to let a user include important [data](#) into his proxy certificate, like, for example, a kerberos ticket

Definition at line 320 of file `voms_api.h`.

3.6.4.4 `std::string vomsdata::workvo`

The value of the `-vo` option of the `voms-proxy-init` command

Definition at line 319 of file `voms_api.h`.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

Chapter 4

File Documentation

4.1 voms_api.h File Reference

```
#include <fstream>
#include <string>
#include <vector>
#include <openssl/x509.h>
#include <openssl/bio.h>
#include <sys/types.h>
#include "newformat.h"
```

Data Structures

- struct [data](#)
User's characteristics: can be repeated.
- struct [attribute](#)
- struct [attributelist](#)
- struct [contactdata](#)
- struct [voms](#)
- struct [vomsdata](#)
- class [vomsdata::Initializer](#)

Typedefs

- typedef void * [gss_cred_id_t](#)
- typedef void * [gss_ctx_id_t](#)
- typedef bool(* [check_sig](#))(X509 *, void *, [verror_type](#) &)

Enumerations

- enum [data_type](#) { [TYPE_NODATA](#), [TYPE_STD](#), [TYPE_CUSTOM](#) }

The type of *data* returned.

- enum `recurse_type` { `RECURSE_CHAIN`, `RECURSE_NONE`, `RECURSE_DEEP` }
- enum `verify_type` {
`VERIFY_FULL` = 0xffffffff, `VERIFY_NONE` = 0x00000000, `VERIFY_DATE` = 0x00000001,
`VERIFY_TARGET` = 0x00000002,
`VERIFY_KEY` = 0x00000004, `VERIFY_SIGN` = 0x00000008, `VERIFY_ORDER` = 0x00000010,
`VERIFY_ID` = 0x00000020,
`VERIFY_CERTLIST` = 0x00000040 }
- enum `verror_type` {
`VERR_NONE`, `VERR_NOCKET`, `VERR_NOIDENT`, `VERR_COMM`,
`VERR_PARAM`, `VERR_NOEXT`, `VERR_NOINIT`, `VERR_TIME`,
`VERR_IDCHECK`, `VERR_EXTRINFO`, `VERR_FORMAT`, `VERR_NODATA`,
`VERR_PARSE`, `VERR_DIR`, `VERR_SIGN`, `VERR_SERVER`,
`VERR_MEM`, `VERR_VERIFY`, `VERR_TYPE`, `VERR_ORDER`,
`VERR_SERVERCODE`, `VERR_NOTAVAIL`, `VERR_FILE` }

Error codes.

Functions

- int `getMajorVersionNumber` (void)
- int `getMinorVersionNumber` (void)
- int `getPatchVersionNumber` (void)

4.1.1 Typedef Documentation

4.1.1.1 typedef bool(* check_sig)(X509 *, void *, verror_type &)

Definition at line 167 of file `voms_api.h`.

4.1.1.2 typedef void* gss_cred_id_t

Definition at line 25 of file `voms_api.h`.

4.1.1.3 typedef void* gss_ctx_id_t

Definition at line 26 of file `voms_api.h`.

4.1.2 Enumeration Type Documentation

4.1.2.1 enum data_type

The type of *data* returned.

Enumerator:

TYPE_NODATA no data
TYPE_STD group, role, capability triplet
TYPE_CUSTOM result of an S command

Definition at line 59 of file voms_api.h.

4.1.2.2 enum recurse_type**Enumerator:**

RECURSE_CHAIN
RECURSE_NONE
RECURSE_DEEP

Definition at line 120 of file voms_api.h.

4.1.2.3 enum verify_type**Enumerator:**

VERIFY_FULL
VERIFY_NONE
VERIFY_DATE
VERIFY_TARGET
VERIFY_KEY
VERIFY_SIGN
VERIFY_ORDER
VERIFY_ID
VERIFY_CERTLIST

Definition at line 126 of file voms_api.h.

4.1.2.4 enum verror_type

Error codes.

Enumerator:

VERR_NONE
VERR_NOSOCKET Socket problem
VERR_NOIDENT Cannot identify itself (certificate problem)
VERR_COMM Server problem
VERR_PARAM Wrong parameters
VERR_NOEXT VOMS extension missing
VERR_NOINIT Initialization error
VERR_TIME Error in time checking

VERR_IDCHECK User [data](#) in extension different from the real ones
VERR_EXTRAINFO VO name and URI missing
VERR_FORMAT Wrong [data](#) format
VERR_NODATA Empty extension
VERR_PARSE Parse error
VERR_DIR Directory error
VERR_SIGN Signature error
VERR_SERVER Unidentifiable VOMS server
VERR_MEM Memory problems
VERR_VERIFY Generic verification error
VERR_TYPE Returned [data](#) of unknown type
VERR_ORDER Ordering different than required
VERR_SERVERCODE Error message from the server
VERR_NOTAVAIL Method not available
VERR_FILE Error reading [data](#) from file

Definition at line 140 of file voms_api.h.

4.1.3 Function Documentation

4.1.3.1 `int getMajorVersionNumber (void)`

4.1.3.2 `int getMinorVersionNumber (void)`

4.1.3.3 `int getPatchVersionNumber (void)`

Index

- ~voms
 - voms, [12](#)
- ~vomsgdata
 - vomsgdata, [16](#)
- AddTarget
 - vomsgdata, [16](#)
- attribute, [5](#)
 - name, [5](#)
 - qualifier, [5](#)
 - value, [5](#)
- attributelist, [7](#)
 - attributes, [7](#)
 - grantor, [7](#)
- attributes
 - attributelist, [7](#)
- cap
 - data, [10](#)
- check_sig
 - voms_api.h, [24](#)
- Contact
 - vomsgdata, [16](#)
- contact
 - contactdata, [8](#)
- contactdata, [8](#)
 - contact, [8](#)
 - host, [8](#)
 - nick, [8](#)
 - port, [8](#)
 - version, [8](#)
 - vo, [8](#)
- ContactRaw
 - vomsgdata, [16](#)
- custom
 - voms, [12](#)
- data, [10](#)
 - cap, [10](#)
 - group, [10](#)
 - role, [10](#)
 - vomsgdata, [21](#)
- data_type
 - voms_api.h, [24](#)
- date1
 - voms, [12](#)
- date2
 - voms, [12](#)
- DefaultData
 - vomsgdata, [17](#)
- error
 - vomsgdata, [21](#)
- ErrorMessage
 - vomsgdata, [17](#)
- Export
 - vomsgdata, [17](#)
- extra_data
 - vomsgdata, [21](#)
- FindByAlias
 - vomsgdata, [17](#)
- FindByVO
 - vomsgdata, [18](#)
- fqn
 - voms, [12](#)
- GetAC
 - voms, [12](#)
- GetAttributes
 - voms, [12](#)
- getMajorVersionNumber
 - voms_api.h, [26](#)
- getMinorVersionNumber
 - voms_api.h, [26](#)
- getPatchVersionNumber
 - voms_api.h, [26](#)
- GetTargets
 - voms, [12](#)
- grantor
 - attributelist, [7](#)
- group
 - data, [10](#)
- gss_cred_id_t
 - voms_api.h, [24](#)
- gss_ctx_id_t
 - voms_api.h, [24](#)
- host
 - contactdata, [8](#)

- Import
 - vomsdata, [18](#)
- ListTargets
 - vomsdata, [18](#)
- LoadCredentials
 - vomsdata, [18](#)
- LoadSystemContacts
 - vomsdata, [18](#)
- LoadUserContacts
 - vomsdata, [18](#)
- name
 - attribute, [5](#)
- nick
 - contactdata, [8](#)
- operator=
 - voms, [12](#)
- Order
 - vomsdata, [19](#)
- port
 - contactdata, [8](#)
- qualifier
 - attribute, [5](#)
- RECURSE_CHAIN
 - voms_api.h, [25](#)
- RECURSE_DEEP
 - voms_api.h, [25](#)
- RECURSE_NONE
 - voms_api.h, [25](#)
- recurse_type
 - voms_api.h, [25](#)
- ResetOrder
 - vomsdata, [19](#)
- ResetTargets
 - vomsdata, [19](#)
- Retrieve
 - vomsdata, [19](#), [20](#)
- RetrieveFromCred
 - vomsdata, [20](#)
- RetrieveFromCtx
 - vomsdata, [20](#)
- RetrieveFromProxy
 - vomsdata, [20](#)
- role
 - data, [10](#)
- serial
 - voms, [13](#)
- server
 - voms, [13](#)
- serverca
 - voms, [13](#)
- ServerErrors
 - vomsdata, [21](#)
- SetLifetime
 - vomsdata, [21](#)
- SetRetryCount
 - vomsdata, [21](#)
- SetVerificationTime
 - vomsdata, [21](#)
- SetVerificationType
 - vomsdata, [21](#)
- siglen
 - voms, [13](#)
- signature
 - voms, [13](#)
- std
 - voms, [13](#)
- TranslateVOMS
 - voms, [12](#)
- type
 - voms, [13](#)
- TYPE_CUSTOM
 - voms_api.h, [25](#)
- TYPE_NODATA
 - voms_api.h, [25](#)
- TYPE_STD
 - voms_api.h, [25](#)
- uri
 - voms, [13](#)
- user
 - voms, [13](#)
- userca
 - voms, [14](#)
- value
 - attribute, [5](#)
- VERIFY_CERTLIST
 - voms_api.h, [25](#)
- VERIFY_DATE
 - voms_api.h, [25](#)
- VERIFY_FULL
 - voms_api.h, [25](#)
- VERIFY_ID
 - voms_api.h, [25](#)
- VERIFY_KEY
 - voms_api.h, [25](#)
- VERIFY_NONE
 - voms_api.h, [25](#)
- VERIFY_ORDER
 - voms_api.h, [25](#)
- VERIFY_SIGN

- voms_api.h, 25
- VERIFY_TARGET
 - voms_api.h, 25
- verify_type
 - voms_api.h, 25
- VERR_COMM
 - voms_api.h, 25
- VERR_DIR
 - voms_api.h, 26
- VERR_EXTRAINFO
 - voms_api.h, 26
- VERR_FILE
 - voms_api.h, 26
- VERR_FORMAT
 - voms_api.h, 26
- VERR_IDCHECK
 - voms_api.h, 25
- VERR_MEM
 - voms_api.h, 26
- VERR_NODATA
 - voms_api.h, 26
- VERR_NOEXT
 - voms_api.h, 25
- VERR_NOIDENT
 - voms_api.h, 25
- VERR_NOINIT
 - voms_api.h, 25
- VERR_NONE
 - voms_api.h, 25
- VERR_NOSOCKET
 - voms_api.h, 25
- VERR_NOTAVAIL
 - voms_api.h, 26
- VERR_ORDER
 - voms_api.h, 26
- VERR_PARAM
 - voms_api.h, 25
- VERR_PARSE
 - voms_api.h, 26
- VERR_SERVER
 - voms_api.h, 26
- VERR_SERVERCODE
 - voms_api.h, 26
- VERR_SIGN
 - voms_api.h, 26
- VERR_TIME
 - voms_api.h, 25
- VERR_TYPE
 - voms_api.h, 26
- VERR_VERIFY
 - voms_api.h, 26
- verror_type
 - voms_api.h, 25
- version
 - voms_api.h, 25
- contactdata, 8
- voms, 14
- vo
 - contactdata, 8
- voms, 11
 - ~voms, 12
 - custom, 12
 - date1, 12
 - date2, 12
 - fqan, 12
 - GetAC, 12
 - GetAttributes, 12
 - GetTargets, 12
 - operator=, 12
 - serial, 13
 - server, 13
 - serverca, 13
 - siglen, 13
 - signature, 13
 - std, 13
 - TranslateVOMS, 12
 - type, 13
 - uri, 13
 - user, 13
 - userca, 14
 - version, 14
 - voms, 12
 - vomsdata, 12
 - voname, 14
- voms_api.h
 - RECURSE_CHAIN, 25
 - RECURSE_DEEP, 25
 - RECURSE_NONE, 25
 - TYPE_CUSTOM, 25
 - TYPE_NODATA, 25
 - TYPE_STD, 25
 - VERIFY_CERTLIST, 25
 - VERIFY_DATE, 25
 - VERIFY_FULL, 25
 - VERIFY_ID, 25
 - VERIFY_KEY, 25
 - VERIFY_NONE, 25
 - VERIFY_ORDER, 25
 - VERIFY_SIGN, 25
 - VERIFY_TARGET, 25
 - VERR_COMM, 25
 - VERR_DIR, 26
 - VERR_EXTRAINFO, 26
 - VERR_FILE, 26
 - VERR_FORMAT, 26
 - VERR_IDCHECK, 25
 - VERR_MEM, 26
 - VERR_NODATA, 26
 - VERR_NOEXT, 25

- VERR_NOIDENT, 25
- VERR_NOINIT, 25
- VERR_NONE, 25
- VERR_NOSOCKET, 25
- VERR_NOTAVAIL, 26
- VERR_ORDER, 26
- VERR_PARAM, 25
- VERR_PARSE, 26
- VERR_SERVER, 26
- VERR_SERVERCODE, 26
- VERR_SIGN, 26
- VERR_TIME, 25
- VERR_TYPE, 26
- VERR_VERIFY, 26
- voms_api.h, 23
 - check_sig, 24
 - data_type, 24
 - getMajorVersionNumber, 26
 - getMinorVersionNumber, 26
 - getPatchVersionNumber, 26
 - gss_cred_id_t, 24
 - gss_ctx_id_t, 24
 - recurse_type, 25
 - verify_type, 25
 - verror_type, 25
- vomsdata, 15
 - ~vomsdata, 16
 - AddTarget, 16
 - Contact, 16
 - ContactRaw, 16
 - data, 21
 - DefaultData, 17
 - error, 21
 - ErrorMessage, 17
 - Export, 17
 - extra_data, 21
 - FindByAlias, 17
 - FindByVO, 18
 - Import, 18
 - ListTargets, 18
 - LoadCredentials, 18
 - LoadSystemContacts, 18
 - LoadUserContacts, 18
 - Order, 19
 - ResetOrder, 19
 - ResetTargets, 19
 - Retrieve, 19, 20
 - RetrieveFromCred, 20
 - RetrieveFromCtx, 20
 - RetrieveFromProxy, 20
 - ServerErrors, 21
 - SetLifetime, 21
 - SetRetryCount, 21
 - SetVerificationTime, 21
 - SetVerificationType, 21
 - voms, 12
 - vomsdata, 16
 - workvo, 22
- voname
 - voms, 14
- workvo
 - vomsdata, 22