



---

30/3/2005

## Extended Resource Specification Language Reference Manual

Refers to ARC release series 0.4 and up



# Contents

1	Introduction	5
2	xRSL syntax and rules	7
2.1	Syntax . . . . .	7
2.2	URLs . . . . .	7
3	Attributes	11
3.1	User-side attributes . . . . .	11
	executable . . . . .	11
	arguments . . . . .	11
	inputFiles . . . . .	12
	executables . . . . .	12
	cache . . . . .	12
	outputFiles . . . . .	13
	cpuTime . . . . .	13
	gridTime . . . . .	14
	memory . . . . .	14
	disk . . . . .	14
	runTimeEnvironment . . . . .	14
	middleware . . . . .	15
	stdin . . . . .	15
	stdout . . . . .	15
	stderr . . . . .	16
	join . . . . .	16
	gmlog . . . . .	16
	jobName . . . . .	16
	ftpThreads . . . . .	16
	acl . . . . .	17
	cluster . . . . .	17
	queue . . . . .	17
	startTime . . . . .	18
	lifeTime . . . . .	18
	notify . . . . .	18

replicaCollection . . . . .	18
rerun . . . . .	19
architecture . . . . .	19
nodeAccess . . . . .	19
dryRun . . . . .	19
rsl_substitution . . . . .	19
environment . . . . .	20
count . . . . .	20
jobreport . . . . .	20
3.2 GM-side attributes . . . . .	20
sstdin . . . . .	20
action . . . . .	21
savestate . . . . .	21
lrmstype . . . . .	21
hostName . . . . .	21
jobid . . . . .	21
3.3 Unsupported Globus RSL attributes . . . . .	22
3.3.1 Unsupported RSL 1.0 attributes . . . . .	22
3.3.2 Unsupported GRAM RSL attributes . . . . .	22
A Examples . . . . .	25
A.1 User-side xRSL script . . . . .	25
A.2 GM-side xRSL script . . . . .	26

# Chapter 1

## Introduction

Execution of jobs at batch clusters is the major part of the data analysis, production and other computational tasks and applications in many research areas. In the Grid infrastructure [1], such clusters are not necessarily local to a job submission site, but can be widely distributed. This implies extra requirements for the proper description of job options. The Globus project [2] developed a Grid middleware toolkit, which makes use of the Resource Specification Language (RSL)[3] to parse job options and definitions to resource management systems. The NorduGrid project [4] developed the Advanced Resource Connector (ARC), { a solution [5, 6] for a Grid facility, suitable for complex tasks, like, for example, a High Energy Physics production. To match the complexity of such tasks, this solution requires certain extensions to the RSL.

To describe a task to be submitted to the ARC-enabled resources, an extended version of the Globus RSL is used. The extensions concern not only introduction of new attributes, but also differentiation between two levels of the job options specifications:

User-side RSL , i.e., the set of attributes specified by a user in a job-specific file. This file is interpreted by the User Interface (UI) [7], and after the necessary modifications is parsed to the Grid Manager (GM) [8]

GM-side RSL , i.e., the set of attributes pre-processed by the UI, and ready to be interpreted by the GM

A user only has to know the user-side part, and utilize it to describe the Grid tasks. The Grid Manager, however, uses slightly different notations, supplied by the User Interface.

In what follows, the description of the NorduGrid-extended RSL, further denoted as xRSL , is given, using the following notations:

<xxxx>	parameter to be substituted with a corresponding string or a number
[xxxx]	optional parameter
xxx yyy zzz	list of possible values of a parameter
-"-	"same as above"



## Chapter 2

# xRSL syntax and rules

For a complete description of Globus RSL, see reference [3]. xRSL uses the same syntax conventions, although changes the meaning and interpretation of some attributes.

### 2.1 Syntax

A Grid task is described by the mean of xRSL attributes, which can be either parsed via a command-line, or, more conveniently, be collected a so-called xRSL- le (suggested extension `xrsl`). Such a le contains a plain list of attribute strings and boolean operands `\&` (for AND) and `\ |` (for OR).

Typically, an xRSL job description starts with an ampersand (`\&`) , to indicate implicit conjunction of all the attributes:

```
&(attribute1=value1)(attribute2=value2)...
```

Whenever a disjunct -request of two or more attributes is needed, the following construction can be used:

```
(|(attribute=value1)(attribute=value2)...)...
```

In expressions, the following operands are allowed:

```
= != > < >= <=
```

Commented lines should start with `\("` and be closed with `\*)`:

```
(*attribute=value1*)
```

Multiple job description in one le is realized via a standard Globus RSL multi-request operand `\+`, which should precede multiple job description:

```
+(\&(...))(\&(...))(\&(...))
```

The xRSL attributes can be written in a single string, or split in lines arbitrary; blank spaces between and inside (attribute=value) relations are ignored.

### 2.2 URLs

File locations in ARC can be specified both as local le names, and as Internet standard Uniform Resource Locators (URL) . However, there are some additional options, used by the Grid Manager. Detailed information is maintained in the ARC URL documentation [9].

The following transfer protocols and metadata servers are supported:

```

ftp { ordinary File Transfer Protocol (FTP)
gsiftp { GridFTP, the Globus-enhanced FTP
http { ordinary Hyper-Text Transfer Protocol (HTTP)
https { HTTP with SSL v3
httpg { HTTP with Globus GSI
ldap { ordinary Lightweight Data Access Protocol (LDAP) [10]
rc { Globus Replica Catalog (RC) [11]
rls { Globus/EDG Replica Location Service (RLS) [12]
se { ARC Smart Storage Element service [13]
file { local to the host le name with a full path

```

An URL can be used in a standard form, i.e.

```
<protocol>://host[:port]/<file>
```

Or, to enhance the performance, it can have additional options:

```
<protocol>://host[:port][;option[:option[...]]]/<file>
```

For a metadata service URL, construction is the following:

```

rc://rc://[location[location[...]]@]<host>[:port]/<DN>/<lfn>
rls://url[url[...]]@<host>[:port]/<lfn>

```

For the Smart Storage Element service, the syntax is

```
se://host[:port][;options]/path[?file_id]
```

Here the URL components are:

location	<location_name_in_RC>[:option[:option[...]]]
host[:port]	IP address of a server
DN	Distinguished Name (as in LDAP) of an RC collection
lfn	Logical File Name
url	URL of the le as registered in RLS
file	local to the host le name with a full path

The following options are supported:

threads=<number>	speci es number of parallel streams to be used by GridFTP or HTTP(s,g); default value is 1, maximal value is 10
cache=yes no	indicates whether the GM should cache the le; default is yes for transfers to local destinations
readonly=yes no	for transfers to local destinations (e.g., cache), speci es whether the le should be read-only (unmodi able); default is yes
secure=yes no	indicates whether the GridFTP data channel should be encrypted; default is no
blocksize=<number>	speci es size of chunks/blocks/bu ers used in GridFTP or HTTP(s,g) transactions; default is protocol dependent
checksum=cksum md5	speci es the algorithm for checksum to be computed (ev. provided to the indexing server)



Local files are referred by specifying either location relative to the job submission working directory, or by an absolute path (the one that starts with "/"), preceded with a "file://" prefix.

Examples of URLs are:

`http://grid.domain.org/dir/script.sh`

`gsiftp://grid.domain.org:2811;threads=10/dir/input_12378.dat`

`ldap://grid.domain.org:389/dc=collection1,rc=Nordugrid,dc=nordugrid,dc=org`

`rc://grid.domain.org/dc=collection1,rc=Nordugrid,dc=nordugrid,dc=org/zebra/f1.zebra`

`file:///home/auser/griddir/steer.cra`



## Chapter 3

# Attributes

Most of the attributes introduced by Globus are supported, some with modifications as indicated in this document. Several new attributes are introduced, of which some are to be specified in the user's script, and others are internal for the GM (are added or modified by the UI).

Attribute names are case-insensitive, although assigned values may well be case-sensitive, if they represent file names, environment variables etc.

### 3.1 User-side attributes

The following attributes can be specified in a user's xRSL script. Some are to be modified by the UI before being passed to the GM.

#### executable

User input: (executable=<string>)  
GM input: (executable=/bin/echo)  
Example: (executable="local\_to\_job.exe")

The executable to be submitted as a main task to a Local Resource Management System (LRMS).

string file name (including path), local to the computing element (CE)

If an executable has to be transferred from the submission node, it has to be specified in the inputFiles list, otherwise it will be added to that list by the UI.

If the file name starts with a leading slash ("/"), it is considered to be the full path to the executable at a CE; otherwise the location of the file is relative to the session directory (where job input and files are stored). If the file name starts with an environment variable ("\${...}"), the value of this variable is resolved locally, but if it is enclosed in double quotes, it will be resolved at the remote computing element: (executable=\${ROOT\_DIR}/myprog.exe) { \$ROOT\_DIR is resolved locally (will cause errors if the path does not exist at the execution machine)  
(executable="\${ROOT\_DIR}/myprog.exe") { \$ROOT\_DIR will be resolved remotely

For internal GM use, the UI creates a dummy executable attribute with, e.g., /bin/echo as an argument (unless the specified executable itself starts with /). The actual executable is transferred by the UI to lists in the arguments, inputFiles and executables internal GM attributes.

#### arguments

User input: (arguments=<string> [string] ... )  
 GM input: (arguments=<executable> <string> [string] ... )  
 Example: (arguments="10000" \$(ATLAS)/input.dat)

List of the arguments for the executable.

string	an argument
executable	the executable to be run by LRMS, taken by the UI from the user-specified executable attribute

### inputFiles

User input: (inputFiles=(<filename> <location>) ... )  
 GM input: (inputFiles=(<filename> <URL>  
                   (<filename> [size][.checksum]) ... )  
 Example: (inputFiles=("local\_to\_job" `gsiftp://grid.quark.lu.se/scratch/remote\_one")  
                   ("local\_to\_job.dat" `/scratch/local\_to\_me.dat")  
                   ("same\_name\_as\_in\_my\_current\_dir" `"))

List of files to be copied to the computing element before the execution.

filename	file name, local to the computing element and always relative to the session directory
location	location of the file (gsiftp, https, ftp, http URLs, or a path, local to the submission node). If void ("", use the quotes!), the input file is taken from the submission directory.
URL	URL of the file (see Section 2.2)
size	file size in bytes
checksum	file checksum (as returned by cksum)

If the list does not contain the standard input file (as specified by stdin) and/or the executable file (as specified by executable if the given name), the UI appends these files to the list. If the <location> is a URL, it is passed by the UI to the GM without changes; if it is a local path (or void, ""), the UI converts it to <size> and <checksum> and uploads those files to the execution cluster.

### executables

User input: (executables=<string> [string] ...)  
 GM input: -"-  
 Example: (executables=myscript.sh myjob.exe)

List of files from the inputFiles set, which will be given executable permissions.

string	file name, local to the computing element and relative to the session directory
--------	---

If the executable file (as specified in executable and is relative to the session directory) is not listed, it will be added to the list by the UI.

### cache

User input: (cache=yes|no)  
 GM input: -"-  
 Example: (cache=yes)

Specifies whether input files specified in the `inputFiles` should be placed by default in the cache or not. This does not affect files described by the `executable`, which will be placed in the session directory always.

If not specified, default value is `\yes`.

#### outputFiles

User input: `(outputFiles=<string> <URL> ... )`

GM input: `-"-`

Example: `(outputFiles=(`local_to_job.dat" ``gsiftp://grid.uio.no/storage/stored.dat")  
 (`local_to_job.res" ``rc://grid.fi.uib.no/group1/stored_and_registered.res")  
 (`local_to_job_dir/" ``")) )`

List of files to be retrieved by the user or uploaded by the GM and registered in a Replica Catalog or RLS.

- string file name, local to the Computing Element (CE). If this string ends with a backslash `\` and `<URL>` is empty, the entire directory is being kept.
- URL URL of the remote file (see Section 2.2); if void (`""`, use the quotes!), the file is kept for manual retrieval. Note that this can not be a local file:// URL.

Using a RC pseudo-URL (see Section 2.2), you should make sure that the location is already defined in the RC. If more than one such location is specified, only those found in the RC for this collection will be used. GM will store output files in one location only: the first randomly picked location that exists. If no locations are specified, all found in the RC for this collection will be tried.

If in RC pseudo-URL the `componenthost[:port]/DN` is not specified, the one given in `thereplicaCollection` attribute is used.

If the list does not contain standard output and/or standard error files (as specified by `stdout/stderr`), the UI appends these file names to the list. If the `<URL>` is not specified (void, `""`, use the quotes!), files will be kept on SE and should be downloaded by the user via the UI. If specified name of file ends with `\`, the entire directory is kept.

A convenient way to keep the entire job directory at the remote site for a manual retrieval is to specify `(outputfiles=("/" ""))`.

#### cpuTime

User input: `(cpuTime=<time>)`

GM input: `-"-`

Example: `(cpuTime=240)`

Maximal CPU time request for the job.

time time (minutes)

If only number is specified, the time is assumed to be minutes. Otherwise, a free format is accepted, i.e., any of the following will be interpreted properly (make sure to enclose such strings in quotes!):

```

``1 week"
``3 days"
``2 days, 12 hours"
``1 hour, 30 minutes"
``36 hours"
``9 days"
``240 minutes"

```

This attribute should be used to direct the job to a system with sufficient CPU resources, typically, a batch queue with the sufficient upper time limit. Jobs exceeding this maximum most likely will be terminated by remote systems! If the `cpuTime` is not specified, the limit is not set and jobs can run as long as the system settings allow (note that in this case you can not avoid queues with too short time limits).

### gridTime

User input: (gridTime=<time>)  
 GM input: none  
 Example: (gridTime="2 h")

Maximal CPU time request for the job scaled to the 2.8 GHz Intel® Pentium® 4 processor.

time      time (minutes)

The attribute is completely analogous to `cpuTime`, except that it will be recalculated to the actual CPU time request for each queue, depending on the published processor clock speed.

### memory

User input: (memory=<integer>)  
 GM input: -"-  
 Example: (memory>=500)

Memory required for the job.

integer      size (Mbytes)

### disk

User input: (disk=<integer>)  
 GM input: -"-  
 Example: (disk=500)

Disk space required for the job.

integer      disk space, Mbytes

### runTimeEnvironment

User input: (runTimeEnvironment=<string>)

GM input: -"

Example: (runTimeEnvironment=Atlas-1.1.0)

Required runtime environment

string environment name

The site to submit the job to will be chosen by the UI among those advertising specified runtime environments. Before starting the job, the GM will set up environment variables and paths according to those requested.

To request several environments, repeat the attribute string:

(runTimeEnvironment=ENV1)(runTimeEnvironment=ENV2) etc.

Before being submitted to the GM, a grouping is done by the UI, e.g. (runTimeEnvironment=ENV1 ENV2)

To make a disjunct-request, use a boolean expression:

(!(runTimeEnvironment=env1)(runTimeEnvironment=env2)) .

Runtime environment string interpretation is case-insensitive. If a runtime environment string consists of a name and a version number, a partial specification is possible: it is sufficient to request only the name.

Use the \>=" operator to request a version \equal or higher".

#### middleware

User input: (middleware=<string>)

GM input: -"

Example: (middleware=NorduGrid-0.3.99)

Required middleware.

string Grid middleware name.

The site to submit the job to will be chosen by the UI among those advertising specified middleware. Usage is identical to that of the runTimeEnvironment . Use the \>=" operator to request a version \equal or higher". Request (middleware=nordugrid) defaults to (middleware>=nordugrid-0.0.0.0) .

#### stdin

User input: (stdin=<string>)

GM input: -"

Example: (stdin=myinput.dat)

The standard input file.

string file name, local to the computing element

The standard input file should be listed in the inputFiles attribute; otherwise it will be forced to that list by the UI.

#### stdout

User input: (stdout=<string>)

GM input: -"

Example: (stdout=myoutput.txt)

The standard output file.

string     le name, local to the computing element and relative to the session directory.

The standard output le should be listed in the `outputFiles` attribute; otherwise it will be forced to that list by the UI. If the standard output is not defined, UI assigns a name.

#### stderr

User input: (stderr=<string>)

GM input:    "-"

Example:     (stderr=myjob.err)

The standard error le.

string     le name, local to the computing element and relative to the session directory.

The standard error le should be listed as an `outputFiles` attribute; otherwise it will be forced to that list by the UI. If the standard error is not defined, UI assigns a name.

#### join

User input: (join=yes|no)

GM input:    "-"

Example:     (join=yes)

If "yes", joins `stderr` and `stdout` les into the `stdout` one. Default is no.

#### gmlog

User input: (gmlog=<string>)

GM input:    "-"

Example:     (gmlog=myjob.log)

The job log le, containing all the job-related messages from the GM.

string     le name, local to the computing element and relative to the session directory

The job log le should be listed as an `outputFiles` attribute; otherwise it will be forced to that list by the UI.

#### jobName

User input: (jobName=<string>)

GM input:    "-"

Example:     (jobName=MyJob)

User-specified job name.

string     job name

This name is meant for convenience of the user. It can be used to select the job while using the UI. It is also available through the Information System.



**ftpThreads**

User input: (ftpThreads=<integer>)

GM input: -"-

Example: (ftpThreads=4)

Defines how many parallel streams will be used by the GM during transfers of files.

integer a number from 1 to 10

If not specified, parallelism is not used.

**acl**

Available in ARC v0.5.12 and higher

User input: (acl=<xml>)

GM input: -"-

Example: (acl="<?xml version='1.0'>  
 <gac version='0.0.1'><entry><any-user></any-user>  
 <allow><write/><read/><list/><admin/></allow></entry></gac>")

Makes use of GACL [14] rules to list users who are allowed to access and control job in addition to job's owner. Access and control levels are specified per user. any-user tag refers to any user authorized at the execution cluster. To get more information about GACL please refer to <http://www.gridsite.org>.

xml a GACL-compliant XML string defining access control list

Following job control levels can be specified via acl :

write	{	allows to modify contents of job data (job directory) and control job (cancel, clean, etc.)
read	{	allows to read content of job data (contents of job directory)
list	{	allows to list files available for the job (contents of job directory)
admin	{	allows to do everything { full equivalence to job ownership

**cluster**

User input: (cluster=<string>)

GM input: -"-

Example: (cluster=nbi)

The name of the execution cluster.

string known cluster name, or a substring of it

Use this attribute to explicitly force job submission to a cluster, or to avoid such. The job will not be submitted if the cluster does not satisfy other requirements of the job. Disjunct-requests of the kind ((cluster=clus1)(cluster=clus2)) are supported. To exclude a cluster, use (cluster!=clus3).

**queue**

User input: (queue=<string>)

GM input: -"-

Example: (queue=pclong)

The name of the remote batch queue.

string      known queue name

Use this attribute to explicitly force job submission to a queue.

### startTime

User input: (startTime=<time>)

GM input: (startTime=<tttt>)

Example: (startTime="2002-05-25 21:30")

Time to start job processing.

time      time string, YYYY-MM-DD hh:mm:ss

tttt      time string, YYYYMMDDhhmmss[Z] (converted by the UI from time )

### lifeTime

User input: (lifeTime=<time>)

GM input: (lifeTime=<tttt>)

Example: (lifeTime=60)

Maximal time to keep job les (the session directory) on the gatekeeper upon job completion.

time      time (days)

tttt      time (seconds, converted by the UI fromtime )

Typical life time is 1 day (24 hours). Speci ed life time can not exceed local settings.

### notify

User input: (notify=<string> [string] ... )

GM input: -"-

Example: (notify="be your.name@your.domain.com")

Request e-mail noti cations on job status change.

string      string of the format: [b][q][f][e][c] user1@domain1 [user2@domain2] ...

here ags indicating the job status are:

b { begin (PREPARING)

q { queued (INLRMS)

f { nalizing (FINISHING)

e { end (FINISHED)

c { cancellation (CANCELLED)

d { deleted (DELETED)

No more than 3 e-mail addresses per status change accepted.

### replicaCollection

User input: (replicaCollection=<URL>)

GM input: -"

Example: (replicaCollection="ldap://grid.uio.no:389/lc=TestCollection,  
rc=NorduGrid,nordugrid,dc=org")

Location of a logical collection in the Replica Catalog.

URL LDAP directory specified as an URL (ldap://host[:port]/dn )

#### rerun

User input: (rerun=<integer>)

GM input: -"

Example: (rerun=2)

Number of reruns (if a system failure occurs).

integer an integer number

If not specified, the default is 0. Default maximal allowed value is 2.

#### architecture

User input: (architecture=<string>)

GM input:

Example: (architecture=i686)

Request a specific architecture.

string architecture (e.g., as produced by `uname -a`)

#### nodeAccess

User input: (nodeAccess=inbound|outbound)

GM input:

Example: (nodeAccess=inbound)

Request cluster nodes with inbound or outbound IP connectivity. If both are needed, a conjunct request should be specified.

#### dryRun

User input: (dryRun=yes|no)

GM input: -"

Example: (dryRun=yes)

If "yes", do dry-run: RSL is parsed, but no job submission to LRMS is made. Should be used for xRSL validation.

#### rsl\_substitution

User input: (rsl\_substitution=(<string1> <string2>))

GM input: -"

Example: (rsl\_substitution=(ATLAS /opt/atlas))

Substitutes <string2> with <string1> for internal RSL use.

string1 new internal RSL variable

string2 any string, e.g., existing combination of variables or a path

Use this attribute to simplify xRSL editing. Only one pair per substitution is allowed. To request several substitution, concatenate such requests. Bear in mind that substitution must be defined prior to actual use of a new variable string1 .

### environment

User input: (environment=(<VAR> <string>) [(<VAR> <string>)] ... )

GM input: -"

Example: (environment=(ATLSRC /opt/atlas/src)  
(ALISRC /opt/alice/src))

Defines execution shell environment variables.

VAR new variable name

string any string, e.g., existing combination of variables or a path

Use this to define variables at an execution site.

### count

User input: (count=<integer>)

GM input: -"

Example: (count=4)

Specifies amount of sub-jobs to be submitted for parallel tasks.

### jobreport

User input: (jobreport=<URL>)

GM input: -"

Example: (jobreport="https://grid.uio.no:8001/logger")

Specifies an URL for a logging service to send reports about job to. The default is set up in the cluster configuration.

URL URL

It is up to a user to make sure the requested logging service accepts reports from the set of clusters she intends to use.

## 3.2 GM-side attributes

The following attributes are constructed by the UI and are parsed to the GM, although users may specify them manually (not advised! ).

**sstdin**

User input:

GM input: (sstdin=<filename>)

Example: (sstdin=myinput.dat)

Internal attribute for the standard input. Can also be spelled stdin .

filename    standard input    le name

**action**

User input:

GM input: (action=request|cancel|clean)

Example: (action=request)

Action to be taken by the gatekeeper: submit the job, cancel job execution, or clear the results of the job (also cancels the job).

**savestate**

User input:

GM input: (savestate=yes|no)

Example: (savestate=yes)

If "yes", input RSL is stored in a temporary le at the gatekeeper. Must be always set as "yes" in the current implementation.

**lrmstype**

User input:

GM input: (lrmstype=<string>)

Example: (lrmstype=pbs)

LRMS type, indicating which submission script is to be invoked.

string    LRMS type (at the moment, only "pbs" is supported)

**hostName**

User input:

GM input: (hostname=<string>)

Example: (hostName=grid.quark.lu.se)

Submission host name.

string    host name, as passed by the UI

**jobid**

User input:

GM input: (jobid=<string>)

Example: (jobid=grid.quark.lu.se:2119/jobmanager-ng/15711.1017133827)

Unique job identification string, needed for cancellation and clean-up.

string      global job ID

It can also be provided during submission of the job and should be unique to a computing element (cluster).

### 3.3 Unsupported Globus RSL attributes

The following Globus attributes are not supported by the ARC middleware. Whenever they are specified, a warning is issued by the UI, and the corresponding attribute is ignored.

#### 3.3.1 Unsupported RSL 1.0 attributes

```
(resourceManagerContact=<string>)
(directory=<string>)
(maxCpuTime=<time>)
(maxWallTime=<time>)
(maxTime=<time>)
(maxMemory=<memory>)
(minMemory=<memory>)
(gramMyJob=independent|collective)
(project=<string>)
(hostCount=<number>)
(label=<string>)
(subjobCommsType=blocking-join|independent)
(subjobStartType=strict-barrier|loose-barrier|no-barrier)
```

#### 3.3.2 Unsupported GRAM RSL attributes

```
(directory=<string>)
(fileCleanUp=<array>)
(fileStageIn=<array>)
(fileStageInShared=<array>)
(fileStageOut=<array>)
(gassCache=<path>)
(gramMyJob=independent|collective)
(hostCount=<number>)
(jobType=<string>)
```

(libraryPath=<path>)

(maxCpuTime=<time>)

(maxWallTime=<time>)

(maxTime=<time>)

(maxMemory=<memory>)

(minMemory=<memory>)

(project=<string>)

(remoteUrl=<string>)

(scratchDir=<string>)





# Appendix A

## Examples

### A.1 User-side xRSL script

```
&
(* test run: if "yes", only submits RSL without actual job start *)
(dryRun=no)
(* some local variables defined for further convenience *)
(rsl_substitution=(TOPDIR /home/oxana))
(rsl_substitution=(NGTEST $(TOPDIR)/examples/ngtest))
(rsl_substitution=(BIGFILE /scratch/oxana/100mb.tmp))
(* some environment variables, to be used by the job *)
(environment=(ATLAS /opt/atlas) (CERN /cern))
(* the main executable file to be staged in and submitted to the PBS *)
(executable=checkall.sh)
(* the arguments for the executable above *)
(arguments=pal)
(* files to be staged in before the execution *)
(inputFiles = (be_kaons ""))
(file1 gsiftp://grid.uio.no$(TOPDIR)/remfile.txt)
(bigfile.dat $(BIGFILE) )
(* files to be given executable permissions after staging in *)
(executables=be_kaons)
(* files to be staged out after the execution *)
(outputFiles=
  (file1 gsiftp://grid.tsl.uu.se/tmp/file1.tmp)
  (100mb.tmp rc://grid.fi.uib.no/bigfile)
  (be_kaons.hbook gsiftp://grid.quark.lu.se$(NGTEST)/kaons.hbook) )
(* location of the Replica collection *)
(replicaCollection="ldap://grid.uio.no:389/lc=TestCollection,rc=NorduGrid,dc=nordugrid,dc=org")
(* user-specified job name *)
(jobName=NGtest)
(* standard input file *)
(stdin="myinput.dat")
(* standard output file *)
(stdout="myoutput.dat")
(* standard error file *)
(stderr="myerror.dat")
(* GM logs directory name *)
(gmlog="gmlog")
(* flag whether to merge stdout and stderr *)
(join="no")
(* request e-mail notification on status change *)
```

```

(notify="bqfe oxana.smirnova@quark.lu.se oxana.smirnova@cern.ch")
(* specific queue to submit the job *)
(queue=atlas)
(* maximal CPU time required for the job, minutes for PBS*)
(CpuTime=60)
(* maximal time for the session directory to exist on the remote node, days *)
(lifeTime=7)
(* memory required for the job, Mbytes *)
(Memory=200)
(* wall time to start job processing *)
(startTime="2002-04-28 17:15:00")
(* disk space required for the job, Mbytes *)
(Disk=500)
(* required architecture of the execution node *)
(architecture=i686)
(* required run-time environment *)
(runTimeEnvironment="Atlas-1.1")
(* number of re-runs, in case of a system failure *)
(rerun=2)

```

## A.2 GM-side xRSL script

```

&
(* saves RSL in a temporary file if "yes"*)
(savestate=yes)
(* job submission to be performed if action is "request" *)
(action=request)
(* LRMS type, so far only pbs *)
(lrmstype=pbs)
(* submission host name *)
(hostName="grid.quark.lu.se")
(* test run: if "yes", only submits RSL without actual job start *)
(dryRun=no)
(* some local variables defined for further convenience *)
(rsl_substitution=(TOPDIR /home/oxana))
(rsl_substitution=(NGTEST $(TOPDIR)/examples/ngtest))
(rsl_substitution=(BIGFILE /scratch/oxana/100mb.tmp))
(* some environment variables, to be used by the job *)
(environment=(ATLAS /opt/atlas) (CERN /cern))
(* a dummy executable *)
(executable=/bin/echo)
(* the main executable itself, and its arguments *)
(arguments=checkall.sh pal)
(* files to be staged in before the execution *)
(inputFiles = (checkall.sh 210.279320915)
(myinput.dat 14.3980640923)
(be_kaons 880788.2035414420)
(file1 gsiftp://grid.uio.no$(TOPDIR)/remfile.txt)
(bigfile.dat 104857600.4087847787)
)
(* files to be given executable permissions after staging in *)
(executables=checkall.sh be_kaons)
(* files to be staged out after the execution *)
(outputFiles=(file1 gsiftp://grid.tsl.uu.se/tmp/file1.tmp)
(100mb.tmp rc://grid.fi.uib.no/bigfile)
(be_kaons.hbook gsiftp://grid.quark.lu.se$(NGTEST)/kaons.hbook)

```

```

        (myoutput.dat  gsiftp://grid.quark.lu.se/home/oxana/examples/ngtest/myoutput.dat)
        (myerror.dat   gsiftp://grid.quark.lu.se/home/oxana/examples/ngtest/myerror.dat)
    )
(* location of the Replica collection *)
(replicaCollection="ldap://grid.uio.no:389/lc=TestCollection,rc=NorduGrid,dc=nordugrid,dc=org")
(* user-specified job name *)
(jobName=NGtest)
(* standard input file *)
(stdin="myinput.dat")
(* standard output file *)
(stdout="myoutput.dat")
(* standard error file *)
(stderr="myerror.dat")
(* flag whether to merge stdout and stderr *)
(join="no")
(* request e-mail notification on status change *)
(notify="bqfe oxana.smirnova@quark.lu.se oxana.smirnova@cern.ch")
(* specific queue to submit the job *)
(queue=pc)
(* CPU time required for the job, minutes for PBS*)
(CpuTime=60)
(* maximal time for the session directory to exist on the remote node, seconds *)
(lifeTime=604800)
(* memory required for the job, Mbytes *)
(Memory=200)
(* wall time to start job processing *)
(startTime=20020128171500)
(* disk space required for the job, Mbytes *)
(Disk=500)
(* required architecture of the execution node *)
(architecture=i686)
(* required run-time environment *)
(runTimeEnvironment="Atlas-1.1")
(* number of re-runs, in case of a system failure *)
(rerun=2)
(* job ID - needed for cancellation and cleanup *)
(* (jobid=157111017133827)*)

```



# Bibliography

- [1] I. Foster and C. Kesselman, The Grid: Blueprint for a New Computing Infrastructure . Morgan Kaufmann, 1999.
- [2] The Globus Project. [Online]. Available: <http://www.globus.org>
- [3] The Globus Resource Specification Language RSL v1.0. [Online]. Available: <http://www-fp.globus.org/gram/rsl%5Fspec1.html>
- [4] The NorduGrid Project. [Online]. Available: <http://www.nordugrid.org>
- [5] A. W. A. van der Veen, "An Overview of an Architecture Proposal for a High Energy Physics Grid," in Proc. of PARA 2002, LNCS 2367, p. 76 J. Fagerholm, Ed. Springer-Verlag Berlin Heidelberg, 2002.
- [6] A. Konstantinov, "The NorduGrid project: Using Globus toolkit for building Grid infrastructure," Nucl. Instr. and Methods A 502, pp. 407-410 2003.
- [7] M. Ellert. The NorduGrid toolkit user interface. [Online]. Available: <http://www.nordugrid.org/documents/NorduGrid-UI.pdf>
- [8] A. Konstantinov. The NorduGrid Grid Manager. [Online]. Available: <http://www.nordugrid.org/documents/GM.pdf>
- [9] J. P. Protocols, Uniform Resource Locators (URL) And Extensions Supported In ARC. [Online]. Available: <http://www.nordugrid.org/documents>
- [10] Open source implementation of the Lightweight Directory Access Protocol. [Online]. Available: <http://www.openldap.org>
- [11] Globus replica catalog service. [Online]. Available: <http://www-fp.globus.org/datagrid/replica-catalog.html>
- [12] Replica Location Service. [Online]. Available: <http://grid-data-management.web.cern.ch/grid-data-management/replica-location-service/index.html>
- [13] A. Konstantinov. The NorduGrid Smart Storage Element. [Online]. Available: <http://www.nordugrid.org/documents>
- [14] The Gridsite. [Online]. Available: <http://www.gridsite.org>

# Index

A	
attribute	
acl	17
action	21
architecture	19
arguments	11
cache	12
cluster	17
count	20
cpuTime	13
disk	14
dryRun	19
environment	20
executable	11
executables	12
ftpThreads	16
gmlog	16
gridTime	14
hostName	21
inputFiles	12
jobid	21
jobName	16
jobreport	20
join	16
lifeTime	18
lrmstype	21
memory	14
middleware	15
nodeAccess	19
notify	18
outputFiles	13
queue	17
replicaCollection	18
rerun	19
rsl_substitution	19
runTimeEnvironment	14
savestate	21
sstdin	20
startTime	18
stderr	16
stdin	15
stdout	15
attributes	11
user-side	11
C	
Computing Element	13
G	
Globus	5
Grid Manager	
	5
N	
NorduGrid	5
R	
RSL	5
U	
URL	7
options	8
User Interface	5
X	
xRSL	5