

globus gss assist Reference Manual

4.0

Generated by Doxygen 1.2.18

Tue Aug 11 22:38:00 2009

Contents

1	Globus GSI GSS Assist	1
2	globus gss assist Module Index	1
3	globus gss assist Module Documentation	1

1 Globus GSI GSS Assist

The GSS Assist code provides convenience functions for using the Globus GSS-API.

2 globus gss assist Module Index

2.1 globus gss assist Modules

Here is a list of all modules:

Activation	1
Utility Functions	2
GSI GSS Assist Constants	10
Security Token Transport	11

3 globus gss assist Module Documentation

3.1 Activation

Globus GSI GSS Assist uses standard Globus module activation and deactivation.

De nes

```
#de ne GLOBUS_GSI_GSSASSIST_MODULE
```

3.1.1 Detailed Description

Globus GSI GSS Assist uses standard Globus module activation and deactivation.

Before any Globus GSS Assist functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GSI_GSS_ASSIST_MODULE);
```

This function returns GLOBUS\$UCCESS if Globus GSI GSS Assist was successfully initialized, and you are therefore allowed to call GSS Assist functions. Otherwise, an error code is returned, and GSS Assist functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GSS Assist, the following function must be called:

```
globus_module_deactivate(GLOBUS_GSI_GSS_ASSIST_MODULE)
```

This function should be called once for each time Globus GSI GSS Assist was activated.

3.1.2 Define Documentation

3.1.2.1 #define GLOBUSGSI_GSSASSIST_MODULE

Module descriptor.

3.2 Utility Functions

Utility functions for GSSAPI.

Accept Security Context

```
OM_uint32 globus_gss_assistacceptseccontext(OM_uint32 minor_status, gssctx_id_t contexthandle, const gsscredid_t credhandle, char src.namechar, OM_uint32 ret_args, int userto_user_ag, int tokenstatus, gsscredid_t delegated_credhandle, int(gssassistgettoken)(void , void , sizet ), void gssassistgetcontext, int(gssassistsendtoken)(void , void , sizet ), void gssassistsendcontext)
```

Accept Security Context Asynchronous

```
OM_uint32 globus_gss_assistacceptsec.contextasync (OM_uint32 minor_status, gssctx_id_t contexthandle, const gsscredid_t cred.handle, char src.namechar, OM_uint32 ret_args, int userto_user_ag, void input.buffer, sizet input.buffer.len, void outputbufferp, sizet outputbuffer.lenp, gsscredid_t delegated_credhandle)
```

Acquire Credential

```
OM_uint32 globus_gss_assistacquirecred(OM_uint32 minor_status, gsscredusage_t credusage, gsscred_id_t output_credhandle)
```

Acquire Credential Extension

```
OM_uint32 globus_gss_assistacquirecredext (OM_uint32 minor_status, char desirednamechar, OM_uint32 timereq, const gss_OID_set desiredmechs, gsscredusage_t credusage, gsscredid_t output_credhandle, gss_OID_set actualmechs, OM_uint32 time_rec)
```

Display Status

```
OM_uint32 globus_gss_assistdisplaystatus(FILE fp, char comment, OM_uint32 majorstatus, OM_uint32 minor_status, int tokenstatus)
```

Display Status String

```
OM_uint32 globus_gss_assistdisplaystatusstr (char str, char comment, OM_uint32 majorstatus, OM_uint32 minor_status, int tokenstatus)
```

De nes

```
#de ne NI_MAXHOST 255
```

Functions

```
int globusgssassistgridmap(char globusidp, char useridp)
int globusgssassistuserok(char globusid, char userid)
int globusgssassistmap.localUser(char localUser, char globusidp)
OM_uint32 globusgssassistimport_seccontext(OM_uint32 minor_status, gssctx_id_t contexthandle, int tokenstatus, int fdp, FILE fperr)
OM_uint32 globusgssassistinit_seccontext(OM_uint32 , const gsscredid_t, gssctx_id_t , char , OM_uint32, OM_uint32 , int , int( get.token)(void , void , size_t ), void get.arg, int( sendtoken)(void , void , size_t), void sendarg)
OM_uint32 globusgssassistinit_seccontextasync (OM_uint32 minor_status, const gsscredid_t credhandle, gssctx_id_t contexthandle, char targetnamechar, OM_uint32 req_args, OM_uint32 ret_args, void input_buffer, size_t input_buffer_len, void outputbufferp, size_t output.buffer_len)
OM_uint32 globusgssassistwill_handlerrestrictions(OM_uint32 minor_status, gssctx_id_t contexthandle)
OM_uint32 globusgssassistget_unwrap(OM_uint32 minor_status, const gssctx_id_t contexthandle, char data, size_t length, int tokenstatus, int(gssassistget.token)(void , void , size_t ), void gssassist-get.context, FILE fperr)
OM_uint32 globusgssassistwrap_send(OM_uint32 minor_status, const gssctx_id_t contexthandle, char data, size_t length, int tokenstatus, int(gssassistsendtoken)(void , void , size_t), void gssassistsend-context, FILE fperr)
```

3.2.1 Detailed Description

Utility functions for GSSAPI.

3.2.2 De ne Documentation

3.2.2.1 #de ne NLMAXHOST 255

Create a GSS Name structure from the given hostname. This function tries to resolve the given host name string to the canonical DNS name for the host.

Parameters:

- hostname The host name or numerical address to be resolved and transform into a GSS Name
- authorization_hostname The resulting GSS Name

Returns:

GLOBUS_SUCCESS on successful completion, a error object otherwise

3.2.3 Function Documentation

3.2.3.1 OM_uint32 globus_gssassistacceptseccontext (OM_uint32 minor_status gssctx_id_t context-handle, const gsscred_id_t cred.handle, char src.name.char, OM_uint32 ret_args, int user_to_user_ag, int tokenstatus gsscred_id_t delegated_cred.handle, int(gssassistget.token)(void , void , size_t), void gssassistget.context int(gssassistsendtoken)(void , void , size_t), void gssassistsendcontext)

This routine accepts a GSSAPI security context and is called by the ~~gatekeeper~~. It isolates the GSSAPI from the rest of the gram code.

Initialize a gssapi security connection. Used by the server. The context handle is returned, and there is one for each connection. This routine will take care of the looping and token processing, using the supplied get and send token routines.

Parameters:

- minor_status gssapi return code
- contexthandle pointer to returned context.
- cred.handle the cred handle obtained by acquire.
- src.name.char Pointer to char string representation of the client which contacted the server. Maybe NULL if not wanted. Should be freed when done.
- ret_ags Pointer to which services are available after the connection is established. Maybe NULL if not wanted.
We will also use this to pass in ags to the globus version of gssapi.
- user_to_user_ag Pointer to ag to be set if the sname is the same as our name. (Following are particular to this assist routine)
- token_status assist routine get/send token status
- delegated_cred.handle pointer to be set to the credential delegated by the client if delegation occurs during the security handshake
- gss_assist_get_token a get token routine
- gss_assist_get_context rst arg for the get token routine
- gss_assist_send_token a send token routine
- gss_assist_send_context rst arg for the send token routine

Returns:

GSSS_COMPLETE on success Other gss errors on failure.

3.2.3.2 OM_uint32 globus_gss_assist_accept_sec_context_async (OM_uint32 minor_status gss.ctx_id_t context_handle, const gsscred_id_t cred.handle, char src.name.char, OM_uint32 ret_ags, int user_to_user_ag, void *input_buffer, size_t input_buffer_len, void *output_bufferp, size_t output_buffer_lenp, gsscred_id_t delegated_cred.handle)

This is a asynchronous version of [globus_gss_assist_accept_sec_context\(\)](#) function. Instead of looping itself it passes in and out the read and written buffers and the calling application is responsible for doing the I/O directly.

Parameters:

- minor_status gssapi return code
- contexthandle pointer to returned context.
- cred.handle the cred handle obtained by acquire.
- src.name.char Pointer to char string representation of the client which contacted the server. Maybe NULL if not wanted. Should be freed when done.
- ret_ags Pointer to which services are available after the connection is established. Maybe NULL if not wanted.
We will also use this to pass in ags to the globus version of gssapi.
- user_to_user_ag Pointer to ag to be set if the sname is the same as our name.
- input_buffer pointer to a buffer received from peer.
- input_buffer_len length of the buffer inpubuffer.
- output_bufferp pointer to a pointer which will be filled in with a pointer to a allocated block of memory. If non-NULL the contents of this block should be written to the peer where they will be fed into the gss_assist_init_seccontextasync() function.

`output_buffer_lenp` pointer to an integer which will be filled in with the length of the allocated output buffer pointed to by `outputbufferp`.

`delegatedcred.handle` pointer to be set to the credential delegated by the client if delegation occurs during the security handshake

Returns:

`GSSS_COMPLETE` on successful completion when this function does not need to be called again.

`GSSS_CONTINUE_NEEDED` when `outputbufferp` should be sent to the peer and a new input buffer read and this function called again.

Other gss errors on failure.

3.2.3.3 OM_uint32 globus_gssassistacquire_cred (OM_uint32 minor_status gsscred_usage cred_usage gsscred_id_t output_cred_handle)

Called once at the start of the process, to obtain the credentials the process is running under. The

Parameters:

`minor_status` pointer for return code

`cred_usage` `GSSC_INITIATE`, `GSS_C_ACCEPT`, or `GSSC_BOTH`

`output_cred_handle` Pointer to the returned handle. This needs to be passed to many gss routines.

Returns:

`GSSS_COMPLETE` on sucess Other GSS return codes

3.2.3.4 OM_uint32 globus_gssassistacquire_cred_ext (OM_uint32 minor_status char desiredname,char, OM_uint32 time_req, const gss_OID_set desired_mechs gsscred_usage cred_usage gsscred_id_t output_cred_handle, gss_OID_set actual_mechs OM_uint32 time_rec)

Called once at the start of the process, to obtain the credentials the process is running under. All the parameters of the `gssacquirecred`, except the `desiredname` is a string of the form: [type:]name. This will be imported with the type.

Returns:

`GSSS_COMPLETE` on sucess Other GSS return codes

See also:

`globus_gsi_gss_acquirecred`

3.2.3.5 OM_uint32 globus_gssassistedisplay_status (FILE fp, char comment OM_uint32 major_status OM_uint32 minor_status int token_status)

Display the messages for the major and minor status on the file pointed at by `fp`. Takes care of the overloaded major status if there was a problem with the `getoken` or `sendtoken` routines.

Parameters:

`fp` a file pointer

`comment` String to print out before other error messages.

`major_status` The major status to display

`minor_status` The minor status to display

`token_status` token status to display

Returns:

0

3.2.3.6 OM_uint32 globus_gss_assist_display_status.str (char *str, char *comment) OM_uint32 major_status
OM_uint32 minor_status int token_status\$

Display the messages for the major and minor status and return a string with the messages. Takes care of the overloaded major_status if there was a problem with the `getoken` or `sendtoken` routines.

Parameters:

- str pointer to char for returned string. Must be freed
- comment String to print out before other error messages.
- major_status The major status to display
- minor_status The minor status to display
- token_status token status to display

Returns:

0

3.2.3.7 int globus_gss_assist_gridmap (char *globusidp, char *useridp)

Routines callable from globus based code to map a globusID to a local unix user

GRIDMAP environment variable pointing at the map file. Defaults to gridmap

A gridmap file is required if being run as root. If being run as a user, it is not required, and defaults to the current user who is running the command.

This is the same file used by the `gssapi_kerberos` but will be used with other gssapi implementations which do not use the gridmap file.

Parameters:

- globusidp the GSSAPI name from the client who requested authentication
- useridp the resulting user ID name for the local system

Returns:

0 on success -1 if bad arguments 1 on error

3.2.3.8 int globus_gss_assist_userok (char *globusid, char *userid)

Check to see if a particular globusid is authorized to access the given local user account.

Parameters:

- globusid the globus id in string form - this should be the user's subject
- userid the local account that access is sought for

Returns:

0 on success (authorization allowed) -1 if bad arguments 1 on error

3.2.3.9 int globus_gss_assist_map_local_user (char *local_user, char *globusidp)

Routine for returning the default globus ID associated with a local user name. This is somewhat of a hack since there is not a guaranteed one-to-one mapping. What we do is look for the first entry in the gridmap file that has the local user as the default login. If the user is not a default on any entry, we find the first entry in which the user exists as a secondary mapping.

Parameters:

local_user the local username to find the DN for
 globusidp the first DN found that reverse maps from the local user

Returns:

0 on success, otherwise an error object identifier is returned. use `globuserror_get` to get the error object from the id. The resulting error object must be freed using `globusobjectfree` when it is no longer needed.

See also:

`globuserror_get` , `globusobjectfree`

3.2.3.10 OMuint32 globus_gssassistimport_seccontext (OM_uint32 minor_status gssctx_id_t contexthandle, int token_status int fdp, FILE *fperr)

Import the security context from a file

Parameters:

minor_status GSSAPI return code. This is a Globus Error code (or GLOBUSUCCESS) cast to a OMint32 pointer. If an error has occurred, the resulting error (from calling `globuserror_get` on this variable) needs to be freed by the caller
 contexthandle The imported context
 token_status Errors that occurred while reading from the file
 fdp the file descriptor pointing to a file containing the security context
 fperr FILE to write error messages

Returns:

the major status

3.2.3.11 OMuint32 globus_gssassistinit_seccontext (OM_uint32 minor_status const gsscared_id_t cred_handle, gssctx_id_t contexthandle, char target.name.char, OM_uint32 req_ags, OM_uint32 ret_ags, int token_status int(gssassistget_token)(void *, void *, size_t), void * gssassistget_context int(gssassistsend_token)(void *, void *, size_t), void * gssassistsend_context)

Initialize a gssapi security connection. Used by the client. The context handle is returned, and there is one for each connection. This routine will take care of the looping and token processing, using the supplied acquire and send token routines.

Parameters:

minor_status GSSAPI return code. The new minor status is a `globusresult` cast to an OMuint32. If the call was successful, the minor status is equivalent to GLOBUSUCCESS. Otherwise, it is a globus error object ID that can be passed to `globuserror_get` to get the error object. The error object needs to be freed with `globusobjectfree`.
 cred.handle the cred handle obtained by `acquire`.
 contexthandle pointer to returned context.
 target.name.char char string representation of the server to be contacted.
 req_ags request args, such as `GSS_DELEG_FLAG` for delegation and the `GSS_MUTUAL_FLAG` for mutual authentication.
 ret_ags Pointer to which services are available after the connection is established. Maybe NULL if not wanted.

The Following are particular to this assist routine:

Parameters:

- token.status the assist routine's get/send token status
- gss.assistget.token function pointer for getting the token
- gss.assistget.context rst argument passed to the gassistget.token function
- gss.assistsendtoken function pointer for setting the token
- gss.assistsendcontext rst argument passed to the gassistset.token function pointer

Returns:

- The major status

3.2.3.12 OM_uint32 globus_gssassistinit_seccontext_async (OM_uint32 minor_status const gsscred_id_t cred.handle, gssctx_id_t contexthandle, char target.name.char, OM_uint32 req_ags, OM_uint32 ret_ags, void input_buffer, size_t input_buffer_len, void output.bufferp, size_t output.buffer_lenp)

This is a asynchronous version of [globus_gssassistinit_seccontext\(\)](#)function. Instead of looping itself it passes in and out the read and written buffers and the calling application is responsible for doing the I/O directly.

Parameters:

- minor_status GSSAPI return code. The new minor status is a `globus_error_t` cast to a OM_uint32. If an error occurred (GSS_ERROR(majorstatus)) the minorstatus is a globus error object id. The error object can be obtained via `globus_error_get` and should be destroyed with `globus_object_free` when no longer needed. If no error occurred, the minor status is equal to GLOBUS_SUCCESS.
- cred.handle the cred handle obtained by `acquire`.
- contexthandle pointer to returned context.
- target.name.char char string representation of the server to be contacted.
- req_ags request ags, such as GSS_DELEG_FLAG for delegation and the GSS_MUTUAL_FLAG for mutual authentication.
- ret_ags Pointer to which services are available after the connection is established. Maybe NULL if not wanted.
- input_buffer pointer to a buffer received from peer. Should be NULL on rst call.
- input_buffer_len length of the buffer inpubuffer. Should be zero on rst call.
- output.bufferp pointer to a pointer which will be filled in with a pointer to a allocated block of memory. If non-NUL the contents of this block should be written to the peer where they will be fed into the gss assistinit_seccontextasync() function.
- output.buffer_lenp pointer to an integer which will be filled in with the length of the allocated output buffer pointed to by outputbufferp.

Returns:

- GSSS_COMPLETE on successful completion when this function does not need to be called again.

GSSS_CONTINUE_NEEDED when outputbufferp should be sent to the peer and a new inbuffer read and this function called again.

Other gss errors on failure.

3.2.3.13 OM_uint32 globus_gss_assistwill_handle_restrictions (OM_uint32 minor_status gssctx_id_t context_handle)

Sets the context to handle restrictions

Parameters:

minor_status the resulting minor status from setting the context handle
contexthandle the context handle to set the minor status of

Returns:

the major status from setting the context

3.2.3.14 OM_uint32 globus_gss_assistgetunwrap (OM_uint32 minor_status const gssctx_id_t context_handle, char *data, size_t *length, int token_status int(gssassistgettoken)(void , void , size_t), void gssassistgetcontext FILE fperr)

Gets a token using the specific tokenizing functions, and performs the GSS unwrap of that token

See also:

gss_unwrap

Parameters:

minor_status GSSAPI return code,

See also:

gss_unwrap

Parameters:

contexthandle the context

data pointer to be set to the unwrapped application data. This must be freed by the caller.

length pointer to be set to the length of the data byte array.

token_status assist routine get/send token status

gssassistgettoken a detokenizing routine

gssassistgetcontext first arg for above routine

fperr error stream to print to

Returns:

GSSS_COMPLETE on success Other gss errors on failure.

3.2.3.15 OM_uint32 globus_gss_assistwrap_send (OM_uint32 minor_status const gssctx_id_t context_handle, char *data, size_t length, int token_status int(gssassistsendtoken)(void , void , size_t), void gssassistsendcontext FILE fperr)

Parameters:

minor_status GSSAPI return code. If the call was successful, the minor status is equal to GLOBUSUCCESS. Otherwise, it is an error object ID for which globus_error_get() and globus_error_free() can be used to get and destroy it.

contexthandle the context.

data pointer to application data to wrap and send

length length of the data array
 token_status assist routine get/send token status
 gss_assist_send_token a sendtoken routine
 gss_assist_send_context first arg for the sendtoken
 fperr file handle to write error message to.

Returns:

GSSS_COMPLETE on success Other gss errors on failure.

See also:

`gss_wrap()`

3.3 GSI GSS Assist Constants

Enumerations

```
enum globus_gsi_gss_assist_error_t { GLOBUS_GSI_GSSASSIST_ERROR_SUCCESS = 0, GLOBUS_GSI_GSSASSIST_ERRORWITH_ARGUMENTS = 1, GLOBUS_GSI_GSSASSIST_ERRORUSERID_DOESNT_MATCH = 2, GLOBUS_GSI_GSSASSIST_ERRORIN_GRIDMAP_NO_USERENTRY = 3, GLOBUS_GSI_GSSASSIST_ERRORWITH_GRIDMAP = 4, GLOBUS_GSI_GSSASSIST_ERRORINVALID_GRIDMAP_FORMAT = 5, GLOBUS_GSI_GSSASSIST_ERRORERRNO = 6, GLOBUS_GSI_GSSASSIST_ERRORWITH_INIT = 7, GLOBUS_GSI_GSSASSIST_ERRORWITH_WRAP = 8, GLOBUS_GSI_GSSASSIST_ERRORWITH_TOKEN = 9, GLOBUS_GSI_GSSASSIST_ERROREXPORTING_CONTEXT = 10, GLOBUS_GSI_GSSASSIST_ERRORIMPORTING_CONTEXT = 11, GLOBUS_GSI_GSSASSIST_ERRORINITIALIZING_CALLOUT_HANDLE = 12, GLOBUS_GSI_GSSASSIST_ERRORWITH_CALLOUT_CONFIG = 13, GLOBUS_GSI_GSSASSIST_CALLOUT_ERROR = 14, GLOBUS_GSI_GSSASSIST_GSSAPIERROR = 15, GLOBUS_GSI_GSSASSIST_GRIDMAP_LOOKUP_FAILED = 16, GLOBUS_GSI_GSSASSIST_BUFFER_TOO_SMALL = 17, GLOBUS_GSI_GSSASSIST_ERRORCANONICALIZING_HOSTNAME = 18 };
```

3.3.1 Enumeration Type Documentation

3.3.1.1 enum globus_gsi_gss_assist_error_t

GSI GSS Assist Error codes.

Enumeration values:

`GLOBUS_GSI_GSSASSIST_ERROR_SUCCESS` Success.

`GLOBUS_GSI_GSSASSIST_ERROR_WITH_ARGUMENTS` No user entry in gridmap ie.

`GLOBUS_GSI_GSSASSIST_ERROR_USER_ID_DOESNT_MATCH` Error user ID doesn't match.

`GLOBUS_GSI_GSSASSIST_ERROR_IN_GRIDMAP_NO_USERENTRY` Error with arguments passed to function.

`GLOBUS_GSI_GSSASSIST_ERROR_WITH_GRIDMAP` Error querying gridmap ie.

`GLOBUS_GSI_GSSASSIST_ERROR_INVALID_GRIDMAP_FORMAT` Invalid gridmap ie format.

`GLOBUS_GSI_GSSASSIST_ERROR_ERRNO` System Error.

`GLOBUS_GSI_GSSASSIST_ERROR_WITH_INIT` Error during context initialization.

`GLOBUS_GSI_GSSASSIST_ERROR_WITH_WRAP` Error during message wrap.

`GLOBUS_GSI_GSSASSIST_ERROR_WITH_TOKEN` Error with token.

GLOBUS_GSI_GSSASSIST_ERROR_EXPORTING_CONTEXT Error exporting context.
 GLOBUS_GSI_GSSASSIST_ERROR_IMPORTING_CONTEXT Error importing context.
 GLOBUS_GSI_GSSASSIST_ERROR_INITIALIZING_CALLOUT_HANDLE Error initializing callout handle.
 GLOBUS_GSI_GSSASSIST_ERROR_WITH_CALLOUT_CONFIG Error reading callout configuration.
 GLOBUS_GSI_GSSASSIST_CALLOUT_ERROR Error invoking callout.
 GLOBUS_GSI_GSSASSIST_GSSAPLERROR A GSSAPI returned an error.
 GLOBUS_GSI_GSSASSIST_GRIDMAP_LOOKUP_FAILED Gridmap lookup failure.
 GLOBUS_GSI_GSSASSIST_BUFFER_TOO_SMALL Caller provided insufficient buffer space for local identity.
 GLOBUS_GSI_GSSASSIST_ERROR_CANONICALIZING_HOSTNAME Failed to obtain canonical host name.

3.4 Security Token Transport

Token routines using fread and fwrite.

Functions

```

int globusgssassisttoken.getfd(void *arg, void *bufp, size_t sizep)
int globusgssassisttoken.sendfd(void *arg, void *buf, size_t size)
int globusgssassisttoken.sendfd\_withoutlength(void *arg, void *buf, size_t size)
int globusgssassisttoken.sendfd\_ex(void *arg, void *buf, size_t size)
int globusgssassisttoken.getnexus(void *arg, void *bufp, size_t sizep)
int globusgssassisttoken.sendnexus(void *arg, void *bufp, size_t sizep)
int globusgssassisttoken.sendnexuswithoutlength(void *arg, void *bufp, size_t sizep)
int globusgssassisttoken.sendnexusex(void *arg, void *bufp, size_t sizep)

```

3.4.1 Detailed Description

Token routines using fread and fwrite.

Additional code has been added to detect tokens which are sent without a length field. These can currently be only SSL tokens. This does require some knowledge of the underlying GSSAPI, by the application, but is within the guidelines of the GSSAPI specifications.

The get routine will automatically attempt this test, while a new send routine will check a flag. The old send routine will work as before, sending a 4-byte length.

3.4.2 Function Documentation

3.4.2.1 int [globusgssassisttoken.getfd](#)(void *arg, void *bufp, size_t sizep)

Use a open file descriptor to get a token. This function provides parameter types that allow it to be passed to [Assist Functions](#) and [Utility Functions](#)

Parameters:

- arg the FILE stream cast to a void pointer
- bufp the resulting token

sizep the size (number of bytes) read into bufp

Returns:

0 on success, 0 is internal return, 0 is the -errno

3.4.2.2 int globusgssassisttoken_sendfd (void *arg, void *buf, size_t size)

Write a token to the open file descriptor. Will write it with a 4 byte length. This function provides parameter types that allow it to be passed [Utility Functions](#) and [Utility Functions](#)

Parameters:

arg the FILE stream to send the token on

buf the token

size the size of the token in bytes

Returns:

0 on success, 0 on error, 0 on errno error

3.4.2.3 int globusgssassisttoken_sendfd_without_length (void *arg, void *buf, size_t size)

Write a token to the open file descriptor. Will write it without a length, so as to

3.4.2.4 int globusgssassisttoken_sendfd_ex (void *exp, void *buf, size_t size)

Write a token to the open file descriptor. Will look at the arg to determine if the length field need to be written.

Parameters:

exp the globusgssassistex variable that holds the FILEstream and args to be set

buf the token buffer to send

size size of the token buffer

Returns:

0 on success, 0 on error, 0 on errno error (-errno)

3.4.2.5 int globusgssassisttoken_get_nexus (void *arg, void **bufp, size_t *sizep)

Use a nexus socket to get the tokens.

Additional code has been added to detect tokens which are sent without a length field. These can currently be only SSL tokens. This does require some knowledge of the underlying GSSAPI, by the application, but is within the guidelines of the GSSAPI specifications.

The get routine will automatically attempt this test, while a new send routine will check a flag. The old send routine will work as before, sending a 4-byte length.

Parameters:

arg the globusio_handle to get the token from

bufp the buffer to read the token into

sizep the size of what gets read

Returns:

0 on success, 0 is internal return, 0 is the -errno returned from nexus

3.4.2.6 int globusgssassisttoken_sendnexus (void *arg, void *buf, size_t size)

Write a token to the nexus io handle. This function provides parameter types that allow it to be passed to [Utility Functions](#) and [Utility Functions](#)

Parameters:

arg nexus io handle to send the token on

buf the token as a buffer

size the size of the buffer

Returns:

0 on success< 0 on error< 0 on errno error (-errno)

3.4.2.7 int globusgssassisttoken_sendnexuswithout_length (void *arg, void *buf, size_t size)

Send a token on a nexus IO handle. Using this function the length is not sent.

See also:

[globusgssassisttoken_getnexus\(\)](#) for further info.

3.4.2.8 int globusgssassisttoken_sendnexus_ex (void *exp, void *buf, size_t size)

Write a token to the open file descriptor. will look at the arg to determine if the length field need to be written.

Parameters:

exp The [globusgssassistex](#) that the wraps the nexus IO handle to send the token on

buf the buffer holding the token

size the size of the buffer

Returns:

0 on success< 0 on error< 0 on errno error (-errno)

Index

Activation, 1

globus.gsi.gss.assist
 globusgss.assistacceptsecontext, 3
 globusgss.assistacceptsecontextasync, 4
 globusgss.assistacquirecred, 5
 globusgss.assistacquirecred.ext, 5
 globusgss.assistdisplay.status, 5
 globusgss.assistdisplay.statusstr, 5
 globusgss.assistget.unwrap, 9
 globusgss.assistgridmap, 6
 globusgss.assistimport.secontext, 7
 globusgss.assistinit_sec.context, 7
 globusgss.assistinit_sec.contextasync, 8
 globusgss.assistmap.local_user, 6
 globusgss.assistuserok, 6
 globusgss.assistwill_handlerrestrictions, 8
 globusgss.assistwrap.send, 9
 NI_MAXHOST, 3

globus.gsi.gss.assistactivation
 GLOBUS_GSLGSSASSIST_MODULE, 2

GLOBUS_GSLGSSASSIST_BUFFER_TOO_SMALL
 globus.gsi.gss.assistconstants, 11

GLOBUS_GSLGSSASSIST_CALLOUT_ERROR
 globus.gsi.gss.assistconstants, 11

globus.gsi.gss.assistconstants
 GLOBUS_GSLGSSASSIST_BUFFER_TOO_SMALL, 11

 GLOBUS_GSLGSSASSIST_CALLOUT_ERROR, 11

 GLOBUS_GSLGSSASSIST_ERROR_CANONICALIZING_HOSTNAME, 11

 GLOBUS_GSLGSSASSIST_ERROR_INVALID_GRIDMAP_NO_USER_ENTRY, 10

 GLOBUS_GSLGSSASSIST_ERROR_INITIALIZING_CALLOUT_HANDLE, 11

 GLOBUS_GSLGSSASSIST_ERROR_INVALID_GRIDMAP_FORMAT, 10

 GLOBUS_GSLGSSASSIST_ERROR_SUCCESS, 10

 GLOBUS_GSLGSSASSIST_ERRORUSER_ID_DOESNT_MATCH, 10

GLOBUS_GSLGSSASSIST_ERRORWITH_ARGUMENTS, 10

GLOBUS_GSLGSSASSIST_ERRORWITH_CALLOUT_CONFIG, 11

GLOBUS_GSLGSSASSIST_ERRORWITH_GRIDMAP, 10

GLOBUS_GSLGSSASSIST_ERRORWITH_INIT, 10

GLOBUS_GSLGSSASSIST_ERRORWITH_TOKEN, 10

GLOBUS_GSLGSSASSIST_ERRORWITH_WRAP, 10

GLOBUS_GSLGSSASSIST_GRIDMAP_LOOKUP_FAILED, 11

GLOBUS_GSLGSSASSIST_GSSAPIERROR, 11

globus.gsi.gss.assistconstants
 globus.gsi.gss.assisterror_t, 10

GLOBUS_GSLGSSASSIST_ERROR_CANONICALIZING_HOSTNAME
 globus.gsi.gss.assistconstants, 11

GLOBUS_GSLGSSASSIST_ERRORERRNO
 globus.gsi.gss.assistconstants, 10

GLOBUS_GSLGSSASSIST_ERROREXPORTING_CONTEXT
 globus.gsi.gss.assistconstants, 10

GLOBUS_GSLGSSASSIST_ERRORIMPORTING_CONTEXT
 globus.gsi.gss.assistconstants, 11

GLOBUS_GSLGSSASSIST_ERRORIN_GRIDMAP_NO_USER_ENTRY
 globus.gsi.gss.assistconstants, 10

GLOBUS_GSLGSSASSIST_ERRORINITIALIZING_CALLOUT_HANDLE
 globus.gsi.gss.assistconstants, 11

GLOBUS_GSLGSSASSIST_ERRORINVALID_GRIDMAP_FORMAT
 globus.gsi.gss.assistconstants, 10

GLOBUS_GSLGSSASSIST_ERRORSUCCESS
 globus.gsi.gss.assistconstants, 10

globus.gsi.gss.assisterror_t
 globus.gsi.gss.assistconstants, 10

GLOBUS_GSLGSSASSIST_ERRORUSER_ID_DOESNT_MATCH
 globus.gsi.gss.assistconstants, 10

GLOBUS_GSLGSSASSIST_ERRORWITH_ARGUMENTS
 globus.gsi.gss.assistconstants, 10

GLOBUS_GSLGSSASSIST_ERRORWITH_CALLOUT_CONFIG

globus.gsi.gss.assistconstants,[11](#)
GLOBUS_GSL_GSS_ASSIST_ERRORWITH_-
 GRIDMAP
 globus.gsi.gss.assistconstants,[10](#)
GLOBUS_GSL_GSS_ASSIST_ERRORWITH_INIT
 globus.gsi.gss.assistconstants,[10](#)
GLOBUS_GSL_GSS_ASSIST_ERRORWITH_-
 TOKEN
 globus.gsi.gss.assistconstants,[10](#)
GLOBUS_GSL_GSS_ASSIST_ERRORWITH_WRAP
 globus.gsi.gss.assistconstants,[10](#)
GLOBUS_GSL_GSS_ASSIST_GRIDMAP_-
 LOOKUP_FAILED
 globus.gsi.gss.assistconstants,[11](#)
GLOBUS_GSL_GSS_ASSIST_GSSAPI_ERROR
 globus.gsi.gss.assistconstants,[11](#)
GLOBUS_GSL_GSS_ASSIST_MODULE
 globus.gsi.gss.assistactivation,[2](#)
globus.gsi.gss.assisttokens
 globus.gss.assisttoken.get_fd, [11](#)
 globus.gss.assisttoken.get_nexus, [12](#)
 globus.gss.assisttoken.sendfd, [12](#)
 globus.gss.assisttoken.sendfd_ex, [12](#)
 globus.gss.assisttoken.sendfd_without_length,
 [12](#)
 globus.gss.assisttoken.sendnexus, [12](#)
 globus.gss.assisttoken.sendnexusex, [13](#)
 globus.gss.assisttoken.sendnexuswithout_-
 length, [13](#)
globus.gss.assistacceptseccontext
 globus.gsi.gss.assist,[3](#)
globus.gss.assistacceptseccontextasync
 globus.gsi.gss.assist,[4](#)
globus.gss.assistacquirecred
 globus.gsi.gss.assist,[5](#)
globus.gss.assistacquirecredext
 globus.gsi.gss.assist,[5](#)
globus.gss.assistdisplaystatus
 globus.gsi.gss.assist,[5](#)
globus.gss.assistdisplaystatusstr
 globus.gsi.gss.assist,[5](#)
globus.gss.assistunwrap
 globus.gsi.gss.assist,[9](#)
globus.gss.assistgridmap
 globus.gsi.gss.assist,[6](#)
globus.gss.assistimport_sec_context
 globus.gsi.gss.assist,[7](#)
globus.gss.assistinit_sec_context
 globus.gsi.gss.assist,[7](#)
globus.gss.assistinit_sec_contextasync
 globus.gsi.gss.assist,[8](#)
globus.gss.assistmap.local_user
 globus.gsi.gss.assist,[6](#)

globus.gss.assisttoken.get_fd
 globus.gsi.gss.assisttokens,[11](#)
globus.gss.assisttoken.get_nexus
 globus.gsi.gss.assisttokens,[12](#)
globus.gss.assisttokensendfd
 globus.gsi.gss.assisttokens,[12](#)
globus.gss.assisttokensendfd_ex
 globus.gsi.gss.assisttokens,[12](#)
globus.gss.assisttokensendfd_without_length
 globus.gsi.gss.assisttokens,[12](#)
globus.gss.assisttokensendnexus
 globus.gsi.gss.assisttokens,[12](#)
globus.gss.assisttokensendnexusex
 globus.gsi.gss.assisttokens,[13](#)
globus.gss.assisttokensendnexuswithout_length
 globus.gsi.gss.assisttokens,[13](#)
globus.gss.assistuserok
 globus.gsi.gss.assist,[6](#)
globus.gss.assistwill_handlerrestrictions
 globus.gsi.gss.assist,[8](#)
globus.gss.assistwrap.send
 globus.gsi.gss.assist,[9](#)
GSI GSS Assist Constants,[10](#)

NI_MAXHOST
 globus.gsi.gss.assist,[3](#)

Security Token Transport,[1,1](#)

Utility Functions,[2](#)