

globus gss assist Reference Manual

4.0

Generated by Doxygen 1.3.5

Tue Aug 11 21:13:05 2009

Contents

1	Globus GSI GSS Assist	1
2	globus gss assist Module Index	1
3	globus gss assist Module Documentation	1

1 Globus GSI GSS Assist

The GSS Assist code provides convenience functions for using the Globus GSS-API.

2 globus gss assist Module Index

2.1 globus gss assist Modules

Here is a list of all modules:

Activation	1
Utility Functions	2
GSI GSS Assist Constants	11
Security Token Transport	12

3 globus gss assist Module Documentation

3.1 Activation

Globus GSI GSS Assist uses standard Globus module activation and deactivation.

De nes

- #de ne `GLOBUS_GSI_GSS_ASSIST_MODULE`

3.1.1 Detailed Description

Globus GSI GSS Assist uses standard Globus module activation and deactivation.

Before any Globus GSS Assist functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GSI_GSS_ASSIST_MODULE);
```

This function returns `GLOBUS_SUCCESS` if Globus GSI GSS Assist was successfully initialized, and you are therefore allowed to call GSS Assist functions. Otherwise, an error code is returned, and GSS Assist functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GSS Assist, the following function must be called:

```
globus_module_deactivate(GLOBUS_GSI_GSS_ASSIST_MODULE)
```

This function should be called once for each time Globus GSI GSS Assist was activated.

3.1.2 Define Documentation

3.1.2.1 #define GLOBUS_GSI_GSS_ASSIST_MODULE

Module descriptor.

3.2 Utility Functions

Utility functions for GSSAPI.

Accept Security Context

- OM_uint32 `globus_gss_assist_accept_sec_cred`(OM_uint32 minor_status, gss_ctx_id_t context_handle, const gss_cred_id_t cred_handle, char* src_name_char, OM_uint32 ret_ags, int user_to_user_ag, int token_status, gss_cred_id_t delegated_cred_handle, int(gss_assist_get_token)(void void*, size_t), void gss_assist_get_context, int(gss_assist_send_token)(void void*, size_t), void gss_assist_send_context)

Accept Security Context Asynchronous

- OM_uint32 `globus_gss_assist_accept_sec_context_a`(OM_uint32 minor_status, gss_ctx_id_t context_handle, const gss_cred_id_t cred_handle, char* src_name_char, OM_uint32 ret_ags, int user_to_user_ag, void input_buffer, size_t input_buffer_len, void output_bufferp, size_t output_buffer_lenp, gss_cred_id_t delegated_cred_handle)

Acquire Credential

- OM_uint32 `globus_gss_assist_acquire_cred`(OM_uint32 minor_status, gss_cred_usage_t cred_usage, gss_cred_id_t output_cred_handle)

Acquire Credential Extension

- OM_uint32 `globus_gss_assist_acquire_cred_ex`(OM_uint32 minor_status, char* desired_name_char, OM_uint32 time_req, const gss_OID_set desired_mechs, gss_cred_usage_t cred_usage, gss_cred_id_t cred_handle, gss_OID_set actual_mechs, OM_uint32 time_rec)

Display Status

- OM_uint32 `globus_gss_assist_display_status`(FILE fp, char comment, OM_uint32 major_status, OM_uint32 minor_status, int token_status)

Display Status String

- OM_uint32 `globus_gss_assist_display_status(char str, char comment, OM_uint32 major_status, OM_uint32 minor_status, int token_status)`

Gridmap

- int `globus_gss_assist_gridm(char globusidp, char useridp)`

User OK

- int `globus_gss_assist_user(char globusid, char userid)`

Map Local User

- int `globus_gss_assist_map_local_user(char local_user, char globusidp)`

[NOHEADER]

- OM_uint32 `globus_gss_assist_import_sec_context(OM_uint32 minor_status, gss_ctx_id_t context_handle, int token_status, int fdp, FILE *fperr)`

Init Security Context

- OM_uint32 `globus_gss_assist_init_sec_context(OM_uint32 minor_status, const gss_cred_id_t cred_handle, gss_ctx_id_t context_handle, char target_name_char, OM_uint32 req_ags, OM_uint32 et_ags, int token_status, int(gss_assist_get_token)(void *voidp, size_t), void *gss_assist_get_context, int(gss_assist_send_token)(void *voidp, size_t), void *gss_assist_send_context)`

Init Security Context Async

- OM_uint32 `globus_gss_assist_init_sec_context_async(OM_uint32 minor_status, const gss_cred_id_t cred_handle, gss_ctx_id_t context_handle, char target_name_char, OM_uint32 req_ags, OM_uint32 et_ags, void *input_buffer, size_t input_buffer_len, void *output_bufferp, size_t output_buffer_lenp)`

Will Handle Restrictions

- OM_uint32 `globus_gss_assist_will_handle_restrictions(OM_uint32 minor_status, gss_ctx_id_t context_handle)`

Get Unwrap

- OM_uint32 `globus_gss_assist_get_unwrap(OM_uint32 minor_status, const gss_ctx_id_t context_handle, char *data, size_t length, int token_status, int(gss_assist_get_token)(void *voidp, size_t), void *gss_assist_get_context, FILE *fperr)`

Wrap

- OM_uint32 **globus_gss_assist_wrap_send**(OM_uint32 minor_status, const gss_ctx_id_t context_handle, char data, size_t length, int token_status, int(gss_assist_send_token)(void*, void*, size_t), void gss_assist_send_context, FILEfperr)

De nes

- #de ne **NI_MAXHOST** 255

3.2.1 Detailed Description

Utility functions for GSSAPI.

3.2.2 De ne Documentation

3.2.2.1 #de ne NI_MAXHOST 255

Create a GSS Name structure from the given hostname. This function tries to resolve the given host name string to the canonical DNS name for the host.

Parameters:

hostname The host name or numerical address to be resolved and transform into a GSS Name
authorization_hostname The resulting GSS Name

Returns:

GLOBUS_SUCCESS on successful completion, a error object otherwise

3.2.3 Function Documentation

3.2.3.1 OM_uint32 globus_gss_assist_accept_sec_context(OM_uint32 minor_status gss_ctx_id_t context_handle, const gss_cred_id_t cred_handle, char src_name, OM_uint32 ret_ags, int user_to_user_ag, int token_status, gss_cred_id_t delegated_cred_handle, int(gss_assist_get_token)(void*, void*, size_t), void gss_assist_get_context, int(gss_assist_send_token)(void*, void*, size_t), void gss_assist_send_context)

This routine accepts a GSSAPI security context and is called by the gram_gatekeeper. It isolates the GSSAPI from the rest of the gram code.

Initialize a gssapi security connection. Used by the server. The context_handle is returned, and there is one for each connection. This routine will take care of the looping and token processing, using the supplied get_token and send_token routines.

Parameters:

minor_status gssapi return code
context_handle pointer to returned context.
cred_handle the cred handle obtained by acquire_cred.
src_name char Pointer to char string representation of the client which contacted the server. Maybe NULL if not wanted. Should be freed when done.
ret_ags Pointer to which services are available after the connection is established. Maybe NULL if not wanted.
We will also use this to pass in ags to the globus version of gssapi_ssleay

`user_to_user_ag` Pointer to `ag` to be set if the `src_name` is the same as our name. (Following are particular to this assist routine)

`token_status` assist routine get/send token status

`delegated_cred_handle` pointer to be set to the credential delegated by the client if delegation occurs during the security handshake

`gss_assist_get_token` get token routine

`gss_assist_get_context` arg for the get token routine

`gss_assist_send_token` send token routine

`gss_assist_send_context` arg for the send token routine

Returns:

`GSS_S_COMPLETE` on success Other gss errors on failure.

3.2.3.2 `OM_uint32 globus_gss_assist_accept_sec_context_async (OM_uint32 minor_status gss_ctx_id_t context_handle const gss_cred_id_t cred_handle char *src_name_char OM_uint32 *ret_ags, int user_to_user_ag void *input_buffer, size_t input_buffer_len, void *output_bufferp, size_t output_buffer_len p gss_cred_id_t delegated_cred_handle)`

This is a asynchronous version of the [globus_gss_assist_accept_sec_context\(\)](#) function. Instead of looping itself it passes in and out the read and written buffers and the calling application is responsible for doing the I/O directly.

Parameters:

`minor_status` gssapi return code

`context_handle` pointer to returned context.

`cred_handle` the cred handle obtained by `acquire_cred`.

`src_name_char` pointer to char string representation of the client which contacted the server. Maybe NULL if not wanted. Should be freed when done.

`ret_ags` Pointer to which services are available after the connection is established. Maybe NULL if not wanted. We will also use this to pass in `ags` to the globus version of `gssapi_ssleay`

`user_to_user_ag` Pointer to `ag` to be set if the `src_name` is the same as our name.

`input_buffer` pointer to a buffer received from peer.

`input_buffer_len` length of the buffer `input_buffer`.

`output_bufferp` pointer to a pointer which will be filled in with a pointer to a allocated block of memory. If non-NUL the contents of this block should be written to the peer where they will be fed into the `gss_assist_init_sec_context_async()` function.

`output_buffer_lenp` pointer to an integer which will be filled in with the length of the allocated output buffer pointed to by `output_bufferp`.

`delegated_cred_handle` pointer to be set to the credential delegated by the client if delegation occurs during the security handshake

Returns:

`GSS_S_COMPLETE` on successful completion when this function does not need to be called again.

`GSS_S_CONTINUE_NEEDED` where `output_bufferp` should be sent to the peer and a new `input_buffer` read and this function called again.

Other gss errors on failure.

3.2.3.3 OM_uint32 globus_gss_assist_acquire_cred (OM_uint32 minor_status gss_cred_usage cred_usage gss_cred_id_t output_cred_handle)

Called once at the start of the process, to obtain the credentials the process is running under. The

Parameters:

minor_status pointer for return code

cred_usage GSS_C_INITIATE, GSS_C_ACCEPT, or GSS_C_BOTH

output_cred_handle Pointer to the returned handle. This needs to be passed to many gss routines.

Returns:

GSS_S_COMPLETE on success Other GSS return codes

3.2.3.4 OM_uint32 globus_gss_assist_acquire_cred_ext (OM_uint32 minor_status char desired_name_ char, OM_uint32 time_req const gss_OID set desired_mech gss_cred_usage cred_usage gss_cred_id_t output_cred_handle gss_OID set actual_mech OM_uint32 time_req)

Called once at the start of the process, to obtain the credentials the process is running under. All the parameters of the gss_acquire_cred, except the desired_name is a string of the form: [type:]name. This will be imported with the type.

Returns:

GSS_S_COMPLETE on success Other GSS return codes

See also:

[globus_gsi_gss_acquire_cred](#)

3.2.3.5 OM_uint32 globus_gss_assist_display_status (FILE *fp, char comment OM_uint32 major_status OM_uint32 minor_status int token_status)

Display the messages for the major and minor status on the file pointed at by fp. Takes care of the overloaded major_status if there was a problem with the get_token or send_token routines.

Parameters:

fp a file pointer

comment String to print out before other error messages.

major_status The major status to display

minor_status The minor status to display

token_status token status to display

Returns:

0

3.2.3.6 OM_uint32 globus_gss_assist_display_status_str (char str, char comment OM_uint32 major_status OM_uint32 minor_status int token_status)

Display the messages for the major and minor status and return a string with the messages. Takes care of the overloaded major_status if there was a problem with the get_token or send_token routines.

Parameters:

str pointer to char for returned string. Must be freed

comment String to print out before other error messages.

major_status The major status to display

minor_status The minor status to display

token_statustoken status to display

Returns:

0

3.2.3.7 int globus_gss_assist_gridmap (char* globusidp, char* useridp)

Routines callable from globus based code to map a globusID to a local unix user

GRIDMAP environment variable pointing at the map file. Defaults to gridmap

A gridmap file is required if being run as root. If being run as a user, it is not required, and defaults to the current user who is running the command.

This is the same file used by the gssapi_cleartext but will be used with other gssapi implementations which do not use the gridmap file.

Parameters:

globusidp the GSSAPI name from the client who requested authentication

useridp the resulting user ID name for the local system

Returns:

0 on success -1 if bad arguments 1 on error

3.2.3.8 int globus_gss_assist_userok (char* globusid, char* userid)

Check to see if a particular globusid is authorized to access the given local user account.

Parameters:

globusid the globus id in string form - this should be the user's subject

userid the local account that access is sought for

Returns:

0 on success (authorization allowed) -1 if bad arguments 1 on error

3.2.3.9 int globus_gss_assist_map_local_user (char* local_user, char* globusidp)

Routine for returning the default globus ID associated with a local user name. This is somewhat of a hack since there is not a guaranteed one-to-one mapping. What we do is look for the first entry in the gridmap file that has the local user as the default login. If the user is not a default on any entry, we find the first entry in which the user exists as a secondary mapping.

Parameters:

local_user the local username to find the DN for

globusidp the first DN found that reverse maps from the local_user

Returns:

0 on success, otherwise an error object identifier is returned. Use `globus_error_get` to get the error object from the id. The resulting error object must be freed using `globus_object_free` when it is no longer needed.

See also:

`globus_error_get`
`globus_object_free`

3.2.3.10 OM_uint32 globus_gss_assist_import_sec_context (OM_uint32 minor_status, gss_ctx_id_t context_handle, int token_status, int fd, FILE *fperr)

Import the security context from a file

Parameters:

minor_status GSSAPI return code. This is a Globus Error code (or GLOBUS_SUCCESS) cast to a OM_uint32 pointer. If an error has occurred, the resulting error (from calling `globus_error_get` on this variable) needs to be freed by the caller
 context_handle The imported context
 token_status Errors that occurred while reading from the file
 fd the file descriptor pointing to a file containing the security context
 fperr FILE to write error messages

Returns:

the major status

3.2.3.11 OM_uint32 globus_gss_assist_init_sec_context (OM_uint32 minor_status, const gss_cred_id_t cred_handle, gss_ctx_id_t context_handle, char target_name, char *req_ags, OM_uint32 *ret_ags, int (*token_status)(gss_assist_get_token_fn, void *, void *, size_t), void (*gss_assist_get_context)(gss_assist_send_token_fn, void *, void *, size_t), void (*gss_assist_send_context)(void))

Initialize a gssapi security connection. Used by the client. The context_handle is returned, and there is one for each connection. This routine will take care of the looping and token processing, using the supplied get_token and send_token routines.

Parameters:

minor_status GSSAPI return code. The new minor_status is a `globus_result_t` cast to an OM_uint32. If the call was successful, the minor status is equivalent to GLOBUS_SUCCESS. Otherwise, it is a globus error object ID that can be passed to `globus_error_get` to get the error object. The error object needs to be freed with `globus_object_free`.
 cred_handle the cred handle obtained by `acquire_cred`.
 context_handle pointer to returned context.
 target_name char string representation of the server to be contacted.
 req_ags request args, such as `GSS_C_DELEG_FLAG` for delegation and the `GSS_C_MUTUAL_FLAG` for mutual authentication.
 ret_ags Pointer to which services are available after the connection is established. Maybe NULL if not wanted.

The following are particular to this assist routine:

Parameters:

`token_status` the assist routine's get/send token status
`gss_assist_get_token` function pointer for getting the token
`gss_assist_get_context` `ctx` argument passed to the `gss_assist_get_token` function
`gss_assist_send_token` function pointer for setting the token
`gss_assist_send_context` `ctx` argument passed to the `gss_assist_set_token` function pointer

Returns:

The major status

3.2.3.12 OM_uint32 globus_gss_assist_init_sec_context_async (OM_uint32 minor_status const gss_cred_id_t cred_handle gss_ctx_id_t context_handle char target_name_char OM_uint32 req_ags, OM_uint32 ret_ags, void * input_buffer, size_t input_buffer_len, void * output_buffer, size_t output_buffer_len)

This is a asynchronous version of [globus_gss_assist_init_sec_context\(\)](#) function. Instead of looping itself it passes in and out the read and written buffers and the calling application is responsible for doing the I/O directly.

Parameters:

`minor_status` GSSAPI return code. The new minor status is a `globus_result_t` cast to a `OM_uint32`. If an error occurred (`GSS_ERROR(minor_status)`) the `minor_status` is a `globus_error` object id. The error object can be obtained via `globus_error_get` and should be destroyed with `globus_object_free` when no longer needed. If no error occurred, the minor status is equal to `GLOBUS_SUCCESS`.
`cred_handle` the cred handle obtained by `acquire_cred`.
`context_handle` pointer to returned context.
`target_name_char` character string representation of the server to be contacted.
`req_ags` request `ags`, such as `GSS_C_DELEG_FLAG` for delegation and the `GSS_C_MUTUAL_FLAG` for mutual authentication.
`ret_ags` Pointer to which services are available after the connection is established. Maybe `NULL` if not wanted.
`input_buffer` pointer to a buffer received from peer. Should be `NULL` on `rst` call.
`input_buffer_len` length of the buffer `input_buffer`. Should be zero on `rst` call.
`output_buffer` pointer to a pointer which will be filled in with a pointer to a allocated block of memory. If non-`NULL` the contents of this block should be written to the peer where they will be fed into the `gss_assist_init_sec_context_async()` function.
`output_buffer_len` pointer to an integer which will be filled in with the length of the allocated output buffer pointed to by `output_buffer`.

Returns:

`GSS_S_COMPLETE` on successful completion when this function does not need to be called again.

`GSS_S_CONTINUE_NEEDED` where `output_buffer` should be sent to the peer and a new `input_buffer` read and this function called again.

Other gss errors on failure.

3.2.3.13 OM_uint32 globus_gss_assist_will_handle_restrictions (OM_uint32 minor_status gss_ctx_id_t context_handle)

Sets the context to handle restrictions

Parameters:

minor_status the resulting minor status from setting the context handle
context_handle the context handle to set the minor status of

Returns:

the major status from setting the context

3.2.3.14 OM_uint32 globus_gss_assist_get_unwrap (OM_uint32 minor_status const gss_ctx_id_t *context_handle, char *data, size_t length, int token_status int(gss_assist_get_token(void *token, void *data, size_t *length), void *gss_assist_get_context FILE *fperr)

Gets a token using the specific tokenizing functions, and performs the GSS unwrap of that token

See also:

[gss_unwrap](#)

Parameters:

minor_status GSSAPI return code,

See also:

[gss_unwrap](#)

Parameters:

context_handle the context
data pointer to be set to the unwrapped application data. This must be freed by the caller.
length pointer to be set to the length of the data byte array.
token_status assist routine get/send token status
gss_assist_get_token a detokenizing routine
gss_assist_get_context a context for above routine
fperr error stream to print to

Returns:

GSS_S_COMPLETE on success Other gss errors on failure.

3.2.3.15 OM_uint32 globus_gss_assist_wrap_send (OM_uint32 minor_status const gss_ctx_id_t *context_handle, char *data, size_t length, int token_status int(gss_assist_send_token(void *token, void *data, size_t *length), void *gss_assist_send_context FILE *fperr)

Parameters:

minor_status GSSAPI return code. If the call was successful, the minor status is equal to GLOBUS_SUCCESS.
Otherwise, it is an error object ID for which `globus_error_get()` and `globus_object_free()` can be used to get and destroy it.
context_handle the context.
data pointer to application data to wrap and send
length length of the data array
token_status assist routine get/send token status
gss_assist_send_token a send_token routine

`gss_assist_send_context` arg for the `send_token`
`fperr` le handle to write error message to.

Returns:

`GSS_S_COMPLETE` on sucess Other gss errors on failure.

See also:

`gss_wrap()`

3.3 GSI GSS Assist Constants

Enumerations

- enum`globus_gsi_gss_assist_error_t`
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_SUCCESS`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_ARGUMENTS`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_USER_ID_DOESNT_MATCH`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_IN_GRIDMAP_NO_USER_ENTRY`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_GRIDMAP`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_INVALID_GRIDMAP_FORMAT`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_ERROR_NONE`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_INT`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_WRAP`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_TOKEN`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_EXPORTING_CONTEXT`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_IMPORTING_CONTEXT`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_INITIALIZING_CALLOUT_HANDLE`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_CALLOUT_CONFIG`,
 - `GLOBUS_GSI_GSS_ASSIST_CALLOUT_ERROR`,
 - `GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR`,
 - `GLOBUS_GSI_GSS_ASSIST_GRIDMAP_LOOKUP_FAILED`,
 - `GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_SMALL`,
 - `GLOBUS_GSI_GSS_ASSIST_ERROR_CANONICALIZING_HOSTNAME`

3.3.1 Enumeration Type Documentation

3.3.1.1 enum`globus_gsi_gss_assist_error_t`

GSI GSS Assist Error codes.

Enumeration values:

`GLOBUS_GSI_GSS_ASSIST_ERROR_SUCCESS`Success.
`GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_ARGUMENTS`No user entry in gridmap le.
`GLOBUS_GSI_GSS_ASSIST_ERROR_USER_ID_DOESNT_MATCH`Error user ID doesn't match.

GLOBUS_GSI_GSS_ASSIST_ERROR_IN_GRIDMAP_NO_USER_ENTRYError with arguments passed to function.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_GRIDMAP_ERROR querying gridmap ie.

GLOBUS_GSI_GSS_ASSIST_ERROR_INVALID_GRIDMAP_FORMATInvalid gridmap ie format.

GLOBUS_GSI_GSS_ASSIST_ERROR_ERRNOSystem Error.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_INIT_ERROR during context initialization.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_WRA_ERROR during message wrap.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_TOKEN_ERROR with token.

GLOBUS_GSI_GSS_ASSIST_ERROR_EXPORTING_CONTEXT_ERROR exporting context.

GLOBUS_GSI_GSS_ASSIST_ERROR_IMPORTING_CONTEXT_ERROR importing context.

GLOBUS_GSI_GSS_ASSIST_ERROR_INITIALIZING_CALLOUT_HANDLE_ERROR initializing callout handle.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_CALLOUT_CONFIGURATION_ERROR reading callout configuration.

GLOBUS_GSI_GSS_ASSIST_CALLOUT_ERROR_ERROR invoking callout.

GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR_GSSAPI returned an error.

GLOBUS_GSI_GSS_ASSIST_GRIDMAP_LOOKUP_FAILEDGridmap lookup failure.

GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_SMALLCaller provided insufficient buffer space for local identity.

GLOBUS_GSI_GSS_ASSIST_ERROR_CANONICALIZING_HOSTNAMEFailed to obtain canonical host name.

3.4 Security Token Transport

Token routines using fread and fwrite.

Token Get File Descriptor

- int `globus_gss_assist_token_get(void *arg, void *bufp, size_t sizep)`

Token Send File Descriptor

- int `globus_gss_assist_token_send(void *arg, void *buf, size_t size)`

Token Send File Descriptor Without Length

- int `globus_gss_assist_token_send_fd_without_le(void *arg, void *buf, size_t size)`

Token Send File Descriptor Flag EX

- int `globus_gss_assist_token_send_fd(void *exp, void *buf, size_t size)`

Token Get Nexus

- int `globus_gss_assist_token_get_nexus(void *arg, void *bufp, size_t sizep)`

Token Send Nexus

- int `globus_gss_assist_token_send_nexus`(`void` arg, `void` buf, `size_t` size)

Token Send Nexus Without Length

- int `globus_gss_assist_token_send_nexus_without_length`(`void` arg, `void` buf, `size_t` size)

Token Send Nexus EX

- int `globus_gss_assist_token_send_nexus_ex`(`void` exp, `void` buf, `size_t` size)

3.4.1 Detailed Description

Token routines using fread and fwrite.

Additional code has been added to detect tokens which are sent without a length field. These can currently be only SSL tokens. This does require some knowledge of the underlying GSSAPI, by the application, but is within the guidelines of the GSSAPI specifications.

The get routine will automatically attempt this test, while a new send routine will check again. The old send routine will work as before, sending a 4-byte length.

3.4.2 Function Documentation

3.4.2.1 int `globus_gss_assist_token_get_fd` (`void`*arg, `void` buf, `size_t` size)

Use a open file descriptor to get a token. This function provides parameter types that allow it to be passed to `globus_gss_assist_init_sec_context` and `globus_gss_assist_accept_sec_context`

Parameters:

- arg the FILE stream cast to a void pointer
- buf the resulting token
- sizep the size (number of bytes) read into buf

Returns:

0 on success, -1 on error, -errno on error

3.4.2.2 int `globus_gss_assist_token_send_fd` (`void`*arg, `void` buf, `size_t` size)

Write a token to the open file descriptor. Will write it with a 4 byte length. This function provides parameter types that allow it to be passed to `globus_gss_assist_init_sec_context` and `globus_gss_assist_accept_sec_context`

Parameters:

- arg the FILE stream to send the token on
- buf the token
- size the size of the token in bytes

Returns:

0 on success, -1 on error, -errno on error

3.4.2.3 int globus_gss_assist_token_send_fd_without_length (void*rg, void* buf, size_t size)

Write a token to the open file descriptor. Will write it without a length. so as to

3.4.2.4 int globus_gss_assist_token_send_fd_ex (void*xp, void* buf, size_t size)

Write a token to the open file descriptor. will look at the tag to determine if the length field need to be written.

Parameters:

exp the globus_gss_assist_ex variable that holds the FILEteam and args to be set

buf the token buffer to send

size size of the token buffer

Returns:

0 on success< 0 on error< 0 on errno error (-errno)

3.4.2.5 int globus_gss_assist_token_get_nexus (void*rg, void* bufp, size_t size)

Use a nexus socket to get the tokens.

Additional code has been added to detect tokens which are sent without a length field. These can currently be only SSL tokens. This does require some knowledge of the underlying GSSAPI, by the application, but is within the guidelines of the GSSAPI specifications.

The get routine will automatically attempt this test, while a new send routine will check a tag. The old send routine will work as before, sending a 4-byte length.

Parameters:

arg the globus_io_handle_t to get the token from

bufp the buffer to read the token into

sizep the size of what gets read

Returns:

0 on success< 0 is internal return< 0 is the -errno returned from nexus

3.4.2.6 int globus_gss_assist_token_send_nexus (void*rg, void* buf, size_t size)

Write a token to the nexus io handle. This function provides parameter types that allow it to be passed to [globus_gss_assist_init_sec_context](#) and [globus_gss_assist_accept_sec_context](#)

Parameters:

arg nexus io handle to send the token on

buf the token as a buffer

size the size of the buffer

Returns:

0 on success< 0 on error< 0 on errno error (-errno)

3.4.2.7 int globus_gss_assist_token_send_nexus_without_length (void~~dg~~, void~~dg~~ buf, size_tsize)

Send a token on a nexus IO handle. Using this function the length is not sent.

See also:

[globus_gss_assist_token_get_nexfor](#)(further info).

3.4.2.8 int globus_gss_assist_token_send_nexus_ex (void~~dp~~, void~~dp~~ buf, size_tsize)

Write a token to the open file descriptor. will look at the tag to determine if the length field need to be written.

Parameters:

exp The globus_gss_assist_ex that the wraps the nexus IO handle to send the token on

buf the buffer holding the token

size the size of the buffer

Returns:

0 on success< 0 on error< 0 on errno error (-errno)

Index

Activation, 1

globus_gsi_gss_assist
 globus_gss_assist_accept_sec_context, 4
 globus_gss_assist_accept_sec_context_aSync, 5
 globus_gss_assist_acquire_cred, 5
 globus_gss_assist_acquire_cred_ext, 6
 globus_gss_assist_display_status, 6
 globus_gss_assist_display_status_str, 6
 globus_gss_assist_get_unwrap, 10
 globus_gss_assist_gridmap,
 globus_gss_assist_import_sec_context, 8
 globus_gss_assist_init_sec_context, 8
 globus_gss_assist_init_sec_context_async, 9
 globus_gss_assist_map_local_user, 7
 globus_gss_assist_userok, 7
 globus_gss_assist_will_handle_restrictions, 9
 globus_gss_assist_wrap_send,
 NI_MAXHOST, 4

globus_gsi_gss_assist_activation
 GLOBUS_GSI_GSS_ASSIST_MODULE, 2

GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_SMALL
 globus_gsi_gss_assist_constants, 12

GLOBUS_GSI_GSS_ASSIST_CALLOUT_ERROR
 globus_gsi_gss_assist_constants, 12

globus_gsi_gss_assist_constants
 GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_SMALL, 12

 GLOBUS_GSI_GSS_ASSIST_CALLOUT_ERROR, 12

 GLOBUS_GSI_GSS_ASSIST_ERROR_CANONICALIZING_HOSTNAME, 12

 GLOBUS_GSI_GSS_ASSIST_ERROR_ERRNO, 12

 GLOBUS_GSI_GSS_ASSIST_ERROR_EXPORTING_CONTEXT, 12

 GLOBUS_GSI_GSS_ASSIST_ERROR_IMPORTING_CONTEXT, 12

 GLOBUS_GSI_GSS_ASSIST_ERROR_IN_GRIDMAP_NO_USER_ENTRY, 11

 GLOBUS_GSI_GSS_ASSIST_ERROR_INITIALIZING_CALLOUT_HANDLE, 12

 GLOBUS_GSI_GSS_ASSIST_ERROR_INVALID_GRIDMAP_FORMAT, 12

 GLOBUS_GSI_GSS_ASSIST_ERROR_SUCCESS, 11

 GLOBUS_GSI_GSS_ASSIST_ERROR_USER_ID_DOESNT_MATCH, 11

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_ARGUMENTS, 11

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_CALLOUT_CONFIG, 12

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_GRIDMAP, 12

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_INIT, 12

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_TOKEN, 12

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_WRAP, 12

GLOBUS_GSI_GSS_ASSIST_GRIDMAP_LOOKUP_FAILED, 12

GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR, 12

globus_gsi_gss_assist_constants
 globus_gsi_gss_assist_error, 11

GLOBUS_GSI_GSS_ASSIST_ERROR_CANONICALIZING_HOSTNAME
 globus_gsi_gss_assist_constants, 12

GLOBUS_GSI_GSS_ASSIST_ERROR_ERRNO
 globus_gsi_gss_assist_constants, 12

GLOBUS_GSI_GSS_ASSIST_ERROR_EXPORTING_CONTEXT
 globus_gsi_gss_assist_constants, 12

GLOBUS_GSI_GSS_ASSIST_ERROR_IMPORTING_CONTEXT
 globus_gsi_gss_assist_constants, 12

GLOBUS_GSI_GSS_ASSIST_ERROR_IN_GRIDMAP_NO_USER_ENTRY
 globus_gsi_gss_assist_constants, 11

GLOBUS_GSI_GSS_ASSIST_ERROR_INITIALIZING_CALLOUT_HANDLE
 globus_gsi_gss_assist_constants, 12

GLOBUS_GSI_GSS_ASSIST_ERROR_INVALID_GRIDMAP_FORMAT
 globus_gsi_gss_assist_constants, 12

GLOBUS_GSI_GSS_ASSIST_ERROR_SUCCESS, 11

globus_gsi_gss_assist_error_t
 globus_gsi_gss_assist_constants, 11

GLOBUS_GSI_GSS_ASSIST_ERROR_USER_ID_DOESNT_MATCH
 globus_gsi_gss_assist_constants, 11

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_ARGUMENTS
 globus_gsi_gss_assist_constants, 11

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_CALLOUT_CONFIG
 globus_gsi_gss_assist_constants, 11

globus_gsi_gss_assist_constants¹²,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
GRIDMAP
globus_gsi_gss_assist_constants¹²,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_INIT
globus_gsi_gss_assist_constants¹²,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
TOKEN
globus_gsi_gss_assist_constants¹²,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
WRAP
globus_gsi_gss_assist_constants¹²,
GLOBUS_GSI_GSS_ASSIST_GRIDMAP_-
LOOKUP_FAILED
globus_gsi_gss_assist_constants¹²,
GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR
globus_gsi_gss_assist_constants¹²,
GLOBUS_GSI_GSS_ASSIST_MODULE
globus_gsi_gss_assist_activation²,
globus_gsi_gss_assist_tokens
globus_gss_assist_token_get¹³,
globus_gss_assist_token_get_nexus¹⁴,
globus_gss_assist_token_send¹⁰,
globus_gss_assist_token_send_fd¹⁰,
globus_gss_assist_token_send_fd_without_-
length¹³
globus_gss_assist_token_send_nexus¹⁴,
globus_gss_assist_token_send_nexus¹⁵,
globus_gss_assist_token_send_nexus_without_-
length¹⁴
globus_gss_assist_accept_sec_context
globus_gsi_gss_assist,
globus_gss_assist_accept_sec_context_async
globus_gsi_gss_assist,
globus_gss_assist_acquire_cred
globus_gsi_gss_assist,
globus_gss_assist_acquire_cred_ext
globus_gsi_gss_assist,
globus_gss_assist_display_status
globus_gsi_gss_assist,
globus_gss_assist_display_status_str
globus_gsi_gss_assist,
globus_gss_assist_get_unwrap
globus_gsi_gss_assist¹⁰
globus_gss_assist_gridmap
globus_gsi_gss_assist,
globus_gss_assist_import_sec_context
globus_gsi_gss_assist,
globus_gss_assist_init_sec_context
globus_gsi_gss_assist,
globus_gss_assist_init_sec_context_async
globus_gsi_gss_assist,
globus_gss_assist_map_local_user
globus_gsi_gss_assist⁷,
globus_gss_assist_token_get_fd
globus_gsi_gss_assist_token¹³,
globus_gss_assist_token_get_nexus
globus_gsi_gss_assist_token¹⁴,
globus_gss_assist_token_send_fd
globus_gsi_gss_assist_token¹³,
globus_gss_assist_token_send_fd_ex
globus_gsi_gss_assist_token¹⁴,
globus_gss_assist_token_send_fd_without_length
globus_gsi_gss_assist_token¹³,
globus_gss_assist_token_send_nexus
globus_gsi_gss_assist_token¹⁴,
globus_gss_assist_token_send_nexus_ex
globus_gsi_gss_assist_token¹⁵,
globus_gss_assist_token_send_nexus_without_length
globus_gsi_gss_assist_token¹⁴,
globus_gss_assist_userok
globus_gsi_gss_assist,
globus_gss_assist_will_handle_restrictions
globus_gsi_gss_assist⁹,
globus_gss_assist_wrap_send
globus_gsi_gss_assist¹⁰
GSI GSS Assist Constants¹⁶
NI_MAXHOST
globus_gsi_gss_assist⁴,
Security Token Transpor¹²
Utility Functions²