

globus gss assist
4.0

Generated by Doxygen 1.5.7.1

Tue Aug 11 14:57:11 2009

Contents

1	Globus GSI GSS Assist	1
2	Module Index	1
2.1	Modules	1
3	Module Documentation	1
3.1	Activation	1
3.1.1	Detailed Description	2
3.1.2	Define Documentation	2
3.2	Utility Functions	2
3.2.1	Detailed Description	2
3.2.2	Define Documentation	2
3.2.3	Function Documentation	3
3.3	GSI GSS Assist Constants	9
3.3.1	Enumeration Type Documentation	10
3.4	Security Token Transport	11
3.4.1	Detailed Description	11
3.4.2	Function Documentation	11

1 Globus GSI GSS Assist

The GSS Assist code provides convenience functions for using the Globus GSS-API.

2 Module Index

2.1 Modules

Here is a list of all modules:

Activation	1
Utility Functions	2
GSI GSS Assist Constants	9
Security Token Transport	11

3 Module Documentation

3.1 Activation

Globus GSI GSS Assist uses standard Globus module activation and deactivation.

Defines

- #define `GLOBUS_GSI_GSS_ASSIST_MODULE`

3.1.1 Detailed Description

Globus GSI GSS Assist uses standard Globus module activation and deactivation.

Before any Globus GSS Assist functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GSI_GSS_ASSIST_MODULE);
```

This function returns `GLOBUS_SUCCESS` if Globus GSI GSS Assist was successfully initialized, and you are therefore allowed to call GSS Assist functions. Otherwise, an error code is returned, and GSS Assist functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GSS Assist, the following function must be called:

```
globus_module_deactivate(GLOBUS_GSI_GSS_ASSIST_MODULE)
```

This function should be called once for each time Globus GSI GSS Assist was activated.

3.1.2 Define Documentation

3.1.2.1 #define `GLOBUS_GSI_GSS_ASSIST_MODULE`

Module descriptor.

3.2 Utility Functions

Utility functions for GSSAPI.

Defines

- #define `NI_MAXHOST` 255

3.2.1 Detailed Description

Utility functions for GSSAPI.

3.2.2 Define Documentation

3.2.2.1 #define `NI_MAXHOST` 255

Create a GSS Name structure from the given hostname.

This function tries to resolve the given host name string to the canonical DNS name for the host.

Parameters:

hostname The host name or numerical address to be resolved and transform into a GSS Name

authorization_hostname The resulting GSS Name

Returns:

`GLOBUS_SUCCESS` on successful completion, a error object otherwise

3.2.3 Function Documentation

3.2.3.1 OM_uint32 globus_gss_assist_accept_sec_context (OM_uint32 * *minor_status*, gss_ctx_id_t * *context_handle*, const gss_cred_id_t *cred_handle*, char ** *src_name_char*, OM_uint32 * *ret_flags*, int * *user_to_user_flag*, int * *token_status*, gss_cred_id_t * *delegated_cred_handle*, int(*) (void *, void **, size_t *) *gss_assist_get_token*, void * *gss_assist_get_context*, int(*) (void *, void *, size_t) *gss_assist_send_token*, void * *gss_assist_send_context*)

This routine accepts a GSSAPI security context and is called by the gram_gatekeeper.

It isolates the GSSAPI from the rest of the gram code.

Initialize a gssapi security connection. Used by the server. The context_handle is returned, and there is one for each connection. This routine will take care of the looping and token processing, using the supplied get_token and send_token routines.

Parameters:

minor_status gssapi return code

context_handle pointer to returned context.

cred_handle the cred handle obtained by acquire_cred.

src_name_char Pointer to char string representation of the client which contacted the server. Maybe NULL if not wanted. Should be freed when done.

ret_flags Pointer to which services are available after the connection is established. Maybe NULL if not wanted. We will also use this to pass in flags to the globus version of gssapi_ssleay

user_to_user_flag Pointer to flag to be set if the src_name is the same as our name. (Following are particular to this assist routine)

token_status assist routine get/send token status

delegated_cred_handle pointer to be set to the credential delegated by the client if delegation occurs during the security handshake

gss_assist_get_token a get token routine

gss_assist_get_context first arg for the get token routine

gss_assist_send_token a send token routine

gss_assist_send_context first arg for the send token routine

Returns:

GSS_S_COMPLETE on success Other gss errors on failure.

3.2.3.2 OM_uint32 globus_gss_assist_accept_sec_context_async (OM_uint32 * *minor_status*, gss_ctx_id_t * *context_handle*, const gss_cred_id_t *cred_handle*, char ** *src_name_char*, OM_uint32 * *ret_flags*, int * *user_to_user_flag*, void * *input_buffer*, size_t *input_buffer_len*, void ** *output_bufferp*, size_t * *output_buffer_lenp*, gss_cred_id_t * *delegated_cred_handle*)

This is an asynchronous version of the [globus_gss_assist_accept_sec_context\(\)](#) function.

Instead of looping itself it passes in and out the read and written buffers and the calling application is responsible for doing the I/O directly.

Parameters:

minor_status gssapi return code

context_handle pointer to returned context.

cred_handle the cred handle obtained by acquire_cred.

src_name_char Pointer to char string representation of the client which contacted the server. Maybe NULL if not wanted. Should be freed when done.

ret_flags Pointer to which services are available after the connection is established. Maybe NULL if not wanted. We will also use this to pass in flags to the globus version of gssapi_ssleay

user_to_user_flag Pointer to flag to be set if the src_name is the same as our name.

input_buffer pointer to a buffer received from peer.

input_buffer_len length of the buffer input_buffer.

output_bufferp pointer to a pointer which will be filled in with a pointer to a allocated block of memory. If non-NULL the contents of this block should be written to the peer where they will be fed into the gss_assist_init_sec_context_async() function.

output_buffer_lenp pointer to an integer which will be filled in with the length of the allocated output buffer pointed to by *output_bufferp.

delegated_cred_handle pointer to be set to the credential delegated by the client if delegation occurs during the security handshake

Returns:

GSS_S_COMPLETE on successful completion when this function does not need to be called again.

GSS_S_CONTINUE_NEEDED when *output_bufferp should be sent to the peer and a new input_buffer read and this function called again.

Other gss errors on failure.

3.2.3.3 OM_uint32 globus_gss_assist_acquire_cred (OM_uint32 * minor_status, gss_cred_usage_t cred_usage, gss_cred_id_t * output_cred_handle)

Called once at the start of the process, to obtain the credentials the process is running under.

The

Parameters:

minor_status pointer for return code

cred_usage GSS_C_INITIATE, GSS_C_ACCEPT, or GSS_C_BOTH

output_cred_handle Pointer to the returned handle. This needs to be passed to many gss routines.

Returns:

GSS_S_COMPLETE on success Other GSS return codes

3.2.3.4 OM_uint32 globus_gss_assist_acquire_cred_ext (OM_uint32 * minor_status, char * desired_name_char, OM_uint32 time_req, const gss_OID_set desired_mechs, gss_cred_usage_t cred_usage, gss_cred_id_t * output_cred_handle, gss_OID_set * actual_mechs, OM_uint32 * time_rec)

Called once at the start of the process, to obtain the credentials the process is running under.

All the parameters of the gss_acquire_cred, except the desired_name is a string of the form: [type:]name. This will be imported with the type.

Returns:

GSS_S_COMPLETE on success Other GSS return codes

See also:

globus_gsi_gss_acquire_cred

3.2.3.5 OM_uint32 globus_gss_assist_display_status (FILE * *fp*, char * *comment*, OM_uint32 *major_status*, OM_uint32 *minor_status*, int *token_status*)

Display the messages for the major and minor status on the file pointed at by *fp*.

Takes care of the overloaded *major_status* if there was a problem with the *get_token* or *send_token* routines.

Parameters:

fp a file pointer
comment String to print out before other error messages.
major_status The major status to display
minor_status The minor status to display
token_status token status to display

Returns:

0

3.2.3.6 OM_uint32 globus_gss_assist_display_status_str (char ** *str*, char * *comment*, OM_uint32 *major_status*, OM_uint32 *minor_status*, int *token_status*)

Display the messages for the major and minor status and return a string with the messages.

Takes care of the overloaded *major_status* if there was a problem with the *get_token* or *send_token* routines.

Parameters:

str pointer to char * for returned string. Must be freed
comment String to print out before other error messages.
major_status The major status to display
minor_status The minor status to display
token_status token status to display

Returns:

0

3.2.3.7 int globus_gss_assist_gridmap (char * *globusidp*, char ** *useridp*)

Routines callable from globus based code to map a globusID to a local unix user.

GRIDMAP environment variable pointing at the map file. Defaults to ~/.gridmap

A gridmap file is required if being run as root. if being run as a user, it is not required, and defaults to the current user who is running the command.

This is the same file used by the *gssapi_cleartext* but will be used with other *gssapi* implementations which do not use the *gridmap* file.

Parameters:

globusidp the GSSAPI name from the client who requested authentication
useridp the resulting user ID name for the local system

Returns:

0 on success -1 if bad arguments 1 on error

3.2.3.8 int globus_gss_assist_userok (char * *globusid*, char * *userid*)

Check to see if a particular globusid is authorized to access the given local user account.

Parameters:

globusid the globus id in string form - this should be the user's subject

userid the local account that access is sought for

Returns:

0 on success (authorization allowed) -1 if bad arguments 1 on error

3.2.3.9 int globus_gss_assist_map_local_user (char * *local_user*, char ** *globusidp*)

Routine for returning the default globus ID associated with a local user name.

This is somewhat of a hack since there is not a guaranteed one-to-one mapping. What we do is look for the first entry in the gridmap file that has the local user as the default login. If the user is not a default on any entry, we find the first entry in which the user exists as a secondary mapping.

Parameters:

local_user the local username to find the DN for

globusidp the first DN found that reverse maps from the local_user

Returns:

0 on success, otherwise an error object identifier is returned. use globus_error_get to get the error object from the id. The resulting error object must be freed using globus_object_free when it is no longer needed.

See also:

globus_error_get

globus_object_free

3.2.3.10 OM_uint32 globus_gss_assist_import_sec_context (OM_uint32 * *minor_status*, gss_ctx_id_t * *context_handle*, int * *token_status*, int *fdp*, FILE * *fperr*)

Import the security context from a file.

Parameters:

minor_status GSSAPI return code. This is a Globus Error code (or GLOBUS_SUCCESS) cast to a OM_uint32 pointer. If an error has occurred, the resulting error (from calling globus_error_get on this variable) needs to be freed by the caller

context_handle The imported context

token_status Errors that occurred while reading from the file

fdp the file descriptor pointing to a file containing the security context

fperr FILE * to write error messages

Returns:

the major status

3.2.3.11 OM_uint32 globus_gss_assist_init_sec_context (OM_uint32 * *minor_status*, const gss_cred_id_t *cred_handle*, gss_ctx_id_t * *context_handle*, char * *target_name_char*, OM_uint32 *req_flags*, OM_uint32 * *ret_flags*, int * *token_status*, int(*)(void *, void **, size_t *) *gss_assist_get_token*, void * *gss_assist_get_context*, int(*)(void *, void *, size_t) *gss_assist_send_token*, void * *gss_assist_send_context*)

Initialize a gssapi security connection.

Used by the client. The *context_handle* is returned, and there is one for each connection. This routine will take care of the looping and token processing, using the supplied *get_token* and *send_token* routines.

Parameters:

minor_status GSSAPI return code. The new *minor_status* is a *globus_result_t* cast to an *OM_uint32*. If the call was successful, the *minor_status* is equivalent to *GLOBUS_SUCCESS*. Otherwise, it is a *globus* error object ID that can be passed to *globus_error_get* to get the error object. The error object needs to be freed with *globus_object_free*.

cred_handle the cred handle obtained by *acquire_cred*.

context_handle pointer to returned context.

target_name_char char string representation of the server to be contacted.

req_flags request flags, such as *GSS_C_DELEG_FLAG* for delegation and the *GSS_C_MUTUAL_FLAG* for mutual authentication.

ret_flags Pointer to which services are available after the connection is established. Maybe NULL if not wanted.

The Following are particular to this assist routine:

Parameters:

token_status the assist routine's get/send token status

gss_assist_get_token function pointer for getting the token

gss_assist_get_context first argument passed to the *gss_assist_get_token* function

gss_assist_send_token function pointer for setting the token

gss_assist_send_context first argument passed to the *gss_assist_set_token* function pointer

Returns:

The major status

3.2.3.12 OM_uint32 globus_gss_assist_init_sec_context_async (OM_uint32 * *minor_status*, const gss_cred_id_t *cred_handle*, gss_ctx_id_t * *context_handle*, char * *target_name_char*, OM_uint32 *req_flags*, OM_uint32 * *ret_flags*, void * *input_buffer*, size_t *input_buffer_len*, void ** *output_bufferp*, size_t * *output_buffer_lenp*)

This is an asynchronous version of the [globus_gss_assist_init_sec_context\(\)](#) function.

Instead of looping itself it passes in and out the read and written buffers and the calling application is responsible for doing the I/O directly.

Parameters:

minor_status GSSAPI return code. The new *minor_status* is a *globus_result_t* cast to a *OM_uint32*. If an error occurred (*GSS_ERROR*(*major_status*)) the *minor_status* is a *globus* error object id. The error object can be obtained via *globus_error_get* and should be destroyed with *globus_object_free* when no longer needed. If no error occurred, the *minor_status* is equal to *GLOBUS_SUCCESS*.

cred_handle the cred handle obtained by *acquire_cred*.

context_handle pointer to returned context.

target_name_char char string representation of the server to be contacted.

req_flags request flags, such as GSS_C_DELEG_FLAG for delegation and the GSS_C_MUTUAL_FLAG for mutual authentication.

ret_flags Pointer to which services are available after the connection is established. Maybe NULL if not wanted.

input_buffer pointer to a buffer received from peer. Should be NULL on first call.

input_buffer_len length of the buffer input_buffer. Should be zero on first call.

output_bufferp pointer to a pointer which will be filled in with a pointer to a allocated block of memory. If non-NULL the contents of this block should be written to the peer where they will be fed into the gss_assist_init_sec_context_async() function.

output_buffer_lenp pointer to an integer which will be filled in with the length of the allocated output buffer pointed to by *output_bufferp.

Returns:

GSS_S_COMPLETE on successful completion when this function does not need to be called again.

GSS_S_CONTINUE_NEEDED when *output_bufferp should be sent to the peer and a new input_buffer read and this function called again.

Other gss errors on failure.

3.2.3.13 OM_uint32 globus_gss_assist_will_handle_restrictions (OM_uint32 * minor_status, gss_ctx_id_t * context_handle)

Sets the context to handle restrictions.

Parameters:

minor_status the resulting minor status from setting the context handle

context_handle the context handle to set the minor status of

Returns:

the major status from setting the context

3.2.3.14 OM_uint32 globus_gss_assist_get_unwrap (OM_uint32 * minor_status, const gss_ctx_id_t context_handle, char ** data, size_t * length, int * token_status, int(*) (void *, void **, size_t *) gss_assist_get_token, void * gss_assist_get_context, FILE * fperr)

Gets a token using the specific tokenizing functions, and performs the GSS unwrap of that token.

See also:

gss_unwrap

Parameters:

minor_status GSSAPI return code,

See also:

gss_unwrap

Parameters:

context_handle the context

data pointer to be set to the unwrapped application data. This must be freed by the caller.

length pointer to be set to the length of the *data* byte array.

token_status assist routine get/send token status

gss_assist_get_token a detokenizing routine

gss_assist_get_context first arg for above routine

fperr error stream to print to

Returns:

GSS_S_COMPLETE on success Other gss errors on failure.

3.2.3.15 OM_uint32 globus_gss_assist_wrap_send (OM_uint32 * *minor_status*, const gss_ctx_id_t *context_handle*, char * *data*, size_t *length*, int * *token_status*, int (*)(void *, void *, size_t) *gss_assist_send_token*, void * *gss_assist_send_context*, FILE * *fperr*)

Parameters:

minor_status GSSAPI return code. If the call was successful, the minor status is equal to GLOBUS_SUCCESS. Otherwise, it is an error object ID for which globus_error_get() and globus_object_free() can be used to get and destroy it.

context_handle the context.

data pointer to application data to wrap and send

length length of the *data* array

token_status assist routine get/send token status

gss_assist_send_token a send_token routine

gss_assist_send_context first arg for the send_token

fperr file handle to write error message to.

Returns:

GSS_S_COMPLETE on success Other gss errors on failure.

See also:

gss_wrap()

3.3 GSI GSS Assist Constants

Enumerations

- enum globus_gsi_gss_assist_error_t {

GLOBUS_GSI_GSS_ASSIST_ERROR_SUCCESS = 0,

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_ARGUMENTS = 1,

GLOBUS_GSI_GSS_ASSIST_ERROR_USER_ID_DOESNT_MATCH = 2,

GLOBUS_GSI_GSS_ASSIST_ERROR_IN_GRIDMAP_NO_USER_ENTRY = 3,

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_GRIDMAP = 4,

GLOBUS_GSI_GSS_ASSIST_ERROR_INVALID_GRIDMAP_FORMAT = 5,

```

GLOBUS_GSI_GSS_ASSIST_ERROR_ERRNO = 6,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_INIT = 7,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_WRAP = 8,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_TOKEN = 9,
GLOBUS_GSI_GSS_ASSIST_ERROR_EXPORTING_CONTEXT = 10,
GLOBUS_GSI_GSS_ASSIST_ERROR_IMPORTING_CONTEXT = 11,
GLOBUS_GSI_GSS_ASSIST_ERROR_INITIALIZING_CALLOUT_HANDLE = 12,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_CALLOUT_CONFIG = 13,
GLOBUS_GSI_GSS_ASSIST_CALLOUT_ERROR = 14,
GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR = 15,
GLOBUS_GSI_GSS_ASSIST_GRIDMAP_LOOKUP_FAILED = 16,
GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_SMALL = 17,
GLOBUS_GSI_GSS_ASSIST_ERROR_CANONICALIZING_HOSTNAME = 18 }

```

3.3.1 Enumeration Type Documentation

3.3.1.1 enum globus_gsi_gss_assist_error_t

GSI GSS Assist Error codes.

Enumerator:

GLOBUS_GSI_GSS_ASSIST_ERROR_SUCCESS Success.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_ARGUMENTS No user entry in gridmap file.

GLOBUS_GSI_GSS_ASSIST_ERROR_USER_ID_DOESNT_MATCH Error user ID doesn't match.

GLOBUS_GSI_GSS_ASSIST_ERROR_IN_GRIDMAP_NO_USER_ENTRY Error with arguments passed to function.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_GRIDMAP Error querying gridmap file.

GLOBUS_GSI_GSS_ASSIST_ERROR_INVALID_GRIDMAP_FORMAT Invalid gridmap file format.

GLOBUS_GSI_GSS_ASSIST_ERROR_ERRNO System Error.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_INIT Error during context initialization.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_WRAP Error during message wrap.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_TOKEN Error with token.

GLOBUS_GSI_GSS_ASSIST_ERROR_EXPORTING_CONTEXT Error exporting context.

GLOBUS_GSI_GSS_ASSIST_ERROR_IMPORTING_CONTEXT Error importing context.

GLOBUS_GSI_GSS_ASSIST_ERROR_INITIALIZING_CALLOUT_HANDLE Error initializing callout handle.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_CALLOUT_CONFIG Error reading callout configuration.

GLOBUS_GSI_GSS_ASSIST_CALLOUT_ERROR Error invoking callout.

GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR A GSSAPI returned an error.

GLOBUS_GSI_GSS_ASSIST_GRIDMAP_LOOKUP_FAILED Gridmap lookup failure.

GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_SMALL Caller provided insufficient buffer space for local identity.

GLOBUS_GSI_GSS_ASSIST_ERROR_CANONICALIZING_HOSTNAME Failed to obtain canonical host name.

3.4 Security Token Transport

Token routines using fread and fwrite.

3.4.1 Detailed Description

Token routines using fread and fwrite.

Additional code has been added to detect tokens which are sent without a length field. These can currently be only SSL tokens. This does require some knowledge of the underlying GSSAPI, by the application, but is within the guidelines of the GSSAPI specifications.

The get routine will automatically attempt this test, while a new send routine will check a flag. The old send routine will work as before, sending a 4-byte length.

3.4.2 Function Documentation

3.4.2.1 `int globus_gss_assist_token_get_fd (void * arg, void ** bufp, size_t * sizep)`

Use a open file descriptor to get a token.

This function provides parameter types that allow it to be passed to [globus_gss_assist_init_sec_context](#) and [globus_gss_assist_accept_sec_context](#)

Parameters:

- arg* the FILE * stream cast to a void pointer
- bufp* the resulting token
- sizep* the size (number of bytes) read into bufp

Returns:

0 on success > 0 is internal return < 0 is the -errno

3.4.2.2 `int globus_gss_assist_token_send_fd (void * arg, void * buf, size_t size)`

Write a token to the open file descriptor.

Will write it with a 4 byte length. This function provides parameter types that allow it to be passed to [globus_gss_assist_init_sec_context](#) and [globus_gss_assist_accept_sec_context](#)

Parameters:

- arg* the FILE * stream to send the token on
- buf* the token
- size* the size of the token in bytes

Returns:

0 on success >0 on error <0 on errno error

3.4.2.3 `int globus_gss_assist_token_send_fd_without_length (void * arg, void * buf, size_t size)`

Write a token to the open file descriptor.

Will write it without a length. so as to

3.4.2.4 `int globus_gss_assist_token_send_fd_ex (void * exp, void * buf, size_t size)`

Write a token to the open file descriptor.

will look at the flag to determine if the length field need to be written.

Parameters:

exp the globus_gss_assist_ex variable that holds the FILE * stream and flags to bet set

buf the token buffer to send

size size of the token buffer

Returns:

0 on success >0 on error <0 on errno error (-errno)

3.4.2.5 `int globus_gss_assist_token_get_nexus (void * arg, void ** bufp, size_t * sizep)`

Use a nexus socket to get the tokens

Additional code has been added to detect tokens which are sent without a length field.

These can currently be only SSL tokens. This does require some knowledge of the underlying GSSAPI, by the application, but is within the guidelines of the GSSAPI specifications.

The get routine will automatically attempt this test, while a new send routine will check a flag. The old send routine will work as before, sending a 4-byte length.

Parameters:

arg the globus_io_handle_t to get the token from

bufp the buffer to read the token into

sizep the size of what gets read

Returns:

0 on success > 0 is internal return < 0 is the -errno returned from nexus

3.4.2.6 `int globus_gss_assist_token_send_nexus (void * arg, void * buf, size_t size)`

Write a token to the nexus io handle.

This function provides parameter types that allow it to be passed to [globus_gss_assist_init_sec_context](#) and [globus_gss_assist_accept_sec_context](#)

Parameters:

arg nexus io handle to send the token on

buf the token as a buffer

size the size of the buffer

Returns:

0 on success >0 on error <0 on errno error (-errno)

3.4.2.7 `int globus_gss_assist_token_send_nexus_without_length (void * arg, void * buf, size_t size)`

Send a token on a nexus IO handle.

Using this function the length is not sent.

See also:

[globus_gss_assist_token_get_nexus\(\)](#) for further info.

3.4.2.8 `int globus_gss_assist_token_send_nexus_ex (void * exp, void * buf, size_t size)`

Write a token to the open file descriptor.

will look at the flag to determine if the length field need to be written.

Parameters:

exp The globus_gss_assist_ex that the wraps the nexus IO handle to send the token on

buf the buffer holding the token

size the size of the buffer

Returns:

0 on success >0 on error <0 on errno error (-errno)

Index

Activation, [1](#)

GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_-
SMALL

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_CALLOUT_ERROR
globus_gsi_gss_assist_constants, [10](#)

globus_gsi_gss_assist_constants

GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_-
SMALL, [10](#)

GLOBUS_GSI_GSS_ASSIST_CALLOUT_-
ERROR, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_-
CANONICALIZING_HOSTNAME, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_-
ERRNO, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_-
EXPORTING_CONTEXT, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_-
IMPORTING_CONTEXT, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_IN_-
GRIDMAP_NO_USER_ENTRY, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_-
INITIALIZING_CALLOUT_HANDLE,
[10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_-
INVALID_GRIDMAP_FORMAT, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_-
SUCCESS, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_USER_-
ID_DOESNT_MATCH, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
ARGUMENTS, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
CALLOUT_CONFIG, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
GRIDMAP, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
INIT, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
TOKEN, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
WRAP, [10](#)

GLOBUS_GSI_GSS_ASSIST_GRIDMAP_-
LOOKUP_FAILED, [10](#)

GLOBUS_GSI_GSS_ASSIST_GSSAPI_-
ERROR, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_-
CANONICALIZING_HOSTNAME

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_ERRNO
globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_-
EXPORTING_CONTEXT

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_-
IMPORTING_CONTEXT

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_IN_-
GRIDMAP_NO_USER_ENTRY

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_-
INITIALIZING_CALLOUT_HANDLE

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_INVALID_-
GRIDMAP_FORMAT

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_SUCCESS
globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_USER_ID_-
DOESNT_MATCH

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
ARGUMENTS

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
CALLOUT_CONFIG

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
GRIDMAP

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_INIT
globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
TOKEN

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_-
WRAP

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_GRIDMAP_-
LOOKUP_FAILED

globus_gsi_gss_assist_constants, [10](#)

GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR
globus_gsi_gss_assist_constants, [10](#)

globus_gsi_gss_assist

globus_gss_assist_accept_sec_context, [2](#)

globus_gss_assist_accept_sec_context_async, [3](#)

globus_gss_assist_acquire_cred, [4](#)

globus_gss_assist_acquire_cred_ext, [4](#)

globus_gss_assist_display_status, [4](#)

globus_gss_assist_display_status_str, [4](#)

globus_gss_assist_get_unwrap, [8](#)

globus_gss_assist_gridmap, [5](#)

globus_gss_assist_import_sec_context, [6](#)

globus_gss_assist_init_sec_context, [6](#)

- globus_gss_assist_init_sec_context_async, [7](#)
 - globus_gss_assist_map_local_user, [5](#)
 - globus_gss_assist_userok, [5](#)
 - globus_gss_assist_will_handle_restrictions, [8](#)
 - globus_gss_assist_wrap_send, [8](#)
 - NI_MAXHOST, [2](#)
- globus_gsi_gss_assist_activation
 - GLOBAL_GSI_GSS_ASSIST_MODULE, [2](#)
- globus_gsi_gss_assist_constants
 - globus_gsi_gss_assist_error_t, [10](#)
- globus_gsi_gss_assist_error_t
 - globus_gsi_gss_assist_constants, [10](#)
- GLOBAL_GSI_GSS_ASSIST_MODULE
 - globus_gsi_gss_assist_activation, [2](#)
- globus_gsi_gss_assist_tokens
 - globus_gss_assist_token_get_fd, [11](#)
 - globus_gss_assist_token_get_nexus, [11](#)
 - globus_gss_assist_token_send_fd, [11](#)
 - globus_gss_assist_token_send_fd_ex, [11](#)
 - globus_gss_assist_token_send_fd_without_length, [11](#)
 - globus_gss_assist_token_send_nexus, [12](#)
 - globus_gss_assist_token_send_nexus_ex, [12](#)
 - globus_gss_assist_token_send_nexus_without_length, [12](#)
- globus_gss_assist_accept_sec_context
 - globus_gsi_gss_assist, [2](#)
- globus_gss_assist_accept_sec_context_async
 - globus_gsi_gss_assist, [3](#)
- globus_gss_assist_acquire_cred
 - globus_gsi_gss_assist, [4](#)
- globus_gss_assist_acquire_cred_ext
 - globus_gsi_gss_assist, [4](#)
- globus_gss_assist_display_status
 - globus_gsi_gss_assist, [4](#)
- globus_gss_assist_display_status_str
 - globus_gsi_gss_assist, [4](#)
- globus_gss_assist_get_unwrap
 - globus_gsi_gss_assist, [8](#)
- globus_gss_assist_gridmap
 - globus_gsi_gss_assist, [5](#)
- globus_gss_assist_import_sec_context
 - globus_gsi_gss_assist, [6](#)
- globus_gss_assist_init_sec_context
 - globus_gsi_gss_assist, [6](#)
- globus_gss_assist_init_sec_context_async
 - globus_gsi_gss_assist, [7](#)
- globus_gss_assist_map_local_user
 - globus_gsi_gss_assist, [5](#)
- globus_gss_assist_token_get_fd
 - globus_gsi_gss_assist_tokens, [11](#)
- globus_gss_assist_token_get_nexus
 - globus_gsi_gss_assist_tokens, [11](#)
- globus_gss_assist_token_send_fd
 - globus_gsi_gss_assist_tokens, [11](#)
- globus_gss_assist_token_send_fd_ex
 - globus_gsi_gss_assist_tokens, [11](#)
- globus_gss_assist_token_send_fd_without_length
 - globus_gsi_gss_assist_tokens, [11](#)
- globus_gss_assist_token_send_nexus
 - globus_gsi_gss_assist_tokens, [12](#)
- globus_gss_assist_token_send_nexus_ex
 - globus_gsi_gss_assist_tokens, [12](#)
- globus_gss_assist_token_send_nexus_without_length
 - globus_gsi_gss_assist_tokens, [12](#)
- globus_gss_assist_userok
 - globus_gsi_gss_assist, [5](#)
- globus_gss_assist_will_handle_restrictions
 - globus_gsi_gss_assist, [8](#)
- globus_gss_assist_wrap_send
 - globus_gsi_gss_assist, [8](#)
- GSI GSS Assist Constants, [9](#)
- NI_MAXHOST
 - globus_gsi_gss_assist, [2](#)
- Security Token Transport, [10](#)
- Utility Functions, [2](#)