

globus xio gsi driver Reference Manual

0.6

Generated by Doxygen 1.3.5

Fri Jun 26 23:43:33 2009

Contents

1 globus xio gsi driver Module Index	1
2 globus xio gsi driver Module Documentation	1

1 globus xio gsi driver Module Index

1.1 globus xio gsi driver Modules

Here is a list of all modules:

Globus XIO GSI Driver	1
Opening/Closing	2
Reading/Writing	2
Server	2
Env Variables	2
Attributes and Cntls	2
Types	13
Error Types	15

2 globus xio gsi driver Module Documentation

2.1 Globus XIO GSI Driver

The GSI driver.

Modules

- [Opening/Closing](#)
- [Reading/Writing](#)
- [Server](#)
- [Env Variables](#)
- [Attributes and Cntls](#)
- [Types](#)
- [Error Types](#)

2.1.1 Detailed Description

The GSI driver.

2.2 Opening/Closing

An XIO handle with the gsi driver can be created with either `globus_xio_handle_create()` or `globus_xio_server_register_accept()`.

If the handle is created with `globus_xio_server_register_accept()`, the `globus_xio_register_open()` call will proceed to accept a GSSAPI security context. Upon successful completion of the open, ie after the open callback has been called, the application may proceed to read or write data associated with the GSI session.

If the handle is created with `globus_xio_handle_create()`, then the XIO handle will implement the client-side (init) of the GSSAPI call sequence and establish a security context with the accepting side indicated by the `contact_string` passed to `globus_xio_register_open()`.

2.3 Reading/Writing

The GSI driver behaves similar to the underlying transport driver with respect to reads and writes, except for the try-read and try-write operations (ie. `waitforbytes == 0`) which always return immediately. This is due to the fact that the security layer needs to read and write tokens of a certain minimal size and thus needs to rely on the underlying transport to handle greater than 0 reads/write which is not possible in "try" mode.

2.4 Server

`globus_xio_server_create()` causes a new transport-specific listener socket to be created to handle new GSI connections. `globus_xio_server_register_accept()` will accept a new connection for processing. `globus_xio_server_register_close()` cleans up the internal resources associated with the http server and calls close on the listener.

All accepted handles inherit all gsi specific attributes set in the `globus_xio_server_create()`, but can be overridden with the attr to `globus_xio_register_open()`. Furthermore, accepted handles will use the GSSAPI accept security context call unless explicitly overridden during the `globus_xio_register_open()` call ([GLOBUS_XIO_GSI_FORCE_SERVER_MODE](#)).

2.5 Env Variables

The gsi driver uses the following environment variables

- X509_USER_PROXY
- X509_USER_CERT
- X509_USER_KEY
- X509_CERT_DIR

For details see [Globus: GSI Environment Variables](#)

2.6 Attributes and Cntls

Enumerations

- enum [globus_xio_gsi_cmd_t](#)
 - [GLOBUS_XIO_GSI_SET_CREDENTIAL](#)
 - [GLOBUS_XIO_GSI_GET_CREDENTIAL](#)

GLOBUS_XIO_GSI_SET_GSSAPI_REQ_FLAGS
 GLOBUS_XIO_GSI_GET_GSSAPI_REQ_FLAGS
 GLOBUS_XIO_GSI_SET_PROXY_MODE
 GLOBUS_XIO_GSI_GET_PROXY_MODE
 GLOBUS_XIO_GSI_SET_AUTHORIZATION_MODE
 GLOBUS_XIO_GSI_GET_AUTHORIZATION_MODE
 GLOBUS_XIO_GSI_SET_DELEGATION_MODE
 GLOBUS_XIO_GSI_GET_DELEGATION_MODE
 GLOBUS_XIO_GSI_SET_SSL_COMPATIBLE
 GLOBUS_XIO_GSI_SET_ANON
 GLOBUS_XIO_GSI_SET_WRAP_MODE
 GLOBUS_XIO_GSI_GET_WRAP_MODE
 GLOBUS_XIO_GSI_SET_BUFFER_SIZE
 GLOBUS_XIO_GSI_GET_BUFFER_SIZE
 GLOBUS_XIO_GSI_SET_PROTECTION_LEVEL
 GLOBUS_XIO_GSI_GET_PROTECTION_LEVEL
 GLOBUS_XIO_GSI_GET_TARGET_NAME
 GLOBUS_XIO_GSI_SET_TARGET_NAME
 GLOBUS_XIO_GSI_GET_CONTEXT
 GLOBUS_XIO_GSI_GET_DELEGATED_CRED
 GLOBUS_XIO_GSI_GET_PEER_NAME
 GLOBUS_XIO_GSI_GET_LOCAL_NAME
 GLOBUS_XIO_GSI_INIT_DELEGATION
 GLOBUS_XIO_GSI_REGISTER_INIT_DELEGATION
 GLOBUS_XIO_GSI_ACCEPT_DELEGATION
 GLOBUS_XIO_GSI_REGISTER_ACCEPT_DELEGATION
 GLOBUS_XIO_GSI_FORCE_SERVER_MODE

Functions

- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_SET_CREDENTIAL, gss_cred_id_t credential)
- globus_result_t [globus_xio_handle_cntl](#)(handle, driver, GLOBUS_XIO_GSI_SET_CREDENTIAL, gss_cred_id_t credential)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_GET_CREDENTIAL, gss_cred_id_t credential)
- globus_result_t [globus_xio_handle_cntl](#)(handle, driver, GLOBUS_XIO_GSI_GET_CREDENTIAL, gss_cred_id_t credential)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_SET_GSSAPI_REQ_FLAGS, OM_uint32 req_ags)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_GET_GSSAPI_REQ_FLAGS, OM_uint32 req_ags)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_SET_PROXY_MODE, [globus_xio_gsi_proxy_mode_t](#) proxy_mode)

- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_GET_PROXY_MODE, [globus_xio_gsi_proxy_mode_t](#) proxy_mode)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_SET_AUTHORIZATION_MODE, [globus_xio_gsi_authorization_mode_t](#) authz_mode)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_GET_AUTHORIZATION_MODE, [globus_xio_gsi_authorization_mode_t](#) authz_mode)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_SET_DELEGATION_MODE, [globus_xio_gsi_delegation_mode_t](#) delegation_mode)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_GET_DELEGATION_MODE, [globus_xio_gsi_delegation_mode_t](#) delegation_mode)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_SET_SSL_COMPATIBLE, globus_bool_t ssl_mode)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_SET_ANON, globus_bool_t anon_mode)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_SET_WRAP_MODE, globus_boolean_t wrap_mode)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_GET_WRAP_MODE, globus_boolean_t wrap_mode)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_SET_BUFFER_SIZE, globus_size_t buffer_size)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_GET_BUFFER_SIZE, globus_size_t buffer_size)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_SET_PROTECTION_LEVEL, [globus_xio_gsi_protection_level_t](#) protection_level)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_GET_PROTECTION_LEVEL, [globus_xio_gsi_protection_level_t](#) protection_level)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_GET_TARGET_NAME, gss_name_t target_name)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_SET_TARGET_NAME, gss_name_t target_name)
- globus_result_t [globus_xio_handle_cntl](#)(handle, driver, GLOBUS_XIO_GSI_GET_CONTEXT, gss_ctx_id_t context)
- globus_result_t [globus_xio_handle_cntl](#)(handle, driver, GLOBUS_XIO_GSI_GET_DELEGATED_CRED, gss_cred_id_t credential)
- globus_result_t [globus_xio_handle_cntl](#)(handle, driver, GLOBUS_XIO_GSI_GET_PEER_NAME, gss_name_t peer_name)
- globus_result_t [globus_xio_handle_cntl](#)(handle, driver, GLOBUS_XIO_GSI_GET_LOCAL_NAME, gss_name_t local_name)
- globus_result_t [globus_xio_handle_cntl](#)(handle, driver, GLOBUS_XIO_GSI_INIT_DELEGATION, gss_cred_id_t credential, gss_OID_set restriction_oids, gss_buffer_set_t restriction_buffers, OM_uint32 time_req)
- globus_result_t [globus_xio_handle_cntl](#)(handle, driver, GLOBUS_XIO_GSI_REGISTER_INIT_DELEGATION, gss_cred_id_t credential, gss_OID_set restriction_oids, gss_buffer_set_t restriction_buffers, OM_uint32 time_req, [globus_xio_gsi_delegation_init_callback_t](#) callback, void callback_arg)
- globus_result_t [globus_xio_handle_cntl](#)(handle, driver, GLOBUS_XIO_GSI_ACCEPT_DELEGATION, gss_cred_id_t credential, gss_OID_set restriction_oids, gss_buffer_set_t restriction_buffers, OM_uint32 time_req)
- globus_result_t [globus_xio_handle_cntl](#)(handle, driver, GLOBUS_XIO_GSI_REGISTER_ACCEPT_DELEGATION, gss_OID_set restriction_oids, gss_buffer_set_t restriction_buffers, OM_uint32 time_req, [globus_xio_gsi_delegation_accept_callback_t](#) callback, void callback_arg)
- globus_result_t [globus_xio_attr_cntl](#)(attr, driver, GLOBUS_XIO_GSI_FORCE_SERVER_MODE, globus_bool_t server_mode)

2.6.1 Detailed Description

GSI driver specific attrs and cntls.

See also:

[globus_xio_attr_cntl\(\)](#)
[globus_xio_handle_cntl\(\)](#)

2.6.2 Enumeration Type Documentation

2.6.2.1 enum [globus_xio_gsi_cmd_t](#)

GSI driver specific cntls.

Enumeration values:

[GLOBUS_XIO_GSI_SET_CREDENTIAL](#) See usage for [globus_xio_attr_cntl](#)/[globus_xio_handle_cntl](#)
[GLOBUS_XIO_GSI_GET_CREDENTIAL](#) See usage for [globus_xio_attr_cntl](#)/[globus_xio_handle_cntl](#)
[GLOBUS_XIO_GSI_SET_GSSAPI_REQ_FLAGS](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_GET_GSSAPI_REQ_FLAGS](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_SET_PROXY_MODE](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_GET_PROXY_MODE](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_SET_AUTHORIZATION_MODE](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_GET_AUTHORIZATION_MODE](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_SET_DELEGATION_MODE](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_GET_DELEGATION_MODE](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_SET_SSL_COMPATIBLE](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_SET_ANON](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_SET_WRAP_MODE](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_GET_WRAP_MODE](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_SET_BUFFER_SIZE](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_GET_BUFFER_SIZE](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_SET_PROTECTION_LEVEL](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_GET_PROTECTION_LEVEL](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_GET_TARGET_NAME](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_SET_TARGET_NAME](#) See usage for [globus_xio_attr_cntl](#)
[GLOBUS_XIO_GSI_GET_CONTEXT](#) See usage for [globus_xio_handle_cntl](#)
[GLOBUS_XIO_GSI_GET_DELEGATED_CRED](#) See usage for [globus_xio_handle_cntl](#)
[GLOBUS_XIO_GSI_GET_PEER_NAME](#) See usage for [globus_xio_handle_cntl](#)
[GLOBUS_XIO_GSI_GET_LOCAL_NAME](#) See usage for [globus_xio_handle_cntl](#)
[GLOBUS_XIO_GSI_INIT_DELEGATION](#) See usage for [globus_xio_handle_cntl](#)
[GLOBUS_XIO_GSI_REGISTER_INIT_DELEGATION](#) See usage for [globus_xio_handle_cntl](#)
[GLOBUS_XIO_GSI_ACCEPT_DELEGATION](#) See usage for [globus_xio_handle_cntl](#)
[GLOBUS_XIO_GSI_REGISTER_ACCEPT_DELEGATION](#) See usage for [globus_xio_handle_cntl](#)
[GLOBUS_XIO_GSI_FORCE_SERVER_MODE](#) See usage for [globus_xio_attr_cntl](#)

2.6.3 Function Documentation

2.6.3.1 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_SET_CREDENTIAL, gss_cred_id_t credential)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Set the credential to be used

Parameters:

credential The credential to set. The credential structure needs to remain valid for the lifetime of any xio data-structure it is used by.

Note:

If this is called with the `handle_cntl`, there must be no outstanding operations on the handle.

2.6.3.2 `globus_result_t globus_xio_handle_cntl (handle, driver, GLOBUS_XIO_GSI_SET_CREDENTIAL, gss_cred_id_t credential)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Set the credential to be used

Parameters:

credential The credential to set. The credential structure needs to remain valid for the lifetime of any xio data-structure it is used by.

Note:

If this is called with the `handle_cntl`, there must be no outstanding operations on the handle.

2.6.3.3 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_GET_CREDENTIAL, gss_cred_id_t credential)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the credential to be used

Parameters:

credential The credential that is currently set. This will only return a credential if a credential was explicitly set prior to this call. It will not return any credential automatically acquired during context initialization.

2.6.3.4 `globus_result_t globus_xio_handle_cntl (handle, driver, GLOBUS_XIO_GSI_GET_CREDENTIAL, gss_cred_id_t credential)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the credential to be used

Parameters:

credential The credential that is currently set. This will only return a credential if a credential was explicitly set prior to this call. It will not return any credential automatically acquired during context initialization.

2.6.3.5 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_SET_GSSAPI_REQ_FLAGS, OM_uint32 req_ags)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Set the GSSAPI req_ags to be used

Parameters:

req_ags The req_ags to set

2.6.3.6 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_GET_GSSAPI_REQ_FLAGS, OM_uint32 req_ags)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the GSSAPI req_ags to be used

Parameters:

req_ags The req_ags currently in effect

2.6.3.7 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_SET_PROXY_MODE, globus_xio_gsi_proxy_mode_t proxy_mode)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Set the proxy mode

Parameters:

proxy_mode The proxy mode to set

Note:

Changing the proxy mode changes the req_ags

2.6.3.8 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_GET_PROXY_MODE, globus_xio_gsi_proxy_mode_t proxy_mode)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the proxy mode

Parameters:

proxy_mode The proxy mode that is currently in effect

Note:

Changing the proxy mode changes the req_ags

2.6.3.9 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_SET_AUTHORIZATION_MODE, globus\_xio\_gsi\_authorization\_mode\_t authz_mode)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Set the authorization mode

Parameters:

`authz_mode` The authorization mode to set

2.6.3.10 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_GET_AUTHORIZATION_MODE, globus\_xio\_gsi\_authorization\_mode\_t authz_mode)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the authorization mode

Parameters:

`authz_mode` The authorization mode that is currently in effect

2.6.3.11 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_SET_DELEGATION_MODE, globus\_xio\_gsi\_delegation\_mode\_t delegation_mode)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Set the delegation mode

Parameters:

`delegation_mode` The delegation mode to use

Note:

Changing the delegation mode changes the `req_ags`

2.6.3.12 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_GET_DELEGATION_MODE, globus\_xio\_gsi\_delegation\_mode\_t delegation_mode)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the delegation mode

Parameters:

`delegation_mode` The delegation mode currently in effect

2.6.3.13 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_SET_SSL_COMPATIBLE, globus_bool_t ssl_mode)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Make the on the wire protocol SSL compatible.

This implies no wrapping of security tokens and no delegation

Parameters:

ssl_mode The ssl compatibility mode to use

Note:

Changing the ssl compatibility mode changes the req_ags

2.6.3.14 globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_SET_ANON, globus_bool_t anon_mode)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Do anonymous authentication

Parameters:

anon_mode The ssl compatibility mode to use

Note:

Changing the ssl compatibility mode changes the req_ags and the wrapping mode

2.6.3.15 globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_SET_WRAP_MODE, globus_boolean_t wrap_mode)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Set the wrapping mode

This mode determines whether tokens will be wrapped with a Globus IO style header or not.

Parameters:

wrap_mode The wrapping mode to use

2.6.3.16 globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_GET_WRAP_MODE, globus_boolean_t wrap_mode)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the wrapping mode

This mode determines whether tokens will be wrapped with a Globus IO style header or not.

Parameters:

wrap_mode The wrapping mode currently in use.

2.6.3.17 globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_SET_BUFFER_SIZE, globus_size_t buffer_size)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Set the read buffer size

The read buffer is used for buffering wrapped data, is initialized with a default size of 128K and scaled dynamically to always be able to fit whole tokens.

Parameters:

buffer_size The size of the read buffer

2.6.3.18 globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_GET_BUFFER_SIZE, globus_size_t buffer_size)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the read buffer size

The read buffer is used for buffering wrapped data, is initialized with a default size of 128K and scaled dynamically to always be able to fit whole tokens.

Parameters:

buffer_size The size of the read buffer

2.6.3.19 globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_SET_PROTECTION_LEVEL, globus_xio_gsi_protection_level_t protection_level)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Set the protection level

Parameters:

protection_level The protection level to set

Note:

Changing the proxy mode changes the req_agt

2.6.3.20 globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_GET_PROTECTION_LEVEL, globus_xio_gsi_protection_level_t protection_level)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the protection level

Parameters:

protection_level The current protection level

2.6.3.21 globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_GET_TARGET_NAME, gss_name_t target_name)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Set the expected peer name

Parameters:

target_name The expected peer name

2.6.3.22 `globus_result_t globus_xio_attr_cntl (attr, driver, GLOBUS_XIO_GSI_SET_TARGET_NAME, gss_name_target_name)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the expected peer name

Parameters:

`target_name` The expected peer name

2.6.3.23 `globus_result_t globus_xio_handle_cntl (handle, driver, GLOBUS_XIO_GSI_GET_CONTEXT, gss_ctx_id_t context)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the GSS context

Parameters:

`context` The GSS context

2.6.3.24 `globus_result_t globus_xio_handle_cntl (handle, driver, GLOBUS_XIO_GSI_GET_DELEGATED_CRED, gss_cred_id_t credential)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the delegated credential

Parameters:

`credential` The delegated credential

2.6.3.25 `globus_result_t globus_xio_handle_cntl (handle, driver, GLOBUS_XIO_GSI_GET_PEER_NAME, gss_name_t peer_name)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the name of the peer

Parameters:

`peer_name` The GSS name of the peer.

2.6.3.26 `globus_result_t globus_xio_handle_cntl (handle, driver, GLOBUS_XIO_GSI_GET_LOCAL_NAME, gss_name_t local_name)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Get the GSS name associated with the local credentials

Parameters:

`local_name` The GSS name of the local credentials

2.6.3.27 `globus_result_t globus_xio_handle_cntl (handle, driver, GLOBUS_XIO_GSI_INIT_DELEGATION, gss_cred_id_t credential, gss_OID_set restriction_oids, gss_buffer_set_t restriction_buffers, OM_uint32 time_req)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Initialize delegation-at-any-time process

Parameters:

`credential` The GSS credential to delegate
`restriction_oids` The OIDS for X.509 extensions to embed in the delegated credential
`restriction_buffers` The corresponding bodies for the X.509 extensions
`time_req` The lifetime of the delegated credential

2.6.3.28 `globus_result_t globus_xio_handle_cntl (handle, driver, GLOBUS_XIO_GSI_REGISTER_INIT_DELEGATION, gss_cred_id_t credential, gss_OID_set restriction_oids, gss_buffer_set_t restriction_buffers, OM_uint32 time_req, globus\_xio\_gsi\_delegation\_init\_callback\_t callback, void * callback_arg)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Initialize non-blocking delegation-at-any-time process

Parameters:

`credential` The GSS credential to delegate
`restriction_oids` The OIDS for X.509 extensions to embed in the delegated credential
`restriction_buffers` The corresponding bodies for the X.509 extensions
`time_req` The lifetime of the delegated credential
`callback` The callback to call when the operation completes
`callback_arg` The arguments to pass to the callback

2.6.3.29 `globus_result_t globus_xio_handle_cntl (handle, driver, GLOBUS_XIO_GSI_ACCEPT_DELEGATION, gss_cred_id_t credential, gss_OID_set restriction_oids, gss_buffer_set_t restriction_buffers, OM_uint32 time_req)`

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Accept delegation-at-any-time process

Parameters:

`credential` The delegated GSS credential
`restriction_oids` The OIDS for X.509 extensions to embed in the delegated credential
`restriction_buffers` The corresponding bodies for the X.509 extensions
`time_req` The requested lifetime of the delegated credential

2.6.3.30 `globus_result_t globus_xio_handle_cntl` (`handle`, `driver`, `GLOBUS_XIO_GSI_REGISTER_ACCEPT_DELEGATION`, `gss_OID_set restriction_oids`, `gss_buffer_set_t restriction_buffers`, `OM_uint32 time_req`, `globus_xio_gsi_delegation_accept_callback`, `void callback_arg`)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Accept non-blocking delegation-at-any-time process

Parameters:

- `restriction_oids` The OIDS for X.509 extensions to embed in the delegated credential
- `restriction_buffers` The corresponding bodies for the X.509 extensions
- `time_req` The lifetime of the delegated credential
- `callback` The callback to call when the operation completes
- `callback_arg` The arguments to pass to the callback

2.6.3.31 `globus_result_t globus_xio_attr_cntl` (`attr`, `driver`, `GLOBUS_XIO_GSI_FORCE_SERVER_MODE`, `globus_bool_t server_mode`)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Force the server mode setting.

This explicitly sets the directionality of context establishment and delegation.

Parameters:

- `server_mode` The server mode.

2.7 Types

Typedefs

- typedef void([globus_xio_gsi_delegation_init_callback](#))(`globus_result_t result`, `void user_arg`)
- typedef void([globus_xio_gsi_delegation_accept_callback](#))(`globus_result_t result`, `gss_cred_id_t delegated_cred`, `OM_uint32 time_rec`, `void user_arg`)

Enumerations

- enum [globus_xio_gsi_protection_level_t](#)
 - `GLOBUS_XIO_GSI_PROTECTION_LEVEL_NONE`
 - `GLOBUS_XIO_GSI_PROTECTION_LEVEL_INTEGRITY`
 - `GLOBUS_XIO_GSI_PROTECTION_LEVEL_PRIVACY`
- enum [globus_xio_gsi_delegation_mode_t](#)
 - `GLOBUS_XIO_GSI_DELEGATION_MODE_NONE`
 - `GLOBUS_XIO_GSI_DELEGATION_MODE_LIMITED`
 - `GLOBUS_XIO_GSI_DELEGATION_MODE_FULL`

- enum [globus_xio_gsi_proxy_mode_t](#)
 GLOBUS_XIO_GSI_PROXY_MODE_FULL
 GLOBUS_XIO_GSI_PROXY_MODE_LIMITED
 GLOBUS_XIO_GSI_PROXY_MODE_MANY}
- enum [globus_xio_gsi_authorization_mode_t](#)
 GLOBUS_XIO_GSI_NO_AUTHORIZATION
 GLOBUS_XIO_GSI_SELF_AUTHORIZATION
 GLOBUS_XIO_GSI_IDENTITY_AUTHORIZATION
 GLOBUS_XIO_GSI_HOST_AUTHORIZATION}

2.7.1 Typedef Documentation

2.7.1.1 typedef void([globus_xio_gsi_delegation_init_callback](#))(globus_result_t result, void user_arg)

Globus XIO GSI init delegation callback.

2.7.1.2 typedef void([globus_xio_gsi_delegation_accept_callback](#))(globus_result_t result, gss_cred_id_t delegated_cred, OM_uint32 time_rec, void user_arg)

Globus XIO GSI init delegation callback.

2.7.2 Enumeration Type Documentation

2.7.2.1 enum [globus_xio_gsi_protection_level_t](#)

Globus XIO GSI protection levels.

Enumeration values:

GLOBUS_XIO_GSI_PROTECTION_LEVEL_NONE No security.

GLOBUS_XIO_GSI_PROTECTION_LEVEL_INTEGRITY Messages are signed.

GLOBUS_XIO_GSI_PROTECTION_LEVEL_PRIVACY Messages are signed and encrypted.

2.7.2.2 enum [globus_xio_gsi_delegation_mode_t](#)

Globus XIO GSI delegation modes.

Enumeration values:

GLOBUS_XIO_GSI_DELEGATION_MODE_NONE No delegation.

GLOBUS_XIO_GSI_DELEGATION_MODE_LIMITED Delegate a limited proxy.

GLOBUS_XIO_GSI_DELEGATION_MODE_FULL Delegate a full proxy.

2.7.2.3 enum [globus_xio_gsi_proxy_mode_t](#)

Globus XIO GSI proxy modes.

Enumeration values:

GLOBUS_XIO_GSI_PROXY_MODE_FULL Accept only full proxies.

GLOBAL_XIO_GSI_PROXY_MODE_LIMITED Accept full proxies and limited proxies if they are the only limited proxy in the cert chain.

GLOBAL_XIO_GSI_PROXY_MODE_MANY Accept both full and limited proxies unconditionally.

2.7.2.4 enumglobus_xio_gsi_authorization_mode_t

Globus XIO GSI authorization modes.

Enumeration values:

GLOBAL_XIO_GSI_NO_AUTHORIZATION Do not perform any authorization.

This will cause a error when used in conjunction with delegation on the init/client side.

GLOBAL_XIO_GSI_SELF_AUTHORIZATION Authorize the peer if the peer has the same identity as ourselves.

GLOBAL_XIO_GSI_IDENTITY_AUTHORIZATION Authorize the peer if the peer identity matches the identity set in the target name.

GLOBAL_XIO_GSI_HOST_AUTHORIZATION Authorize the peer if the identity of the peer matches the identity of the peer hostname.

2.8 Error Types

Enumerations

- enumglobus_xio_gsi_error_t
 - GLOBAL_XIO_GSI_ERROR_INVALID_PROTECTION_LEVEL
 - GLOBAL_XIO_GSI_ERROR_WRAP_GSSAPI
 - GLOBAL_XIO_GSI_ERROR_EMPTY_TARGET_NAME
 - GLOBAL_XIO_GSI_ERROR_EMPTY_HOST_NAME
 - GLOBAL_XIO_GSI_AUTHORIZATION_FAILED
 - GLOBAL_XIO_GSI_ERROR_TOKEN_TOO_BIG

2.8.1 Detailed Description

The GSI driver uses mostly GSSAPI calls, so it generally just wraps the underlying GSSAPI errors or uses generic xio errors.

See also:

```
globus_xio_driver_error_match()
globus_error_gssapi_match()
globus_error_match_openssl_error()
```

2.8.2 Enumeration Type Documentation

2.8.2.1 enumglobus_xio_gsi_error_t

GSI driver specific error types.

Enumeration values:

GLOBAL_XIO_GSI_ERROR_INVALID_PROTECTION_LEVEL Indicates that the established context does not meet the required protection level.

GLBUS_XIO_GSI_ERROR_WRAP_GSSAPWraps a GSSAPI error.

GLBUS_XIO_GSI_ERROR_EMPTY_TARGET_NAMEIndicates that GLBUS_XIO_GSI_IDENTITY_-AUTHORIZATION is set but that the target name is empty.

GLBUS_XIO_GSI_ERROR_EMPTY_HOST_NAMEIndicates that GLBUS_XIO_GSI_HOST_-AUTHORIZATION is set but that no host name is available.

GLBUS_XIO_GSI_AUTHORIZATION_FAILED Indicates that the peer is not authorized.

GLBUS_XIO_GSI_ERROR_TOKEN_TOO_BIGIndicates the the token being read is too big.

Usually happens when someone tries to establish a non secure session with a endpoint that expects security

Index

Attributes and Cntls[2](#)

Env Variables[2](#)

Error Types[15](#)

Globus XIO GSI Driver[1](#)

globus_xio_attr_cntl

gsi_driver_cntls[6–10, 13](#)

GLOBUS_XIO_GSI_ACCEPT_DELEGATION

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_AUTHORIZATION_FAILED

gsi_driver_errors[16](#)

globus_xio_gsi_authorization_mode_t

gsi_driver_types[15](#)

globus_xio_gsi_cmd_t

gsi_driver_cntls[5](#)

globus_xio_gsi_delegation_accept_callback_t

gsi_driver_types[14](#)

globus_xio_gsi_delegation_init_callback_t

gsi_driver_types[14](#)

GLOBUS_XIO_GSI_DELEGATION_MODE_FULL

gsi_driver_types[14](#)

GLOBUS_XIO_GSI_DELEGATION_MODE_-
LIMITED

gsi_driver_types[14](#)

GLOBUS_XIO_GSI_DELEGATION_MODE_-
NONE

gsi_driver_types[14](#)

globus_xio_gsi_delegation_mode_t

gsi_driver_types[14](#)

GLOBUS_XIO_GSI_ERROR_EMPTY_HOST_-
NAME

gsi_driver_errors[16](#)

GLOBUS_XIO_GSI_ERROR_EMPTY_TARGET_-
NAME

gsi_driver_errors[16](#)

GLOBUS_XIO_GSI_ERROR_INVALID_-
PROTECTION_LEVEL

gsi_driver_errors[15](#)

globus_xio_gsi_error_t

gsi_driver_errors[15](#)

GLOBUS_XIO_GSI_ERROR_TOKEN_TOO_BIG

gsi_driver_errors[16](#)

GLOBUS_XIO_GSI_ERROR_WRAP_GSSAPI

gsi_driver_errors[15](#)

GLOBUS_XIO_GSI_FORCE_SERVER_MODE

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_AUTHORIZATION_-
MODE

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_BUFFER_SIZE

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_CONTEXT

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_CREDENTIAL

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_DELEGATED_CRED

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_DELEGATION_MODE

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_GSSAPI_REQ_FLAGS

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_LOCAL_NAME

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_PEER_NAME

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_PROTECTION_LEVEL

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_PROXY_MODE

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_TARGET_NAME

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_GET_WRAP_MODE

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_HOST_AUTHORIZATION

gsi_driver_types[15](#)

GLOBUS_XIO_GSI_IDENTITY_-
AUTHORIZATION

gsi_driver_types[15](#)

GLOBUS_XIO_GSI_INIT_DELEGATION

gsi_driver_cntls[5](#)

GLOBUS_XIO_GSI_NO_AUTHORIZATION

gsi_driver_types[15](#)

GLOBUS_XIO_GSI_PROTECTION_LEVEL_-
INTEGRITY

gsi_driver_types[14](#)

GLOBUS_XIO_GSI_PROTECTION_LEVEL_-
NONE

gsi_driver_types[14](#)

GLOBUS_XIO_GSI_PROTECTION_LEVEL_-
PRIVACY

gsi_driver_types[14](#)

globus_xio_gsi_protection_level_t

gsi_driver_types[14](#)

GLOBUS_XIO_GSI_PROXY_MODE_FULL

gsi_driver_types[14](#)

GLOBUS_XIO_GSI_PROXY_MODE_LIMITED

gsi_driver_types[14](#)

GLOBUS_XIO_GSI_PROXY_MODE_MANY

gsi_driver_types[15](#)

globus_xio_gsi_proxy_mode_t

- gsi_driver_types [14](#)
- GLOBUS_XIO_GSI_REGISTER_ACCEPT_-
DELEGATION
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_REGISTER_INIT_-
DELEGATION
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_SELF_AUTHORIZATION
- gsi_driver_types [15](#)
- GLOBUS_XIO_GSI_SET_ANON
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_SET_AUTHORIZATION_-
MODE
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_SET_BUFFER_SIZE
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_SET_CREDENTIAL
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_SET_DELEGATION_MODE
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_SET_GSSAPI_REQ_FLAGS
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_SET_PROTECTION_LEVEL
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_SET_PROXY_MODE
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_SET_SSL_COMPATIBLE
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_SET_TARGET_NAME
- gsi_driver_cntls [5](#)
- GLOBUS_XIO_GSI_SET_WRAP_MODE
- gsi_driver_cntls [5](#)
- globus_xio_handle_cntl
- gsi_driver_cntls [6, 11, 12](#)
- gsi_driver_cntls
 - GLOBUS_XIO_GSI_ACCEPT_DELEGATION,
[5](#)
 - GLOBUS_XIO_GSI_FORCE_SERVER_-
MODE, [5](#)
 - GLOBUS_XIO_GSI_GET_-
AUTHORIZATION_MODE, [5](#)
 - GLOBUS_XIO_GSI_GET_BUFFER_SIZE, [5](#)
 - GLOBUS_XIO_GSI_GET_CONTEXT [5](#)
 - GLOBUS_XIO_GSI_GET_CREDENTIAL [5](#)
 - GLOBUS_XIO_GSI_GET_DELEGATED_-
CRED, [5](#)
 - GLOBUS_XIO_GSI_GET_DELEGATION_-
MODE, [5](#)
 - GLOBUS_XIO_GSI_GET_GSSAPI_REQ_-
FLAGS, [5](#)
 - GLOBUS_XIO_GSI_GET_LOCAL_NAME [5](#)
 - GLOBUS_XIO_GSI_GET_PEER_NAME [5](#)
 - GLOBUS_XIO_GSI_GET_PROTECTION_-
LEVEL, [5](#)
 - GLOBUS_XIO_GSI_GET_PROXY_MODE [5](#)
 - GLOBUS_XIO_GSI_GET_SSL_-
COMPATIBLE, [5](#)
 - GLOBUS_XIO_GSI_GET_TARGET_NAME [5](#)
 - GLOBUS_XIO_GSI_GET_WRAP_MODE [5](#)
- gsi_driver_cntls
 - globus_xio_attr_cntl [6-10, 13](#)
 - globus_xio_gsi_cmd [6](#)
 - globus_xio_handle_cntl [6, 11, 12](#)
- gsi_driver_errors
 - GLOBUS_XIO_GSI_AUTHORIZATION_-
FAILED, [16](#)
 - GLOBUS_XIO_GSI_ERROR_EMPTY_-
HOST_NAME, [16](#)
 - GLOBUS_XIO_GSI_ERROR_EMPTY_-
TARGET_NAME, [16](#)
 - GLOBUS_XIO_GSI_ERROR_INVALID_-
PROTECTION_LEVEL, [15](#)
 - GLOBUS_XIO_GSI_ERROR_TOKEN_TOO_-
BIG, [16](#)
 - GLOBUS_XIO_GSI_ERROR_WRAP_-
GSSAPI, [15](#)
- gsi_driver_errors
 - globus_xio_gsi_error_ [15](#)
- gsi_driver_types
 - GLOBUS_XIO_GSI_DELEGATION_MODE_-
FULL, [14](#)
 - GLOBUS_XIO_GSI_DELEGATION_MODE_-
LIMITED, [14](#)
 - GLOBUS_XIO_GSI_DELEGATION_MODE_-
NONE, [14](#)
 - GLOBUS_XIO_GSI_HOST_-
AUTHORIZATION, [15](#)

GLOBUS_XIO_GSI_IDENTITY_-
 AUTHORIZATION, [15](#)
 GLOBUS_XIO_GSI_NO_AUTHORIZATION,
 [15](#)
 GLOBUS_XIO_GSI_PROTECTION_LEVEL_-
 INTEGRITY, [14](#)
 GLOBUS_XIO_GSI_PROTECTION_LEVEL_-
 NONE, [14](#)
 GLOBUS_XIO_GSI_PROTECTION_LEVEL_-
 PRIVACY, [14](#)
 GLOBUS_XIO_GSI_PROXY_MODE_FULL,
 [14](#)
 GLOBUS_XIO_GSI_PROXY_MODE_-
 LIMITED, [14](#)
 GLOBUS_XIO_GSI_PROXY_MODE_MANY,
 [15](#)
 GLOBUS_XIO_GSI_SELF_-
 AUTHORIZATION, [15](#)
gsi_driver_types
 globus_xio_gsi_authorization_mode [15](#)
 globus_xio_gsi_delegation_accept_callback_t,
 [14](#)
 globus_xio_gsi_delegation_init_callback [14](#)
 globus_xio_gsi_delegation_mode [14](#)
 globus_xio_gsi_protection_level [14](#)
 globus_xio_gsi_proxy_mode [14](#)

Opening/Closing [2](#)

Reading/Writing [2](#)

Server [2](#)

Types, [13](#)