

# VOMS CC API

## 1.5.0

Generated by Doxygen 1.5.6

Tue Oct 20 13:45:18 2009



# Contents

<b>1</b>	<b>Data Structure Index</b>	<b>1</b>
1.1	Data Structures . . . . .	1
<b>2</b>	<b>File Index</b>	<b>3</b>
2.1	File List . . . . .	3
<b>3</b>	<b>Data Structure Documentation</b>	<b>5</b>
3.1	attribute Struct Reference . . . . .	5
3.1.1	Detailed Description . . . . .	5
3.1.2	Field Documentation . . . . .	5
3.1.2.1	name . . . . .	5
3.1.2.2	qualifier . . . . .	5
3.1.2.3	value . . . . .	5
3.2	attributelist Struct Reference . . . . .	7
3.2.1	Detailed Description . . . . .	7
3.2.2	Field Documentation . . . . .	7
3.2.2.1	grantor . . . . .	7
3.2.2.2	attributes . . . . .	7
3.3	contactdata Struct Reference . . . . .	8
3.3.1	Detailed Description . . . . .	8
3.3.2	Field Documentation . . . . .	8
3.3.2.1	nick . . . . .	8
3.3.2.2	host . . . . .	8
3.3.2.3	contact . . . . .	8
3.3.2.4	vo . . . . .	8
3.3.2.5	port . . . . .	8
3.3.2.6	version . . . . .	9
3.4	data Struct Reference . . . . .	10
3.4.1	Detailed Description . . . . .	10

3.4.2	Field Documentation . . . . .	10
3.4.2.1	group . . . . .	10
3.4.2.2	role . . . . .	10
3.4.2.3	cap . . . . .	10
3.5	voms Struct Reference . . . . .	11
3.5.1	Detailed Description . . . . .	11
3.5.2	Constructor & Destructor Documentation . . . . .	12
3.5.2.1	voms . . . . .	12
3.5.2.2	voms . . . . .	12
3.5.2.3	~voms . . . . .	12
3.5.3	Member Function Documentation . . . . .	12
3.5.3.1	operator= . . . . .	12
3.5.3.2	GetAC . . . . .	12
3.5.3.3	GetAttributes . . . . .	12
3.5.3.4	GetTargets . . . . .	12
3.5.4	Friends And Related Function Documentation . . . . .	12
3.5.4.1	vomsdata . . . . .	12
3.5.4.2	TranslateVOMS . . . . .	12
3.5.5	Field Documentation . . . . .	12
3.5.5.1	version . . . . .	12
3.5.5.2	siglen . . . . .	12
3.5.5.3	signature . . . . .	12
3.5.5.4	user . . . . .	13
3.5.5.5	userca . . . . .	13
3.5.5.6	server . . . . .	13
3.5.5.7	serverca . . . . .	13
3.5.5.8	voname . . . . .	13
3.5.5.9	uri . . . . .	13
3.5.5.10	date1 . . . . .	13
3.5.5.11	date2 . . . . .	13
3.5.5.12	type . . . . .	13
3.5.5.13	std . . . . .	14
3.5.5.14	custom . . . . .	14
3.5.5.15	fqn . . . . .	14
3.5.5.16	serial . . . . .	14
3.6	vomsdata Struct Reference . . . . .	15

3.6.1	Detailed Description	16
3.6.2	Constructor & Destructor Documentation	16
3.6.2.1	vomsdata	16
3.6.2.2	~vomsdata	16
3.6.2.3	vomsdata	16
3.6.3	Member Function Documentation	16
3.6.3.1	LoadSystemContacts	16
3.6.3.2	LoadUserContacts	16
3.6.3.3	FindByAlias	17
3.6.3.4	FindByVO	17
3.6.3.5	Order	17
3.6.3.6	ResetOrder	17
3.6.3.7	AddTarget	17
3.6.3.8	ListTargets	18
3.6.3.9	ResetTargets	18
3.6.3.10	ServerErrors	18
3.6.3.11	Retrieve	18
3.6.3.12	Contact	18
3.6.3.13	Contact	19
3.6.3.14	ContactRaw	19
3.6.3.15	ContactRaw	19
3.6.3.16	SetVerificationType	20
3.6.3.17	SetLifetime	20
3.6.3.18	Import	20
3.6.3.19	Export	20
3.6.3.20	DefaultData	20
3.6.3.21	ErrorMessage	21
3.6.3.22	RetrieveFromCtx	21
3.6.3.23	RetrieveFromCred	21
3.6.3.24	Retrieve	21
3.6.3.25	RetrieveFromProxy	21
3.6.3.26	Retrieve	22
3.6.3.27	SetRetryCount	22
3.6.3.28	SetVerificationTime	22
3.6.3.29	LoadCredentials	22
3.6.4	Field Documentation	22

3.6.4.1	<a href="#">error</a>	22
3.6.4.2	<a href="#">data</a>	22
3.6.4.3	<a href="#">workvo</a>	22
3.6.4.4	<a href="#">extra_data</a>	23
<b>4</b>	<b>File Documentation</b>	<b>25</b>
4.1	<a href="#">voms_api.h File Reference</a>	25
4.1.1	<a href="#">Typedef Documentation</a>	26
4.1.1.1	<a href="#">check_sig</a>	26
4.1.1.2	<a href="#">gss_cred_id_t</a>	26
4.1.1.3	<a href="#">gss_ctx_id_t</a>	26
4.1.2	<a href="#">Enumeration Type Documentation</a>	26
4.1.2.1	<a href="#">data_type</a>	26
4.1.2.2	<a href="#">recurse_type</a>	27
4.1.2.3	<a href="#">verify_type</a>	27
4.1.2.4	<a href="#">verror_type</a>	27
4.1.3	<a href="#">Function Documentation</a>	28
4.1.3.1	<a href="#">getMajorVersionNumber</a>	28
4.1.3.2	<a href="#">getMinorVersionNumber</a>	28
4.1.3.3	<a href="#">getPatchVersionNumber</a>	28

# Chapter 1

# Data Structure Index

## 1.1 Data Structures

Here are the data structures with brief descriptions:

<a href="#">attribute</a>	5
<a href="#">attributelist</a>	7
<a href="#">contactdata</a>	8
<a href="#">data</a> (User's characteristics: can be repeated )	10
<a href="#">voms</a>	11
<a href="#">vomsdata</a>	15



# Chapter 2

## File Index

### 2.1 File List

Here is a list of all files with brief descriptions:

<a href="#">voms_api.h</a>	25
----------------------------	----



## Chapter 3

# Data Structure Documentation

### 3.1 attribute Struct Reference

```
#include <voms_api.h>
```

#### Data Fields

- std::string [name](#)
- std::string [qualifier](#)
- std::string [value](#)

#### 3.1.1 Detailed Description

Definition at line 46 of file voms\_api.h.

#### 3.1.2 Field Documentation

##### 3.1.2.1 std::string attribute::name

attribute's group

Definition at line 47 of file voms\_api.h.

##### 3.1.2.2 std::string attribute::qualifier

attribute's qualifier

Definition at line 48 of file voms\_api.h.

##### 3.1.2.3 std::string attribute::value

attribute's value

Definition at line 49 of file voms\_api.h.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)

## 3.2 attributelist Struct Reference

```
#include <voms_api.h>
```

### Data Fields

- std::string [grantor](#)
- std::vector< [attribute](#) > [attributes](#)

### 3.2.1 Detailed Description

Definition at line 52 of file voms\_api.h.

### 3.2.2 Field Documentation

#### 3.2.2.1 std::string attributelist::grantor

Who granted these attributes.

Definition at line 53 of file voms\_api.h.

#### 3.2.2.2 std::vector<attribute> attributelist::attributes

The attributes themselves.

Definition at line 54 of file voms\_api.h.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)

## 3.3 contactdata Struct Reference

```
#include <voms_api.h>
```

### Data Fields

- std::string [nick](#)
- std::string [host](#)
- std::string [contact](#)
- std::string [vo](#)
- int [port](#)
- int [version](#)

### 3.3.1 Detailed Description

Definition at line 66 of file voms\_api.h.

### 3.3.2 Field Documentation

#### 3.3.2.1 std::string contactdata::nick

< You must never allocate directly this structure. Its sizeof() is subject to change without notice. The only supported way to obtain it is via the FindBy\* functions. The alias of the server

Definition at line 70 of file voms\_api.h.

#### 3.3.2.2 std::string contactdata::host

The hostname of the server

Definition at line 71 of file voms\_api.h.

#### 3.3.2.3 std::string contactdata::contact

The subject of the server's certificate

Definition at line 72 of file voms\_api.h.

#### 3.3.2.4 std::string contactdata::vo

The VO served by this server

Definition at line 73 of file voms\_api.h.

#### 3.3.2.5 int contactdata::port

The port on which the server is listening

Definition at line 74 of file voms\_api.h.

#### 3.3.2.6 int contactdata::version

The version of globus under which the server is running

Definition at line 76 of file voms\_api.h.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)

## 3.4 data Struct Reference

User's characteristics: can be repeated.

```
#include <voms_api.h>
```

### Data Fields

- `std::string` [group](#)
- `std::string` [role](#)
- `std::string` [cap](#)

### 3.4.1 Detailed Description

User's characteristics: can be repeated.

Definition at line 38 of file `voms_api.h`.

### 3.4.2 Field Documentation

#### 3.4.2.1 `std::string data::group`

user's group

Definition at line 39 of file `voms_api.h`.

#### 3.4.2.2 `std::string data::role`

user's role

Definition at line 40 of file `voms_api.h`.

#### 3.4.2.3 `std::string data::cap`

user's capability

Definition at line 41 of file `voms_api.h`.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)

## 3.5 voms Struct Reference

```
#include <voms_api.h>
```

### Public Member Functions

- [voms](#) (const [voms](#) &)
- [voms](#) ()
- [voms](#) & [operator=](#) (const [voms](#) &)
- [~voms](#) ()
- AC \* [GetAC](#) ()
- std::vector< [attributelist](#) > & [GetAttributes](#) ()
- std::vector< std::string > [GetTargets](#) ()

### Data Fields

- int [version](#)
- int [siglen](#)
- std::string [signature](#)
- std::string [user](#)
- std::string [userca](#)
- std::string [server](#)
- std::string [serverca](#)
- std::string [voname](#)
- std::string [uri](#)
- std::string [date1](#)
- std::string [date2](#)
- [data\\_type](#) type
- std::vector< [data](#) > [std](#)
- std::string [custom](#)
- std::vector< std::string > [fqan](#)
- std::string [serial](#)

### Friends

- class [vomsdata](#)
- int [TranslateVOMS](#) (struct vomsdatar \*vd, std::vector< [voms](#) > &v, int \*error)

#### 3.5.1 Detailed Description

Definition at line 79 of file voms\_api.h.

## 3.5.2 Constructor & Destructor Documentation

**3.5.2.1** `voms::voms (const voms &)`

**3.5.2.2** `voms::voms ()`

**3.5.2.3** `voms::~~voms ()`

## 3.5.3 Member Function Documentation

**3.5.3.1** `voms& voms::operator= (const voms &)`

**3.5.3.2** `AC* voms::GetAC ()`

**3.5.3.3** `std::vector<attributelist>& voms::GetAttributes ()`

Generic attributes

**3.5.3.4** `std::vector<std::string> voms::GetTargets ()`

## 3.5.4 Friends And Related Function Documentation

**3.5.4.1** `friend class vomsdata` [*friend*]

Definition at line 80 of file voms\_api.h.

**3.5.4.2** `int TranslateVOMS (struct vomsdatar * vd, std::vector< voms > & v, int * error)`  
[*friend*]

## 3.5.5 Field Documentation

**3.5.5.1** `int voms::version`

0 means [data](#) didn't originate from an AC

Definition at line 81 of file voms\_api.h.

**3.5.5.2** `int voms::siglen`

The length of the VOMS server signature

Definition at line 82 of file voms\_api.h.

**3.5.5.3** `std::string voms::signature`

The VOMS server signature

Definition at line 83 of file voms\_api.h.

**3.5.5.4 std::string voms::user**

The user's DN, as from his certificate

Definition at line 84 of file voms\_api.h.

**3.5.5.5 std::string voms::userca**

The CA which signed the user's certificate

Definition at line 85 of file voms\_api.h.

**3.5.5.6 std::string voms::server**

The VOMS server DN, as from its certificate

Definition at line 86 of file voms\_api.h.

**3.5.5.7 std::string voms::serverca**

The CA which signed the VOMS certificate

Definition at line 87 of file voms\_api.h.

**3.5.5.8 std::string voms::voname**

The name of the VO to which the VOMS belongs

Definition at line 88 of file voms\_api.h.

**3.5.5.9 std::string voms::uri**

The URI of the VOMS server

Definition at line 89 of file voms\_api.h.

**3.5.5.10 std::string voms::date1**

Beginning of validity of the user info

Definition at line 90 of file voms\_api.h.

**3.5.5.11 std::string voms::date2**

End of validity of the user info

Definition at line 91 of file voms\_api.h.

**3.5.5.12 data\_type voms::type**

The type of [data](#) returned

Definition at line 92 of file voms\_api.h.

**3.5.5.13 `std::vector<data> voms::std`**

User's characteristics

Definition at line 93 of file voms\_api.h.

**3.5.5.14 `std::string voms::custom`**

The [data](#) returned by an S command

Definition at line 94 of file voms\_api.h.

**3.5.5.15 `std::vector<std::string> voms::fqan`**

Keeps the [data](#) in the compact format

Definition at line 96 of file voms\_api.h.

**3.5.5.16 `std::string voms::serial`**

Serial number. "0" if coming from non-ac

Definition at line 97 of file voms\_api.h.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)

## 3.6 vomsdata Struct Reference

```
#include <voms_api.h>
```

### Public Member Functions

- [vomsdata](#) (std::string voms\_dir="", std::string cert\_dir="")
- bool [LoadSystemContacts](#) (std::string dir="")
- bool [LoadUserContacts](#) (std::string dir="")
- std::vector< [contactdata](#) > [FindByAlias](#) (std::string alias)
- std::vector< [contactdata](#) > [FindByVO](#) (std::string vo)
- void [Order](#) (std::string att)
- void [ResetOrder](#) (void)
- void [AddTarget](#) (std::string target)
- std::vector< std::string > [ListTargets](#) (void)
- void [ResetTargets](#) (void)
- std::string [ServerErrors](#) (void)
- bool [Retrieve](#) (X509 \*cert, STACK\_OF(X509)\*chain, [recurse\\_type](#) how=RECURSE\_CHAIN)
- bool [Contact](#) (std::string hostname, int port, std::string servsubject, std::string command)
- bool [Contact](#) (std::string hostname, int port, std::string servsubject, std::string command, int timeout)
- bool [ContactRaw](#) (std::string hostname, int port, std::string servsubject, std::string command, std::string &raw, int &version)
- bool [ContactRaw](#) (std::string hostname, int port, std::string servsubject, std::string command, std::string &raw, int &version, int timeout)
- void [SetVerificationType](#) ([verify\\_type](#) how)
- void [SetLifetime](#) (int lifetime)
- bool [Import](#) (std::string buffer)
- bool [Export](#) (std::string &data)
- bool [DefaultData](#) (voms &)
- std::string [ErrorMessage](#) (void)
- bool [RetrieveFromCtx](#) ([gss\\_ctx\\_id\\_t](#) context, [recurse\\_type](#) how)
- bool [RetrieveFromCred](#) ([gss\\_cred\\_id\\_t](#) credential, [recurse\\_type](#) how)
- bool [Retrieve](#) (X509\_EXTENSION \*ext)
- bool [RetrieveFromProxy](#) ([recurse\\_type](#) how)
- bool [Retrieve](#) (FILE \*file, [recurse\\_type](#) how)
- [~vomsdata](#) ()
- [vomsdata](#) (const [vomsdata](#) &)
- void [SetRetryCount](#) (int retryCount)
- void [SetVerificationTime](#) (time\_t)
- bool [LoadCredentials](#) (X509 \*, EVP\_PKEY \*, STACK\_OF(X509)\*)

### Data Fields

- [verror\\_type](#) error
- std::vector< [voms](#) > data
- std::string workvo
- std::string extra\_data

## Data Structures

- class **Initializer**

### 3.6.1 Detailed Description

Definition at line 170 of file voms\_api.h.

### 3.6.2 Constructor & Destructor Documentation

#### 3.6.2.1 vomsdata::vomsdata (std::string voms\_dir = "", std::string cert\_dir = "")

##### Parameters:

*voms\_dir* The directory which contains the certificate of the VOMS server

*cert\_dir* The directory which contains the certificate of the CA

If voms\_dir is empty, the value of the environment variable X509\_VOMS\_DIR is taken.

If cert\_dir is empty, the value of the environment variable X509\_CERT\_DIR is taken.

#### 3.6.2.2 vomsdata::~vomsdata ()

#### 3.6.2.3 vomsdata::vomsdata (const vomsdata &)

### 3.6.3 Member Function Documentation

#### 3.6.3.1 bool vomsdata::LoadSystemContacts (std::string dir = "")

Loads the system wide configuration files.

##### Parameters:

*dir* The directory in which the files are stored.

If dir is empty, defaults to /opt/edg/etc/vomses.

##### Returns:

True if all went OK, false otherwise.

#### 3.6.3.2 bool vomsdata::LoadUserContacts (std::string dir = "")

Loads the user-specific configuration files.

##### Parameters:

*dir* The directory in which the files are stored.

If dir is empty, defaults to \$VOMS\_USERCONF. If this is empty too, defaults to \$HOME/.edg/vomses, or to ~/.edg/vomses as a last resort.

**Returns:**

True if all went OK, false otherwise.

**3.6.3.3 `std::vector<contactdata> vomldata::FindByAlias (std::string alias)`**

Finds servers which share a common alias.

**Parameters:**

*alias* The alias to look for.

**Returns:**

The servers found. The order in which they are returned is unspecified.

**3.6.3.4 `std::vector<contactdata> vomldata::FindByVO (std::string vo)`**

Finds servers which serve a common VO

**Parameters:**

*vo* The VO name to look for.

**Returns:**

The servers found. The order in which they are returned is unspecified.

**3.6.3.5 `void vomldata::Order (std::string att)`**

Sets up the ordering of the results.

Defines the ordering of the [data](#) returned by [Contact\(\)](#). Results are ordered in the same order as the calls to this function.

**Parameters:**

*att* The [attribute](#) to be ordered.

**3.6.3.6 `void vomldata::ResetOrder (void)`**

Resets the ordering.

**3.6.3.7 `void vomldata::AddTarget (std::string target)`**

Adds a target to the AC.

**Parameters:**

*target* The target to be added. it should be a FQDN.

**3.6.3.8 std::vector<std::string> vomsdata::ListTargets (void)**

Returns the list of targets.

**3.6.3.9 void vomsdata::ResetTargets (void)**

Resets the target list.

**3.6.3.10 std::string vomsdata::ServerErrors (void)**

Gets the error message returned by the server

**3.6.3.11 bool vomsdata::Retrieve (X509 \* *cert*, STACK\_OF(X509)\* *chain*, recurse\_type *how* = RECURSE\_CHAIN)**

Extracts the VOMS extension from an X.509 certificate. The function doesn't check the validity of the certificates, but it does check the content of the user [data](#).

**Parameters:**

- cert* The certificate with the VOMS extensions
- chain* The chain of the validation certificates (only the intermediate ones)
- how* Recursion type

**Returns:**

failure (F) or success (T)

**3.6.3.12 bool vomsdata::Contact (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*)**

Contacts a VOMS server to get a certificate

It is the equivalent of the voms\_proxy\_init command, but without the --include functionality.

**Parameters:**

- hostname* FQDN of the VOMS server
- port* the port on which the VOMS server is listening
- servsubject* the subject of the server's certificate
- command* the command sent to the server

**Returns:**

failure (F) or success (T)

### 3.6.3.13 **bool vomsdata::Contact** (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, int *timeout*)

Contacts a VOMS server to get a certificate

It is the equivalent of the voms\_proxy\_init command, but without the --include functionality.

#### Parameters:

*hostname* FQDN of the VOMS server  
*port* the port on which the VOMS server is listening  
*servsubject* the subject of the server's certificate  
*command* the command sent to the server

#### Returns:

failure (F) or success (T)

### 3.6.3.14 **bool vomsdata::ContactRaw** (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, std::string & *raw*, int & *version*)

Same as Contact, however it does not start the verification process, and the message received from the server is not parsed.

#### Parameters:

*hostname* FQDN of the VOMS server  
*port* the port on which the VOMS server is listening  
*servsubject* the subject of the server's certificate  
*command* the command sent to the server  
*raw* OUTPUT PARAMETER the answer from the server  
*version* OUTPUT PARAMETER the version of the answer

#### Returns:

failure (F) or success (T)

### 3.6.3.15 **bool vomsdata::ContactRaw** (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, std::string & *raw*, int & *version*, int *timeout*)

Same as Contact, however it does not start the verification process, and the message received from the server is not parsed.

#### Parameters:

*hostname* FQDN of the VOMS server  
*port* the port on which the VOMS server is listening  
*servsubject* the subject of the server's certificate  
*command* the command sent to the server  
*raw* OUTPUT PARAMETER the answer from the server

*version* OUTPUT PARAMETER the version of the answer

**Returns:**

failure (F) or success (T)

**3.6.3.16 void vomsdata::SetVerificationType (verify\_type *how*)**

Sets the type of verification done on the [data](#).

**Parameters:**

*how* The type of verification.

**3.6.3.17 void vomsdata::SetLifetime (int *lifetime*)**

Set requested lifetime for the [Contact\(\)](#) call.

**Parameters:**

*lifetime* Requested lifetime, in seconds

**3.6.3.18 bool vomsdata::Import (std::string *buffer*)**

Converts [data](#) from the format used for inclusion into a certificate to the internal format

The function does verify the [data](#).

**Parameters:**

*buffer* contains the [data](#) to be converted

**Returns:**

Failure (F) or Success (T)

**3.6.3.19 bool vomsdata::Export (std::string & *data*)**

Exports [data](#) from [vomsdata::data](#) to the format used for inclusion into a certificate.

The function doesn't verify the [data](#)

**Parameters:**

*data* The certificate extension

**Returns:**

Failure (F) or Success (T)

**3.6.3.20 bool vomsdata::DefaultData (voms &)**

Get the default [data](#) extension from those present in the pseudo certificate

**3.6.3.21 std::string vomsdata::ErrorMessage (void)**

Gets a textual description of the error.

**Returns:**

A string containing the error message.

**3.6.3.22 bool vomsdata::RetrieveFromCtx (gss\_ctx\_id\_t *context*, recurse\_type *how*)**

Gets VOMS information from the given globus context

**Parameters:**

*context* The context from which to retrieve the certificate.

*how* Recursion type

**Returns:**

failure (F) or success (T)

**3.6.3.23 bool vomsdata::RetrieveFromCred (gss\_cred\_id\_t *credential*, recurse\_type *how*)**

Gets VOMS information from the given globus credential

**Parameters:**

*credential* The credential from which to retrieve the certificate.

*how* Recursion type

**Returns:**

failure (F) or success (T)

**3.6.3.24 bool vomsdata::Retrieve (X509\_EXTENSION \* *ext*)**

Gets VOMS information from the given extension

**Parameters:**

*ext* The extension to parse.

**Returns:**

failure (F) or success (T)

**3.6.3.25 bool vomsdata::RetrieveFromProxy (recurse\_type *how*)**

Gets VOMS information from an existing globus proxy

**Parameters:**

*how* Recursion type

**Returns:**

failure (F) or success (T)

**3.6.3.26 bool vomsdata::Retrieve (FILE \**file*, recurse\_type *how*)**

Gets VOMS information from a proxy saved as a file.

**Parameters:**

*the* file

*how* Recursion type

**Returns:**

failure (F) or success (T)

Note: Does NOT verify that the proxy is valid. Such verification must be obtained through other means.

**3.6.3.27 void vomsdata::SetRetryCount (int *retryCount*)****3.6.3.28 void vomsdata::SetVerificationTime (time\_t)****3.6.3.29 bool vomsdata::LoadCredentials (X509 \*, EVP\_PKEY \*, STACK\_OF(X509)\*)****3.6.4 Field Documentation****3.6.4.1 verror\_type vomsdata::error**

Error code

Definition at line 189 of file voms\_api.h.

**3.6.4.2 std::vector<voms> vomsdata::data**

User's info, as in the certificate extension. It may contain [data](#) gathered from more than one VOMS server,

Definition at line 344 of file voms\_api.h.

**3.6.4.3 std::string vomsdata::workvo**

The value of the -vo option of the voms-proxy-init command

Definition at line 347 of file voms\_api.h.

#### 3.6.4.4 std::string vomsdata::extra\_data

The [data](#) specified by the user with the `--include` switch.

Note that this field doesn't contain the result of a request to the VOMS server, but instead [data](#) specified by the user.

The reason for the introduction of this extension is to let a user include important [data](#) into his proxy certificate, like, for example, a kerberos ticket

Definition at line 348 of file `voms_api.h`.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)



# Chapter 4

## File Documentation

### 4.1 voms\_api.h File Reference

```
#include <fstream>
#include <string>
#include <vector>
#include <openssl/x509.h>
#include <openssl/bio.h>
#include <sys/types.h>
#include "newformat.h"
```

#### Data Structures

- struct [data](#)  
*User's characteristics: can be repeated.*
- struct [attribute](#)
- struct [attributelist](#)
- struct [contactdata](#)
- struct [voms](#)
- struct [vomsdata](#)
- class [vomsdata::Initializer](#)

#### Typedefs

- typedef void \* [gss\\_cred\\_id\\_t](#)
- typedef void \* [gss\\_ctx\\_id\\_t](#)
- typedef bool(\* [check\\_sig](#))(X509 \*, void \*, [verror\\_type](#) &)

#### Enumerations

- enum [data\\_type](#) { [TYPE\\_NODATA](#), [TYPE\\_STD](#), [TYPE\\_CUSTOM](#) }

The type of *data* returned.

- enum `recurse_type` { `RECURSE_CHAIN`, `RECURSE_NONE`, `RECURSE_DEEP` }
- enum `verify_type` {  
`VERIFY_FULL` = 0xffffffff, `VERIFY_NONE` = 0x00000000, `VERIFY_DATE` = 0x00000001,  
`VERIFY_TARGET` = 0x00000002,  
`VERIFY_KEY` = 0x00000004, `VERIFY_SIGN` = 0x00000008, `VERIFY_ORDER` = 0x00000010,  
`VERIFY_ID` = 0x00000020,  
`VERIFY_CERTLIST` = 0x00000040 }
- enum `verror_type` {  
`VERR_NONE`, `VERR_NOCKET`, `VERR_NOIDENT`, `VERR_COMM`,  
`VERR_PARAM`, `VERR_NOEXT`, `VERR_NOINIT`, `VERR_TIME`,  
`VERR_IDCHECK`, `VERR_EXTRINFO`, `VERR_FORMAT`, `VERR_NODATA`,  
`VERR_PARSE`, `VERR_DIR`, `VERR_SIGN`, `VERR_SERVER`,  
`VERR_MEM`, `VERR_VERIFY`, `VERR_TYPE`, `VERR_ORDER`,  
`VERR_SERVERCODE`, `VERR_NOTAVAIL`, `VERR_FILE` }

Error codes.

## Functions

- int `getMajorVersionNumber` (void)
- int `getMinorVersionNumber` (void)
- int `getPatchVersionNumber` (void)

### 4.1.1 Typedef Documentation

#### 4.1.1.1 typedef bool(\* check\_sig)(X509 \*, void \*, verror\_type &)

Definition at line 168 of file `voms_api.h`.

#### 4.1.1.2 typedef void\* gss\_cred\_id\_t

Definition at line 26 of file `voms_api.h`.

#### 4.1.1.3 typedef void\* gss\_ctx\_id\_t

Definition at line 27 of file `voms_api.h`.

### 4.1.2 Enumeration Type Documentation

#### 4.1.2.1 enum data\_type

The type of *data* returned.

**Enumerator:**

*TYPE\_NODATA* no data  
*TYPE\_STD* group, role, capability triplet  
*TYPE\_CUSTOM* result of an S command

Definition at line 60 of file voms\_api.h.

**4.1.2.2 enum recurse\_type****Enumerator:**

*RECURSE\_CHAIN*  
*RECURSE\_NONE*  
*RECURSE\_DEEP*

Definition at line 121 of file voms\_api.h.

**4.1.2.3 enum verify\_type****Enumerator:**

*VERIFY\_FULL*  
*VERIFY\_NONE*  
*VERIFY\_DATE*  
*VERIFY\_TARGET*  
*VERIFY\_KEY*  
*VERIFY\_SIGN*  
*VERIFY\_ORDER*  
*VERIFY\_ID*  
*VERIFY\_CERTLIST*

Definition at line 127 of file voms\_api.h.

**4.1.2.4 enum verror\_type**

Error codes.

**Enumerator:**

*VERR\_NONE*  
*VERR\_NOSOCKET* Socket problem  
*VERR\_NOIDENT* Cannot identify itself (certificate problem)  
*VERR\_COMM* Server problem  
*VERR\_PARAM* Wrong parameters  
*VERR\_NOEXT* VOMS extension missing  
*VERR\_NOINIT* Initialization error  
*VERR\_TIME* Error in time checking

***VERR\_IDCHECK*** User [data](#) in extension different from the real ones  
***VERR\_EXTRAINFO*** VO name and URI missing  
***VERR\_FORMAT*** Wrong [data](#) format  
***VERR\_NODATA*** Empty extension  
***VERR\_PARSE*** Parse error  
***VERR\_DIR*** Directory error  
***VERR\_SIGN*** Signature error  
***VERR\_SERVER*** Unidentifiable VOMS server  
***VERR\_MEM*** Memory problems  
***VERR\_VERIFY*** Generic verification error  
***VERR\_TYPE*** Returned [data](#) of unknown type  
***VERR\_ORDER*** Ordering different than required  
***VERR\_SERVERCODE*** Error message from the server  
***VERR\_NOTAVAIL*** Method not available  
***VERR\_FILE*** Error reading [data](#) from file

Definition at line 141 of file voms\_api.h.

### 4.1.3 Function Documentation

**4.1.3.1** `int getMajorVersionNumber (void)`

**4.1.3.2** `int getMinorVersionNumber (void)`

**4.1.3.3** `int getPatchVersionNumber (void)`

# Index

- ~voms
  - voms, [12](#)
- ~vomsgdata
  - vomsgdata, [16](#)
- AddTarget
  - vomsgdata, [17](#)
- attribute, [5](#)
  - name, [5](#)
  - qualifier, [5](#)
  - value, [5](#)
- attributelist, [7](#)
  - attributes, [7](#)
  - grantor, [7](#)
- attributes
  - attributelist, [7](#)
- cap
  - data, [10](#)
- check\_sig
  - voms\_api.h, [26](#)
- Contact
  - vomsgdata, [18](#)
- contact
  - contactdata, [8](#)
- contactdata, [8](#)
  - contact, [8](#)
  - host, [8](#)
  - nick, [8](#)
  - port, [8](#)
  - version, [8](#)
  - vo, [8](#)
- ContactRaw
  - vomsgdata, [19](#)
- custom
  - voms, [14](#)
- data, [10](#)
  - cap, [10](#)
  - group, [10](#)
  - role, [10](#)
  - vomsgdata, [22](#)
- data\_type
  - voms\_api.h, [26](#)
- date1
  - voms, [13](#)
- date2
  - voms, [13](#)
- DefaultData
  - vomsgdata, [20](#)
- error
  - vomsgdata, [22](#)
- ErrorMessage
  - vomsgdata, [20](#)
- Export
  - vomsgdata, [20](#)
- extra\_data
  - vomsgdata, [22](#)
- FindByAlias
  - vomsgdata, [17](#)
- FindByVO
  - vomsgdata, [17](#)
- fqn
  - voms, [14](#)
- GetAC
  - voms, [12](#)
- GetAttributes
  - voms, [12](#)
- getMajorVersionNumber
  - voms\_api.h, [28](#)
- getMinorVersionNumber
  - voms\_api.h, [28](#)
- getPatchVersionNumber
  - voms\_api.h, [28](#)
- GetTargets
  - voms, [12](#)
- grantor
  - attributelist, [7](#)
- group
  - data, [10](#)
- gss\_cred\_id\_t
  - voms\_api.h, [26](#)
- gss\_ctx\_id\_t
  - voms\_api.h, [26](#)
- host
  - contactdata, [8](#)

- Import
  - vomsdata, 20
- ListTargets
  - vomsdata, 17
- LoadCredentials
  - vomsdata, 22
- LoadSystemContacts
  - vomsdata, 16
- LoadUserContacts
  - vomsdata, 16
- name
  - attribute, 5
- nick
  - contactdata, 8
- operator=
  - voms, 12
- Order
  - vomsdata, 17
- port
  - contactdata, 8
- qualifier
  - attribute, 5
- RECURSE\_CHAIN
  - voms\_api.h, 27
- RECURSE\_DEEP
  - voms\_api.h, 27
- RECURSE\_NONE
  - voms\_api.h, 27
- recurse\_type
  - voms\_api.h, 27
- ResetOrder
  - vomsdata, 17
- ResetTargets
  - vomsdata, 18
- Retrieve
  - vomsdata, 18, 21, 22
- RetrieveFromCred
  - vomsdata, 21
- RetrieveFromCtx
  - vomsdata, 21
- RetrieveFromProxy
  - vomsdata, 21
- role
  - data, 10
- serial
  - voms, 14
- server
  - voms, 13
- serverca
  - voms, 13
- ServerErrors
  - vomsdata, 18
- SetLifetime
  - vomsdata, 20
- SetRetryCount
  - vomsdata, 22
- SetVerificationTime
  - vomsdata, 22
- SetVerificationType
  - vomsdata, 20
- siglen
  - voms, 12
- signature
  - voms, 12
- std
  - voms, 13
- TranslateVOMS
  - voms, 12
- type
  - voms, 13
- TYPE\_CUSTOM
  - voms\_api.h, 27
- TYPE\_NODATA
  - voms\_api.h, 27
- TYPE\_STD
  - voms\_api.h, 27
- uri
  - voms, 13
- user
  - voms, 12
- userca
  - voms, 13
- value
  - attribute, 5
- VERIFY\_CERTLIST
  - voms\_api.h, 27
- VERIFY\_DATE
  - voms\_api.h, 27
- VERIFY\_FULL
  - voms\_api.h, 27
- VERIFY\_ID
  - voms\_api.h, 27
- VERIFY\_KEY
  - voms\_api.h, 27
- VERIFY\_NONE
  - voms\_api.h, 27
- VERIFY\_ORDER
  - voms\_api.h, 27
- VERIFY\_SIGN

- voms\_api.h, [27](#)
- VERIFY\_TARGET
  - voms\_api.h, [27](#)
- verify\_type
  - voms\_api.h, [27](#)
- VERR\_COMM
  - voms\_api.h, [27](#)
- VERR\_DIR
  - voms\_api.h, [28](#)
- VERR\_EXTRAINFO
  - voms\_api.h, [28](#)
- VERR\_FILE
  - voms\_api.h, [28](#)
- VERR\_FORMAT
  - voms\_api.h, [28](#)
- VERR\_IDCHECK
  - voms\_api.h, [27](#)
- VERR\_MEM
  - voms\_api.h, [28](#)
- VERR\_NODATA
  - voms\_api.h, [28](#)
- VERR\_NOEXT
  - voms\_api.h, [27](#)
- VERR\_NOIDENT
  - voms\_api.h, [27](#)
- VERR\_NOINIT
  - voms\_api.h, [27](#)
- VERR\_NONE
  - voms\_api.h, [27](#)
- VERR\_NOSOCKET
  - voms\_api.h, [27](#)
- VERR\_NOTAVAIL
  - voms\_api.h, [28](#)
- VERR\_ORDER
  - voms\_api.h, [28](#)
- VERR\_PARAM
  - voms\_api.h, [27](#)
- VERR\_PARSE
  - voms\_api.h, [28](#)
- VERR\_SERVER
  - voms\_api.h, [28](#)
- VERR\_SERVERCODE
  - voms\_api.h, [28](#)
- VERR\_SIGN
  - voms\_api.h, [28](#)
- VERR\_TIME
  - voms\_api.h, [27](#)
- VERR\_TYPE
  - voms\_api.h, [28](#)
- VERR\_VERIFY
  - voms\_api.h, [28](#)
- verror\_type
  - voms\_api.h, [27](#)
- version
  - contactdata, [8](#)
  - voms, [12](#)
- vo
  - contactdata, [8](#)
- voms, [11](#)
  - ~voms, [12](#)
  - custom, [14](#)
  - date1, [13](#)
  - date2, [13](#)
  - fqan, [14](#)
  - GetAC, [12](#)
  - GetAttributes, [12](#)
  - GetTargets, [12](#)
  - operator=, [12](#)
  - serial, [14](#)
  - server, [13](#)
  - serverca, [13](#)
  - siglen, [12](#)
  - signature, [12](#)
  - std, [13](#)
  - TranslateVOMS, [12](#)
  - type, [13](#)
  - uri, [13](#)
  - user, [12](#)
  - userca, [13](#)
  - version, [12](#)
  - voms, [12](#)
  - vomsdata, [12](#)
  - voname, [13](#)
- voms\_api.h
  - RECURSE\_CHAIN, [27](#)
  - RECURSE\_DEEP, [27](#)
  - RECURSE\_NONE, [27](#)
  - TYPE\_CUSTOM, [27](#)
  - TYPE\_NODATA, [27](#)
  - TYPE\_STD, [27](#)
  - VERIFY\_CERTLIST, [27](#)
  - VERIFY\_DATE, [27](#)
  - VERIFY\_FULL, [27](#)
  - VERIFY\_ID, [27](#)
  - VERIFY\_KEY, [27](#)
  - VERIFY\_NONE, [27](#)
  - VERIFY\_ORDER, [27](#)
  - VERIFY\_SIGN, [27](#)
  - VERIFY\_TARGET, [27](#)
  - VERR\_COMM, [27](#)
  - VERR\_DIR, [28](#)
  - VERR\_EXTRAINFO, [28](#)
  - VERR\_FILE, [28](#)
  - VERR\_FORMAT, [28](#)
  - VERR\_IDCHECK, [27](#)
  - VERR\_MEM, [28](#)
  - VERR\_NODATA, [28](#)
  - VERR\_NOEXT, [27](#)

- VERR\_NOIDENT, 27
- VERR\_NOINIT, 27
- VERR\_NONE, 27
- VERR\_NOCKET, 27
- VERR\_NOTAVAIL, 28
- VERR\_ORDER, 28
- VERR\_PARAM, 27
- VERR\_PARSE, 28
- VERR\_SERVER, 28
- VERR\_SERVERCODE, 28
- VERR\_SIGN, 28
- VERR\_TIME, 27
- VERR\_TYPE, 28
- VERR\_VERIFY, 28
- voms\_api.h, 25
  - check\_sig, 26
  - data\_type, 26
  - getMajorVersionNumber, 28
  - getMinorVersionNumber, 28
  - getPatchVersionNumber, 28
  - gss\_cred\_id\_t, 26
  - gss\_ctx\_id\_t, 26
  - recurse\_type, 27
  - verify\_type, 27
  - verror\_type, 27
- vomsdata, 15
  - ~vomsdata, 16
  - AddTarget, 17
  - Contact, 18
  - ContactRaw, 19
  - data, 22
  - DefaultData, 20
  - error, 22
  - ErrorMessage, 20
  - Export, 20
  - extra\_data, 22
  - FindByAlias, 17
  - FindByVO, 17
  - Import, 20
  - ListTargets, 17
  - LoadCredentials, 22
  - LoadSystemContacts, 16
  - LoadUserContacts, 16
  - Order, 17
  - ResetOrder, 17
  - ResetTargets, 18
  - Retrieve, 18, 21, 22
  - RetrieveFromCred, 21
  - RetrieveFromCtx, 21
  - RetrieveFromProxy, 21
  - ServerErrors, 18
  - SetLifetime, 20
  - SetRetryCount, 22
  - SetVerificationTime, 22
  - SetVerificationType, 20
  - voms, 12
  - vomsdata, 16
  - workvo, 22
- voname
  - voms, 13
- workvo
  - vomsdata, 22