

# VOMS CC API Reference Manual

## 1.5.0

Generated by Doxygen 1.5.1

Tue Nov 2 23:00:48 2010



# Contents

<b>1</b>	<b>VOMS CC API Data Structure Index</b>	<b>1</b>
1.1	VOMS CC API Data Structures . . . . .	1
<b>2</b>	<b>VOMS CC API File Index</b>	<b>3</b>
2.1	VOMS CC API File List . . . . .	3
<b>3</b>	<b>VOMS CC API Data Structure Documentation</b>	<b>5</b>
3.1	attribute Struct Reference . . . . .	5
3.2	attributelist Struct Reference . . . . .	7
3.3	contactdata Struct Reference . . . . .	8
3.4	data Struct Reference . . . . .	10
3.5	voms Struct Reference . . . . .	11
3.6	vomsdata Struct Reference . . . . .	15
<b>4</b>	<b>VOMS CC API File Documentation</b>	<b>25</b>
4.1	voms_api.h File Reference . . . . .	25



# Chapter 1

## VOMS CC API Data Structure Index

### 1.1 VOMS CC API Data Structures

Here are the data structures with brief descriptions:

<code>attribute</code> . . . . .	5
<code>attributelist</code> . . . . .	7
<code>contactdata</code> . . . . .	8
<code>data</code> (User's characteristics: can be repeated ) . . . . .	10
<code>voms</code> . . . . .	11
<code>vomsdata</code> . . . . .	15



## **Chapter 2**

# **VOMS CC API File Index**

### **2.1 VOMS CC API File List**

Here is a list of all files with brief descriptions:

<a href="#">voms_api.h</a>	.....	25
----------------------------	-------	----



# Chapter 3

## VOMS CC API Data Structure Documentation

### 3.1 attribute Struct Reference

```
#include <voms_api.h>
```

#### Data Fields

- std::string [name](#)
- std::string [qualifier](#)
- std::string [value](#)

#### 3.1.1 Detailed Description

Definition at line 60 of file voms\_api.h.

#### 3.1.2 Field Documentation

##### 3.1.2.1 std::string [attribute::name](#)

attribute's group

Definition at line 61 of file voms\_api.h.

##### 3.1.2.2 std::string [attribute::qualifier](#)

attribute's qualifier

Definition at line 62 of file voms\_api.h.

##### 3.1.2.3 std::string [attribute::value](#)

attribute's value

Definition at line 63 of file voms\_api.h.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)

## 3.2 attributelist Struct Reference

```
#include <voms_api.h>
```

### Data Fields

- std::string [grantor](#)
- std::vector<[attribute](#)> [attributes](#)

#### 3.2.1 Detailed Description

Definition at line 66 of file voms\_api.h.

#### 3.2.2 Field Documentation

##### 3.2.2.1 std::string [attributelist::grantor](#)

Who granted these attributes.

Definition at line 67 of file voms\_api.h.

##### 3.2.2.2 std::vector<[attribute](#)> [attributelist::attributes](#)

The attributes themselves.

Definition at line 68 of file voms\_api.h.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)

### 3.3 contactdata Struct Reference

```
#include <voms_api.h>
```

#### Data Fields

- std::string **nick**
- std::string **host**
- std::string **contact**
- std::string **vo**
- int **port**
- int **version**

#### 3.3.1 Detailed Description

Definition at line 80 of file voms\_api.h.

#### 3.3.2 Field Documentation

##### 3.3.2.1 std::string **contactdata::nick**

< You must never allocate directly this structure. Its sizeof() is subject to change without notice. The only supported way to obtain it is via the FindBy\* functions. The alias of the server

Definition at line 84 of file voms\_api.h.

##### 3.3.2.2 std::string **contactdata::host**

The hostname of the server

Definition at line 85 of file voms\_api.h.

##### 3.3.2.3 std::string **contactdata::contact**

The subject of the server's certificate

Definition at line 86 of file voms\_api.h.

##### 3.3.2.4 std::string **contactdata::vo**

The VO served by this server

Definition at line 87 of file voms\_api.h.

##### 3.3.2.5 int **contactdata::port**

The port on which the server is listening

Definition at line 88 of file voms\_api.h.

### 3.3.2.6 int **contactdata::version**

The version of globus under which the server is running

Definition at line 90 of file voms\_api.h.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)

## 3.4 data Struct Reference

User's characteristics: can be repeated.

```
#include <voms_api.h>
```

### Data Fields

- std::string [group](#)
- std::string [role](#)
- std::string [cap](#)

#### 3.4.1 Detailed Description

User's characteristics: can be repeated.

Definition at line 52 of file voms\_api.h.

#### 3.4.2 Field Documentation

##### 3.4.2.1 std::string [data::group](#)

user's group

Definition at line 53 of file voms\_api.h.

##### 3.4.2.2 std::string [data::role](#)

user's role

Definition at line 54 of file voms\_api.h.

##### 3.4.2.3 std::string [data::cap](#)

user's capability

Definition at line 55 of file voms\_api.h.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)

## 3.5 voms Struct Reference

```
#include <voms_api.h>
```

### Public Member Functions

- `voms` (const `voms` &)
- `voms` ()
- `voms` & `operator=` (const `voms` &)
- `~voms` ()
- `AC * GetAC` ()
- `std::vector< attributelist > & GetAttributes` ()
- `std::vector< std::string > GetTargets` ()

### Data Fields

- `int version`
- `int siglen`
- `std::string signature`
- `std::string user`
- `std::string userca`
- `std::string server`
- `std::string serverca`
- `std::string voname`
- `std::string uri`
- `std::string date1`
- `std::string date2`
- `data_type type`
- `std::vector< data > std`
- `std::string custom`
- `std::vector< std::string > fqan`
- `std::string serial`

### Friends

- class `vomsdata`
- `int TranslateVOMS` (struct `vomsdata` \*vd, `std::vector< voms > &v, int *error)`

### 3.5.1 Detailed Description

Definition at line 93 of file `voms_api.h`.

### 3.5.2 Constructor & Destructor Documentation

3.5.2.1 `voms::voms (const voms &)`

3.5.2.2 `voms::voms ()`

3.5.2.3 `voms::~voms ()`

### 3.5.3 Member Function Documentation

3.5.3.1 `voms& voms::operator= (const voms &)`

3.5.3.2 `AC* voms::GetAC ()`

3.5.3.3 `std::vector<attributelist>& voms::GetAttributes ()`

Generic attributes

3.5.3.4 `std::vector<std::string> voms::GetTargets ()`

### 3.5.4 Friends And Related Function Documentation

3.5.4.1 `friend class vomsdata [friend]`

Definition at line 94 of file voms\_api.h.

3.5.4.2 `int TranslateVOMS (struct vomsdata * vd, std::vector< voms > & v, int * error) [friend]`

### 3.5.5 Field Documentation

3.5.5.1 `int voms::version`

0 means data didn't originate from an AC

Definition at line 95 of file voms\_api.h.

3.5.5.2 `int voms::siglen`

The length of the VOMS server signature

Definition at line 96 of file voms\_api.h.

3.5.5.3 `std::string voms::signature`

The VOMS server signature

Definition at line 97 of file voms\_api.h.

**3.5.5.4 std::string voms::user**

The user's DN, as from his certificate

Definition at line 98 of file voms\_api.h.

**3.5.5.5 std::string voms::userca**

The CA which signed the user's certificate

Definition at line 99 of file voms\_api.h.

**3.5.5.6 std::string voms::server**

The VOMS server DN, as from its certificate

Definition at line 100 of file voms\_api.h.

**3.5.5.7 std::string voms::serverca**

The CA which signed the VOMS certificate

Definition at line 101 of file voms\_api.h.

**3.5.5.8 std::string voms::vuname**

The name of the VO to which the VOMS belongs

Definition at line 102 of file voms\_api.h.

**3.5.5.9 std::string voms::uri**

The URI of the VOMS server

Definition at line 103 of file voms\_api.h.

**3.5.5.10 std::string voms::date1**

Beginning of validity of the user info

Definition at line 104 of file voms\_api.h.

**3.5.5.11 std::string voms::date2**

End of validity of the user info

Definition at line 105 of file voms\_api.h.

**3.5.5.12 data\_type voms::type**

The type of data returned

Definition at line 106 of file voms\_api.h.

### 3.5.5.13 std::vector<[data](#)> voms::std

User's characteristics

Definition at line 107 of file voms\_api.h.

### 3.5.5.14 std::string voms::custom

The data returned by an S command

Definition at line 108 of file voms\_api.h.

### 3.5.5.15 std::vector<std::string> voms::fqan

Keeps the data in the compact format

Definition at line 110 of file voms\_api.h.

### 3.5.5.16 std::string voms::serial

Serial number. "0" if coming from non-ac

Definition at line 111 of file voms\_api.h.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)

## 3.6 vomsdata Struct Reference

```
#include <voms_api.h>
```

### Public Member Functions

- `vomsdata (std::string voms_dir="", std::string cert_dir "")`
- `bool LoadSystemContacts (std::string dir "")`
- `bool LoadUserContacts (std::string dir "")`
- `std::vector< contactdata > FindByAlias (std::string alias)`
- `std::vector< contactdata > FindByVO (std::string vo)`
- `void Order (std::string att)`
- `void ResetOrder (void)`
- `void AddTarget (std::string target)`
- `std::vector< std::string > ListTargets (void)`
- `void ResetTargets (void)`
- `std::string ServerErrors (void)`
- `bool Retrieve (X509 *cert, STACK_OF(X509)*chain, recurse_type how=RECURSE_CHAIN)`
- `bool Contact (std::string hostname, int port, std::string servsubject, std::string command)`
- `bool Contact (std::string hostname, int port, std::string servsubject, std::string command, int timeout)`
- `bool ContactRaw (std::string hostname, int port, std::string servsubject, std::string command, std::string &raw, int &version)`
- `bool ContactRaw (std::string hostname, int port, std::string servsubject, std::string command, std::string &raw, int &version, int timeout)`
- `void SetVerificationType (verify_type how)`
- `void SetLifetime (int lifetime)`
- `bool Import (std::string buffer)`
- `bool Export (std::string &data)`
- `bool DefaultData (voms &)`
- `std::string ErrorMessage (void)`
- `bool RetrieveFromCtx (void *context, recurse_type how)`
- `bool RetrieveFromCred (void *credential, recurse_type how)`
- `bool RetrieveFromCtx (gss_ctx_id_t context, recurse_type how)`
- `bool RetrieveFromCred (gss_cred_id_t credential, recurse_type how)`
- `bool Retrieve (X509_EXTENSION *ext)`
- `bool RetrieveFromProxy (recurse_type how)`
- `bool Retrieve (FILE *file, recurse_type how)`
- `~vomsdata ()`
- `vomsdata (const vomsdata &)`
- `void SetRetryCount (int retryCount)`
- `void SetVerificationTime (time_t)`
- `bool LoadCredentials (X509 *, EVP_PKEY *, STACK_OF(X509)*)`

### Data Fields

- `verror_type error`
- `std::vector< voms > data`
- `std::string workvo`
- `std::string extra_data`

## Data Structures

- class **Initializer**

### 3.6.1 Detailed Description

Definition at line 184 of file voms\_api.h.

### 3.6.2 Constructor & Destructor Documentation

#### 3.6.2.1 **vomsdata::vomsdata (std::string *voms\_dir* = "", std::string *cert\_dir* = "")**

##### Parameters:

*voms\_dir* The directory which contains the certificate of the VOMS server

*cert\_dir* The directory which contains the certificate of the CA

If *voms\_dir* is empty, the value of the environment variable X509\_VOMS\_DIR is taken.

If *cert\_dir* is empty, the value of the environment variable X509\_CERT\_DIR is taken.

#### 3.6.2.2 **vomsdata::~vomsdata ()**

#### 3.6.2.3 **vomsdata::vomsdata (const **vomsdata** &)**

### 3.6.3 Member Function Documentation

#### 3.6.3.1 **bool vomsdata::LoadSystemContacts (std::string *dir* = "")**

Loads the system wide configuration files.

##### Parameters:

*dir* The directory in which the files are stored.

If *dir* is empty, defaults to /opt/edg/etc/vomses.

##### Returns:

True if all went OK, false otherwise.

#### 3.6.3.2 **bool vomsdata::LoadUserContacts (std::string *dir* = "")**

Loads the user-specific configuration files.

##### Parameters:

*dir* The directory in which the files are stored.

If *dir* is empty, defaults to \$VOMS\_USERCONF. If this is empty too, defaults to \$HOME/.edg/vomses, or to ~/.edg/vomses as a last resort.

**Returns:**

True if all went OK, false otherwise.

**3.6.3.3 std::vector<[contactdata](#)> vomsdata::FindByAlias (std::string *alias*)**

Finds servers which share a common alias.

**Parameters:**

*alias* The alias to look for.

**Returns:**

The servers found. The order in which they are returned is unspecified.

**3.6.3.4 std::vector<[contactdata](#)> vomsdata::FindByVO (std::string *vo*)**

Finds servers which serve a common VO

**Parameters:**

*vo* The VO name to look for.

**Returns:**

The servers found. The order in which they are returned is unspecified.

**3.6.3.5 void vomsdata::Order (std::string *att*)**

Sets up the ordering of the results.

Defines the ordering of the data returned by [Contact\(\)](#). Results are ordered in the same order as the calls to this function.

**Parameters:**

*att* The attribute to be ordered.

**3.6.3.6 void vomsdata::ResetOrder (void)**

Resets the ordering.

**3.6.3.7 void vomsdata::AddTarget (std::string *target*)**

Adds a target to the AC.

**Parameters:**

*target* The target to be added. it should be a FQDN.

**3.6.3.8 std::vector<std::string> vomsdata::ListTargets (void)**

Returns the list of targets.

**3.6.3.9 void vomsdata::ResetTargets (void)**

Resets the target list.

**3.6.3.10 std::string vomsdata::ServerErrors (void)**

Gets the error message returned by the server

**3.6.3.11 bool vomsdata::Retrieve (X509 \* cert, STACK\_OF(X509)\* chain, recurse\_type how = RECURSE\_CHAIN)**

Extracts the VOMS extension from an X.509 certificate. The function doesn't check the validity of the certificates, but it does check the content of the user data.

**Parameters:**

*cert* The certificate with the VOMS extensions

*chain* The chain of the validation certificates (only the intermediate ones)

*how* Recursion type

**Returns:**

failure (F) or success (T)

**3.6.3.12 bool vomsdata::Contact (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*)**

Contacts a VOMS server to get a certificate

It is the equivalent of the voms\_proxy\_init command, but without the –include functionality.

**Parameters:**

*hostname* FQDN of the VOMS server

*port* the port on which the VOMS server is listening

*servsubject* the subject of the server's certificate

*command* the command sent to the server

**Returns:**

failure (F) or success (T)

**3.6.3.13 bool vomsdata::Contact (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, int *timeout*)**

Contacts a VOMS server to get a certificate

It is the equivalent of the voms\_proxy\_init command, but without the –include functionality.

**Parameters:**

*hostname* FQDN of the VOMS server  
*port* the port on which the VOMS server is listening  
*servsubject* the subject of the server's certificate  
*command* the command sent to the server

**Returns:**

failure (F) or success (T)

**3.6.3.14 bool vomsdata::ContactRaw (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, std::string & *raw*, int & *version*)**

Same as Contact, however it does not start the verification process, and the message received from the server is not parsed.

**Parameters:**

*hostname* FQDN of the VOMS server  
*port* the port on which the VOMS server is listening  
*servsubject* the subject of the server's certificate  
*command* the command sent to the server  
*raw* OUTPUT PARAMETER the answer from the server  
*version* OUTPUT PARAMETER the version of the answer

**Returns:**

failure (F) or success (T)

**3.6.3.15 bool vomsdata::ContactRaw (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, std::string & *raw*, int & *version*, int *timeout*)**

Same as Contact, however it does not start the verification process, and the message received from the server is not parsed.

**Parameters:**

*hostname* FQDN of the VOMS server  
*port* the port on which the VOMS server is listening  
*servsubject* the subject of the server's certificate  
*command* the command sent to the server  
*raw* OUTPUT PARAMETER the answer from the server

*version* OUTPUT PARAMETER the version of the answer

**Returns:**

failure (F) or success (T)

**3.6.3.16 void vomsdata::SetVerificationType (*verify\_type how*)**

Sets the type of verification done on the data.

**Parameters:**

*how* The type of verification.

**3.6.3.17 void vomsdata::SetLifetime (int *lifetime*)**

Set requested lifetime for the [Contact\(\)](#) call.

**Parameters:**

*lifetime* Requested lifetime, in seconds

**3.6.3.18 bool vomsdata::Import (std::string *buffer*)**

Converts data from the format used for inclusion into a certificate to the internal format

The function does verify the data.

**Parameters:**

*buffer* contains the data to be converted

**Returns:**

Failure (F) or Success (T)

**3.6.3.19 bool vomsdata::Export (std::string & *data*)**

Exports data from [vomsdata::data](#) to the format used for inclusion into a certificate.

The function doesn't verify the data

**Parameters:**

*data* The certificate extension

**Returns:**

Failure (F) or Success (T)

**3.6.3.20 bool vomsdata::DefaultData (*voms* &)**

Get the default data extension from those present in the pseudo certificate

**3.6.3.21 std::string vomsdata::ErrorMessage (void)**

Gets a textual description of the error.

**Returns:**

A string containg the error message.

**3.6.3.22 bool vomsdata::RetrieveFromCtx (void \* context, recurse\_type how)**

Gets VOMS information from the given globus context

**Parameters:**

*context* The context from which to retrieve the certificate.

*how* Recursion type

**Returns:**

failure (F) or success (T)

Referenced by RetrieveFromCtx().

**3.6.3.23 bool vomsdata::RetrieveFromCred (void \* credential, recurse\_type how)**

Gets VOMS information from the given globus credential

**Parameters:**

*credential* The credential from which to retrieve the certificate.

*how* Recursion type

**Returns:**

failure (F) or success (T)

Referenced by RetrieveFromCred().

**3.6.3.24 bool vomsdata::RetrieveFromCtx (gss\_ctx\_id\_t context, recurse\_type how) [inline]**

Gets VOMS information from the given globus context

**Parameters:**

*context* The context from which to retrieve the certificate.

*how* Recursion type

**Returns:**

failure (F) or success (T)

Definition at line 432 of file voms\_api.h.

References RetrieveFromCtx().

**3.6.3.25 bool vomsdata::RetrieveFromCred (gss\_cred\_id\_t *credential*, recurse\_type *how*)  
[inline]**

Gets VOMS information from the given globus credential

**Parameters:**

*credential* The credential from which to retrieve the certificate.  
*how* Recursion type

**Returns:**

failure (F) or success (T)

Definition at line 439 of file voms\_api.h.

References RetrieveFromCred().

**3.6.3.26 bool vomsdata::Retrieve (X509\_EXTENSION \* *ext*)**

Gets VOMS information from the given extension

**Parameters:**

*ext* The extension to parse.

**Returns:**

failure (F) or success (T)

**3.6.3.27 bool vomsdata::RetrieveFromProxy (recurse\_type *how*)**

Gets VOMS information from an existing globus proxy

**Parameters:**

*how* Recursion type

**Returns:**

failure (F) or success (T)

**3.6.3.28 bool vomsdata::Retrieve (FILE \* *file*, recurse\_type *how*)**

Gets VOMS information from a proxy saved as a file.

**Parameters:**

*the* file  
*how* Recursion type

**Returns:**

failure (F) or success (T)

Note: Does NOT verify that the proxy is valid. Such verification must be obtained through other means.

**3.6.3.29 void vomsdata::SetRetryCount (int *retryCount*)**

**3.6.3.30 void vomsdata::SetVerificationTime (time\_t)**

**3.6.3.31 bool vomsdata::LoadCredentials (X509 \*, EVP\_PKEY \*, STACK\_OF(X509)\*)**

## 3.6.4 Field Documentation

**3.6.4.1 *verror\_type* vomsdata::error**

Error code

Definition at line 203 of file voms\_api.h.

**3.6.4.2 std::vector<[voms](#)> vomsdata::data**

User's info, as in the certificate extension. It may contain data gathered from more than one VOMS server,

Definition at line 358 of file voms\_api.h.

**3.6.4.3 std::string vomsdata::workvo**

The value of the -vo option of the voms-proxy-init command

Definition at line 361 of file voms\_api.h.

**3.6.4.4 std::string vomsdata::extra\_data**

The data specified by the user with the –include switch.

Note that this field doesn't contain the result of a request to the VOMS server, but instead data specified by the user.

The reason for the introduction of this extension is to let a user include important data into his proxy certificate, like, for example, a kerberos ticket

Definition at line 362 of file voms\_api.h.

The documentation for this struct was generated from the following file:

- [voms\\_api.h](#)



# Chapter 4

# VOMS CC API File Documentation

## 4.1 voms\_api.h File Reference

```
#include <fstream>
#include <string>
#include <vector>
#include "gssapi.h"
#include <openssl/x509.h>
#include <openssl/bio.h>
#include <sys/types.h>
#include "newformat.h"
```

### Data Structures

- struct `data`  
*User's characteristics: can be repeated.*
  - struct `attribute`
  - struct `attributelist`
  - struct `contactdata`
  - struct `voms`
  - struct `vomsdata`
  - class `vomsdata::Initializer`

### Typedefs

- typedef bool(\*) `check_sig` (X509 \*, void \*, `verror_type` &)

### Enumerations

- enum `data_type` { `TYPE_NODATA`, `TYPE_STD`, `TYPE_CUSTOM` }

*The type of data returned.*

- enum `recurse_type` { `RECURSE_CHAIN`, `RECURSE_NONE`, `RECURSE_DEEP` }
- enum `verify_type` {
   
`VERIFY_FULL` = 0xffffffff, `VERIFY_NONE` = 0x00000000, `VERIFY_DATE` = 0x00000001,
 `VERIFY_TARGET` = 0x00000002,
   
`VERIFY_KEY` = 0x00000004, `VERIFY_SIGN` = 0x00000008, `VERIFY_ORDER` = 0x00000010,
 `VERIFY_ID` = 0x00000020,
   
`VERIFY_CERTLIST` = 0x00000040 }
- enum `verror_type` {
   
`VERR_NONE`, `VERR_NOSOCKET`, `VERR_NOIDENT`, `VERR_COMM`,
 `VERR_PARAM`, `VERR_NOEXT`, `VERR_NOINIT`, `VERR_TIME`,
 `VERR_IDCHECK`, `VERR_EXTRAINFO`, `VERR_FORMAT`, `VERR_NODATA`,
 `VERR_PARSE`, `VERR_DIR`, `VERR_SIGN`, `VERR_SERVER`,
 `VERR_MEM`, `VERR_VERIFY`, `VERR_TYPE`, `VERR_ORDER`,
 `VERR_SERVERCODE`, `VERR_NOTAVAIL`, `VERR_FILE` }

*Error codes.*

## Functions

- int `getMajorVersionNumber` (void)
- int `getMinorVersionNumber` (void)
- int `getPatchVersionNumber` (void)

### 4.1.1 Typedef Documentation

#### 4.1.1.1 `typedef bool(*) check_sig(X509 *, void *, verror_type &)`

Definition at line 182 of file voms\_api.h.

### 4.1.2 Enumeration Type Documentation

#### 4.1.2.1 `enum data_type`

The type of data returned.

##### Enumerator:

- `TYPE_NODATA` no data
- `TYPE_STD` group, role, capability triplet
- `TYPE_CUSTOM` result of an S command

Definition at line 74 of file voms\_api.h.

#### 4.1.2.2 enum recurse\_type

Enumerator:

*RECURSE\_CHAIN*  
*RECURSE\_NONE*  
*RECURSE\_DEEP*

Definition at line 135 of file voms\_api.h.

#### 4.1.2.3 enum verify\_type

Enumerator:

*VERIFY\_FULL*  
*VERIFY\_NONE*  
*VERIFY\_DATE*  
*VERIFY\_TARGET*  
*VERIFY\_KEY*  
*VERIFY\_SIGN*  
*VERIFY\_ORDER*  
*VERIFY\_ID*  
*VERIFY\_CERTLIST*

Definition at line 141 of file voms\_api.h.

#### 4.1.2.4 enum verror\_type

Error codes.

Enumerator:

*VERR\_NONE*  
*VERR\_NOSOCKET* Socket problem  
*VERR\_NOIDENT* Cannot identify itself (certificate problem)  
*VERR\_COMM* Server problem  
*VERR\_PARAM* Wrong parameters  
*VERR\_NOEXT* VOMS extension missing  
*VERR\_NOINIT* Initialization error  
*VERR\_TIME* Error in time checking  
*VERR\_IDCHECK* User data in extension different from the real ones  
*VERR\_EXTRAINFO* VO name and URI missing  
*VERR\_FORMAT* Wrong data format  
*VERR\_NODATA* Empty extension  
*VERR\_PARSE* Parse error  
*VERR\_DIR* Directory error

***VERR\_SIGN*** Signature error  
***VERR\_SERVER*** Unidentifiable VOMS server  
***VERR\_MEM*** Memory problems  
***VERR\_VERIFY*** Generic verification error  
***VERR\_TYPE*** Returned data of unknown type  
***VERR\_ORDER*** Ordering different than required  
***VERR\_SERVERCODE*** Error message from the server  
***VERR\_NOTAVAIL*** Method not available  
***VERR\_FILE*** Error reading data from file

Definition at line 155 of file voms\_api.h.

#### 4.1.3 Function Documentation

**4.1.3.1 int getMajorVersionNumber (void)**

**4.1.3.2 int getMinorVersionNumber (void)**

**4.1.3.3 int getPatchVersionNumber (void)**

# Index

~voms  
    voms, 12  
~vomsdata  
    vomsdata, 16

AddTarget  
    vomsdata, 17

attribute, 5  
    name, 5  
    qualifier, 5  
    value, 5

attributelist, 7  
    attributes, 7  
    grantor, 7

attributes  
    attributelist, 7

cap  
    data, 10

check\_sig  
    voms\_api.h, 26

Contact  
    vomsdata, 18

contact  
    contactdata, 8

contactdata, 8  
    contact, 8  
    host, 8  
    nick, 8  
    port, 8  
    version, 8  
    vo, 8

ContactRaw  
    vomsdata, 19

custom  
    voms, 14

data, 10  
    cap, 10  
    group, 10  
    role, 10  
    vomsdata, 23

data\_type  
    voms\_api.h, 26

date1

voms, 13

date2  
    voms, 13

DefaultData  
    vomsdata, 20

error  
    vomsdata, 23

ErrorMessage  
    vomsdata, 20

Export  
    vomsdata, 20

extra\_data  
    vomsdata, 23

FindByAlias  
    vomsdata, 17

FindByVO  
    vomsdata, 17

fqan  
    voms, 14

GetAC  
    voms, 12

GetAttributes  
    voms, 12

getMajorVersionNumber  
    voms\_api.h, 28

getMinorVersionNumber  
    voms\_api.h, 28

getPatchVersionNumber  
    voms\_api.h, 28

GetTargets  
    voms, 12

grantor  
    attributelist, 7

group  
    data, 10

host  
    contactdata, 8

Import  
    vomsdata, 20

ListTargets

vomsdata, 17  
 LoadCredentials  
     vomsdata, 23  
 LoadSystemContacts  
     vomsdata, 16  
 LoadUserContacts  
     vomsdata, 16  
  
 name  
     attribute, 5  
 nick  
     contactdata, 8  
  
 operator=  
     voms, 12  
 Order  
     vomsdata, 17  
  
 port  
     contactdata, 8  
  
 qualifier  
     attribute, 5  
  
 RECURSE\_CHAIN  
     voms\_api.h, 27  
 RECURSE\_DEEP  
     voms\_api.h, 27  
 RECURSE\_NONE  
     voms\_api.h, 27  
 recurse\_type  
     voms\_api.h, 26  
 ResetOrder  
     vomsdata, 17  
 ResetTargets  
     vomsdata, 18  
 Retrieve  
     vomsdata, 18, 22  
 RetrieveFromCred  
     vomsdata, 21  
 RetrieveFromCtx  
     vomsdata, 21  
 RetrieveFromProxy  
     vomsdata, 22  
 role  
     data, 10  
  
 serial  
     voms, 14  
 server  
     voms, 13  
 serverca  
     voms, 13  
 ServerErrors  
     vomsdata, 18  
  
 SetLifetime  
     vomsdata, 20  
 SetRetryCount  
     vomsdata, 22  
 SetVerificationTime  
     vomsdata, 23  
 SetVerificationType  
     vomsdata, 20  
 siglen  
     voms, 12  
 signature  
     voms, 12  
 std  
     voms, 13  
  
 TranslateVOMS  
     voms, 12  
 type  
     voms, 13  
 TYPE\_CUSTOM  
     voms\_api.h, 26  
 TYPE\_NODATA  
     voms\_api.h, 26  
 TYPE\_STD  
     voms\_api.h, 26  
  
 uri  
     voms, 13  
 user  
     voms, 12  
 userca  
     voms, 13  
  
 value  
     attribute, 5  
 VERIFY\_CERTLIST  
     voms\_api.h, 27  
 VERIFY\_DATE  
     voms\_api.h, 27  
 VERIFY\_FULL  
     voms\_api.h, 27  
 VERIFY\_ID  
     voms\_api.h, 27  
 VERIFY\_KEY  
     voms\_api.h, 27  
 VERIFY\_NONE  
     voms\_api.h, 27  
 VERIFY\_ORDER  
     voms\_api.h, 27  
 VERIFY\_SIGN  
     voms\_api.h, 27  
 VERIFY\_TARGET  
     voms\_api.h, 27  
 verify\_type

voms\_api.h, 27  
VERR\_COMM  
    voms\_api.h, 27  
VERR\_DIR  
    voms\_api.h, 27  
VERR\_EXTRAINFO  
    voms\_api.h, 27  
VERR\_FILE  
    voms\_api.h, 28  
VERR\_FORMAT  
    voms\_api.h, 27  
VERR\_IDCHECK  
    voms\_api.h, 27  
VERR\_MEM  
    voms\_api.h, 28  
VERR\_NODATA  
    voms\_api.h, 27  
VERR\_NOEXT  
    voms\_api.h, 27  
VERR\_NOIDENT  
    voms\_api.h, 27  
VERR\_NOINIT  
    voms\_api.h, 27  
VERR\_NONE  
    voms\_api.h, 27  
VERR\_NOSOCKET  
    voms\_api.h, 27  
VERR\_NOTAVAIL  
    voms\_api.h, 28  
VERR\_ORDER  
    voms\_api.h, 28  
VERR\_PARAM  
    voms\_api.h, 27  
VERR\_PARSE  
    voms\_api.h, 27  
VERR\_SERVER  
    voms\_api.h, 28  
VERR\_SERVERCODE  
    voms\_api.h, 28  
VERR\_SIGN  
    voms\_api.h, 27  
VERR\_TIME  
    voms\_api.h, 27  
VERR\_TYPE  
    voms\_api.h, 28  
VERR\_VERIFY  
    voms\_api.h, 28  
verror\_type  
    voms\_api.h, 27  
version  
    contactdata, 8  
    voms, 12  
vo  
    contactdata, 8

voms, 11  
    ~voms, 12  
    custom, 14  
    date1, 13  
    date2, 13  
    fqan, 14  
    GetAC, 12  
    GetAttributes, 12  
    GetTargets, 12  
    operator=, 12  
    serial, 14  
    server, 13  
    serverca, 13  
    siglen, 12  
    signature, 12  
    std, 13  
    TranslateVOMS, 12  
    type, 13  
    uri, 13  
    user, 12  
    userca, 13  
    version, 12  
    voms, 12  
    vomsdata, 12  
    voname, 13  
voms\_api.h  
    RECURSE\_CHAIN, 27  
    RECURSE\_DEEP, 27  
    RECURSE\_NONE, 27  
    TYPE\_CUSTOM, 26  
    TYPE\_NODATA, 26  
    TYPE\_STD, 26  
    VERIFY\_CERTLIST, 27  
    VERIFY\_DATE, 27  
    VERIFY\_FULL, 27  
    VERIFY\_ID, 27  
    VERIFY\_KEY, 27  
    VERIFY\_NONE, 27  
    VERIFY\_ORDER, 27  
    VERIFY\_SIGN, 27  
    VERIFY\_TARGET, 27  
VERR\_COMM, 27  
VERR\_DIR, 27  
VERR\_EXTRAINFO, 27  
VERR\_FILE, 28  
VERR\_FORMAT, 27  
VERR\_IDCHECK, 27  
VERR\_MEM, 28  
VERR\_NODATA, 27  
VERR\_NOEXT, 27  
VERR\_NOIDENT, 27  
VERR\_NOINIT, 27  
VERR\_NONE, 27  
VERR\_NOSOCKET, 27

VERR\_NOTAVAIL, 28  
VERR\_ORDER, 28  
VERR\_PARAM, 27  
VERR\_PARSE, 27  
VERR\_SERVER, 28  
VERR\_SERVERCODE, 28  
VERR\_SIGN, 27  
VERR\_TIME, 27  
VERR\_TYPE, 28  
VERR\_VERIFY, 28  
voms\_api.h, 25  
  check\_sig, 26  
  data\_type, 26  
  getMajorVersionNumber, 28  
  getMinorVersionNumber, 28  
  getPatchVersionNumber, 28  
  reurse\_type, 26  
  verify\_type, 27  
  verror\_type, 27  
vomsdata, 15  
  ~vomsdata, 16  
  AddTarget, 17  
  Contact, 18  
  ContactRaw, 19  
  data, 23  
  DefaultData, 20  
  error, 23  
  ErrorMessage, 20  
  Export, 20  
  extra\_data, 23  
  FindByAlias, 17  
  FindByVO, 17  
  Import, 20  
  ListTargets, 17  
  LoadCredentials, 23  
  LoadSystemContacts, 16  
  LoadUserContacts, 16  
  Order, 17  
  ResetOrder, 17  
  ResetTargets, 18  
  Retrieve, 18, 22  
  RetrieveFromCred, 21  
  RetrieveFromCtx, 21  
  RetrieveFromProxy, 22  
  ServerErrors, 18  
  SetLifetime, 20  
  SetRetryCount, 22  
  SetVerificationTime, 23  
  SetVerificationType, 20  
  voms, 12  
  vomsdata, 16  
  workvo, 23  
voname  
  voms, 13