

# globus gsi cert utils

## 5.5

Generated by Doxygen 1.5.5

Tue Aug 11 14:05:36 2009

# Contents

<b>1</b>	<b><a href="#">Globus GSI Certificate Handling Utilities</a></b>	<b>1</b>
<b>2</b>	<b><a href="#">Module Index</a></b>	<b>1</b>
<b>3</b>	<b><a href="#">Module Documentation</a></b>	<b>1</b>

## 1 Globus GSI Certificate Handling Utilities

The Globus GSI Certificate Handling Utilities library. This library contains helper functions for dealing with certificates.

- [Activation](#)
- [Cert Utils Functions](#)
- [Cert Utils Constants](#)

## 2 Module Index

### 2.1 Modules

Here is a list of all modules:

<b>Activation</b>	<b><a href="#">1</a></b>
<b>Cert Utils Functions</b>	<b><a href="#">2</a></b>
<b>Cert Utils Constants</b>	<b><a href="#">2</a></b>

## 3 Module Documentation

### 3.1 Activation

Globus GSI Cert Utils uses standard Globus module activation and deactivation.

#### Defines

- #define [GLOBUS\\_GSI\\_CERT\\_UTILS\\_MODULE](#)

#### 3.1.1 Detailed Description

Globus GSI Cert Utils uses standard Globus module activation and deactivation.

Before any Globus GSI Cert Utils functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GSI_CERT_UTILS_MODULE)
```

This function returns `GLOBUS_SUCCESS` if Globus GSI Credential was successfully initialized, and you are therefore allowed to subsequently call Globus GSI Cert Utils functions. Otherwise, an error code is returned, and Globus GSI Cert Utils functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GSI Cert Utils, the following function must be called:

```
globus_module_deactivate(GLOBUS_GSI_CERT_UTILS_MODULE)
```

This function should be called once for each time Globus GSI Cert Utils was activated.

### 3.1.2 Define Documentation

#### 3.1.2.1 #define GLOBUS\_GSI\_CERT\_UTILS\_MODULE

Module descriptor.

## 3.2 Cert Utils Functions

A generic set of utility functions for manipulating OpenSSL objects, such as X509 certificates.

### Functions

- `globus_result_t globus_gsi_cert_utils_get_eec` (`STACK_OF(X509)*cert_chain`, `X509 **eec`)

#### 3.2.1 Detailed Description

A generic set of utility functions for manipulating OpenSSL objects, such as X509 certificates.

#### 3.2.2 Function Documentation

##### 3.2.2.1 `globus_result_t globus_gsi_cert_utils_get_eec` (`STACK_OF(X509)* cert_chain`, `X509 ** eec`)

Get the end-entity certificate associated with a certificate chain.

### Parameters:

*cert\_chain* Certificate chain to inspect.

*eec* Pointer to be set to the EEC value from within the cert chain. Must freed by the caller.

## 3.3 Cert Utils Constants

### Enumerations

- enum `globus_gsi_cert_utils_error_t` {  
    `GLOBUS_GSI_CERT_UTILS_ERROR_SUCCESS` = 0,  
    `GLOBUS_GSI_CERT_UTILS_ERROR_GETTING_NAME_ENTRY_OF_SUBJECT` = 1,  
    `GLOBUS_GSI_CERT_UTILS_ERROR_COPYING_SUBJECT` = 2,  
    `GLOBUS_GSI_CERT_UTILS_ERROR_GETTING_CN_ENTRY` = 3,  
    `GLOBUS_GSI_CERT_UTILS_ERROR_ADDING_CN_TO_SUBJECT` = 4,  
    `GLOBUS_GSI_CERT_UTILS_ERROR_OUT_OF_MEMORY` = 5,  
}

```

GLOBUS_GSI_CERT_UTILS_ERROR_UNEXPECTED_FORMAT = 6,
GLOBUS_GSI_CERT_UTILS_ERROR_NON_COMPLIANT_PROXY = 7,
GLOBUS_GSI_CERT_UTILS_ERROR_DETERMINING_CERT_TYPE = 8,
GLOBUS_GSI_CERT_UTILS_ERROR_LAST = 9 }
• enum globus_gsi_cert_utils_cert_type_e {
GLOBUS_GSI_CERT_UTILS_TYPE_DEFAULT = 0,
GLOBUS_GSI_CERT_UTILS_TYPE_EEC = (1 << 0),
GLOBUS_GSI_CERT_UTILS_TYPE_CA = (1 << 1),
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2 = (1 << 2),
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3 = (1 << 3),
GLOBUS_GSI_CERT_UTILS_TYPE_RFC = (1 << 4),
GLOBUS_GSI_CERT_UTILS_TYPE_FORMAT_MASK,
GLOBUS_GSI_CERT_UTILS_TYPE_IMPERSONATION_PROXY = (1 << 5),
GLOBUS_GSI_CERT_UTILS_TYPE_LIMITED_PROXY = (1 << 6),
GLOBUS_GSI_CERT_UTILS_TYPE_RESTRICTED_PROXY = (1 << 7),
GLOBUS_GSI_CERT_UTILS_TYPE_INDEPENDENT_PROXY = (1 << 8),
GLOBUS_GSI_CERT_UTILS_TYPE_PROXY_MASK,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_IMPERSONATION_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_INDEPENDENT_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_LIMITED_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_RESTRICTED_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_LIMITED_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_IMPERSONATION_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_INDEPENDENT_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_LIMITED_PROXY,
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_RESTRICTED_PROXY }

```

### 3.3.1 Enumeration Type Documentation

#### 3.3.1.1 enum globus\_gsi\_cert\_utils\_error\_t

Cert Utils Error Codes.

##### Enumerator:

***GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_SUCCESS*** Success - never used.

***GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_NAME\_ENTRY\_OF\_SUBJECT*** Failed to retrieve a subcomponent of the subject.

***GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_COPYING\_SUBJECT*** A error occurred while trying to copy a X.509 subject.

***GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_CN\_ENTRY*** Failed to retrieve a CN subcomponent of the subject.

***GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_ADDING\_CN\_TO\_SUBJECT*** Failed to add a CN component to a X.509 subject name.

***GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_OUT\_OF\_MEMORY*** Out of memory.

***GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_UNEXPECTED\_FORMAT*** Something unexpected happen while converting a string subject to a X509\_NAME structure.

***GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_NON\_COMPLIANT\_PROXY*** Proxy does not comply with the expected format.

***GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_DETERMINING\_CERT\_TYPE*** Couldn't determine the certificate type.

***GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_LAST*** Last marker - never used.

### 3.3.1.2 enum globus\_gsi\_cert\_utils\_cert\_type\_e

Certificate Types.

These certificate types are used to describe some properties of a certificate and to specify what type of proxy should be generated in the proxy core code. There are two non-proxy types of certificates understood by Globus: EEC (End-Entity Certificate) and CA (Certificate Authority Certificates), three proxy formats (GSI 2 "legacy" proxies, GSI 3 "Draft" proxies, and RFC 3820-compliant proxies), and four types of proxy (limited, impersonation "full", restricted, and independent). The latter two types are not expressible in the GSI 2 format.

In addition to enumerations for the concrete renderings of certificate format and type combined, there are default, formats-without-types and types-without-formats so that application logic which uses the proxy library can request default proxy formats which are compatible with the issuing certificate.

#### Enumerator:

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_DEFAULT*** Default proxy type.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_EEC*** A end entity certificate.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_CA*** A CA certificate.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2*** Legacy Proxy Format.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3*** X.509 Proxy Certificate Profile (draft) Proxy Format.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC*** X.509 Proxy Certificate Profile Compliant Proxy Format.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_FORMAT\_MASK*** Proxy certificate formats mask.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_IMPERSONATION\_PROXY*** Impersonation proxy type.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_LIMITED\_PROXY*** Limited proxy type.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RESTRICTED\_PROXY*** Restricted proxy type.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_INDEPENDENT\_PROXY*** Independent proxy type.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_PROXY\_MASK*** Proxy types mask.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_IMPERSONATION\_PROXY*** A X.509 Proxy Certificate Profile (pre-RFC) compliant impersonation proxy.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_INDEPENDENT\_PROXY*** A X.509 Proxy Certificate Profile (pre-RFC) compliant independent proxy.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_LIMITED\_PROXY*** A X.509 Proxy Certificate Profile (pre-RFC) compliant limited proxy.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_RESTRICTED\_PROXY*** A X.509 Proxy Certificate Profile (pre-RFC) compliant restricted proxy.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_PROXY*** A legacy Globus impersonation proxy.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_LIMITED\_PROXY*** A legacy Globus limited impersonation proxy.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_IMPERSONATION\_PROXY*** A X.509 Proxy Certificate Profile RFC compliant impersonation proxy.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_INDEPENDENT\_PROXY*** A X.509 Proxy Certificate Profile RFC compliant independent proxy.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_LIMITED\_PROXY*** A X.509 Proxy Certificate Profile RFC compliant limited proxy.

***GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_RESTRICTED\_PROXY*** A X.509 Proxy Certificate Profile RFC compliant restricted proxy.

## Index

Activation, [1](#)

Cert Utils Constants, [2](#)

Cert Utils Functions, [2](#)

globus\_gsi\_cert\_utils\_constants

- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_-  
  ADDING\_CN\_TO\_SUBJECT, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_-  
  COPYING\_SUBJECT, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_-  
  DETERMINING\_CERT\_TYPE, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_-  
  GETTING\_CN\_ENTRY, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_-  
  GETTING\_NAME\_ENTRY\_OF\_-  
  SUBJECT, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_LAST,  
  [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_NON\_-  
  COMPLIANT\_PROXY, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_OUT\_-  
  OF\_MEMORY, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_-  
  SUCCESS, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_-  
  UNEXPECTED\_FORMAT, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_CA, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_-  
  DEFAULT, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_EEC, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_-  
  FORMAT\_MASK, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_-  
  LIMITED\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_-  
  PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_-  
  IMPERSONATION\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_-  
  INDEPENDENT\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_-  
  LIMITED\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_-  
  RESTRICTED\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_-  
  IMPERSONATION\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_-  
  INDEPENDENT\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_-  
  LIMITED\_PROXY, [4](#)

- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_PROXY\_-  
  MASK, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_-  
  RESTRICTED\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_-  
  IMPERSONATION\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_-  
  INDEPENDENT\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_-  
  LIMITED\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_-  
  RESTRICTED\_PROXY, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_ADDING\_-  
  CN\_TO\_SUBJECT  
  globus\_gsi\_cert\_utils\_constants, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_COPYING\_-  
  SUBJECT  
  globus\_gsi\_cert\_utils\_constants, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_-  
  DETERMINING\_CERT\_TYPE  
  globus\_gsi\_cert\_utils\_constants, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_-  
  CN\_ENTRY  
  globus\_gsi\_cert\_utils\_constants, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_-  
  NAME\_ENTRY\_OF\_SUBJECT  
  globus\_gsi\_cert\_utils\_constants, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_LAST  
  globus\_gsi\_cert\_utils\_constants, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_NON\_-  
  COMPLIANT\_PROXY  
  globus\_gsi\_cert\_utils\_constants, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_OUT\_OF\_-  
  MEMORY  
  globus\_gsi\_cert\_utils\_constants, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_SUCCESS  
  globus\_gsi\_cert\_utils\_constants, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_-  
  UNEXPECTED\_FORMAT  
  globus\_gsi\_cert\_utils\_constants, [3](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_CA  
  globus\_gsi\_cert\_utils\_constants, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_DEFAULT  
  globus\_gsi\_cert\_utils\_constants, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_EEC  
  globus\_gsi\_cert\_utils\_constants, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_FORMAT\_-  
  MASK  
  globus\_gsi\_cert\_utils\_constants, [4](#)
- GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2  
  globus\_gsi\_cert\_utils\_constants, [4](#)

GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_-  
     LIMITED\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_-  
     PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_-  
     IMPERSONATION\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_-  
     INDEPENDENT\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_-  
     LIMITED\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_-  
     RESTRICTED\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_-  
     IMPERSONATION\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_-  
     INDEPENDENT\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_LIMITED\_-  
     PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_PROXY\_-  
     MASK  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_-  
     RESTRICTED\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_-  
     IMPERSONATION\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_-  
     INDEPENDENT\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_-  
     LIMITED\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_-  
     RESTRICTED\_PROXY  
     globus\_gsi\_cert\_utils\_constants, 4  
 globus\_gsi\_cert\_utils  
     globus\_gsi\_cert\_utils\_get\_eec, 2  
 globus\_gsi\_cert\_utils\_activation  
     GLOBUS\_GSI\_CERT\_UTILS\_MODULE, 2  
 globus\_gsi\_cert\_utils\_cert\_type\_e  
     globus\_gsi\_cert\_utils\_constants, 3  
 globus\_gsi\_cert\_utils\_constants

    globus\_gsi\_cert\_utils\_cert\_type\_e, 3  
     globus\_gsi\_cert\_utils\_error\_t, 3  
 globus\_gsi\_cert\_utils\_error\_t  
     globus\_gsi\_cert\_utils\_constants, 3  
 globus\_gsi\_cert\_utils\_get\_eec  
     globus\_gsi\_cert\_utils, 2  
 GLOBUS\_GSI\_CERT\_UTILS\_MODULE  
     globus\_gsi\_cert\_utils\_activation, 2