

globus callout Reference Manual

0.7

Generated by Doxygen 1.4.4

Wed Aug 12 00:47:18 2009

Contents

1 Globus Callout API	1
2 globus callout Module Index	1
3 globus callout Directory Hierarchy	2
4 globus callout Module Documentation	2
5 globus callout Directory Documentation	6

1 Globus Callout API

It (hopefully) achieves this goal by providing the following functionality:

- It provides a function for reading callout configuration files. Files are assumed to have the following format:
 - Anything after a '#' is assumed to be a comment
 - Blanks lines are ignored
 - Lines specifying callouts have the format abstract type library symbol where "abstract type" denotes the type of callout, e.g. globus_gram_jobmanager_authz, "library" denotes the library the callout can be found in and "symbol" denotes the function name of the callout.
- It provides a API function for registering callouts
- All callouts are assumed to have the function signature globus_result_t callout_func(va_list ap)
- It provides a function for calling a callout given a abstract type. If multiple callouts are defined for the same abstract type then all callouts for the abstract type will be called. Implementers should not rely on any correlation between the order of configuration and the order of invocation of callouts of the same abstract type.

Any program that uses Globus Callout functions must include "globus_callout.h".

2 globus callout Module Index

2.1 globus callout Modules

Here is a list of all modules:

Activation	2
Callout Handle Operations	2
Callout Configuration	3
Callout Invocation	4
Globus Callout Constants	5

3 globus callout Directory Hierarchy

3.1 globus callout Directories

This directory hierarchy is sorted roughly, but not completely, alphabetically:

library

6

4 globus callout Module Documentation

4.1 Activation

Globus Callout API uses standard Globus module activation and deactivation.

Defines

- #define [GLOBUS_CALLOUT_MODULE](#)

4.1.1 Detailed Description

Globus Callout API uses standard Globus module activation and deactivation.

Before any Globus Callout API functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_CALLOUT_MODULE)
```

This function returns `GLOBUS_SUCCESS` if Globus Callout API was successfully initialized, and you are therefore allowed to subsequently call Globus Callout API functions. Otherwise, an error code is returned, and Globus GSI Credential functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus Callout API, the following function must be called:

```
globus_module_deactivate(GLOBUS_CALLOUT_MODULE)
```

This function should be called once for each time Globus Callout API was activated.

4.1.2 Define Documentation

4.1.2.1 #define `GLOBUS_CALLOUT_MODULE`

Module descriptor.

4.2 Callout Handle Operations

Initialize and Destroy a Globus Callout Handle structure.

Initialize Handle

- `globus_result_t` [globus_callout_handle_init](#) ([globus_callout_handle_t](#) *handle)

Destroy Handle

- globus_result_t [globus_callout_handle_destroy](#) ([globus_callout_handle_t](#) handle)

Typedefs

- typedef globus_i_callout_handle_s * [globus_callout_handle_t](#)

4.2.1 Detailed Description

Initialize and Destroy a Globus Callout Handle structure.

This section defines operations for initializing and destroying Globus Callout Handle structure.

4.2.2 Typedef Documentation

4.2.2.1 typedef struct globus_i_callout_handle_s* [globus_callout_handle_t](#)

Callout handle type definition.

4.2.3 Function Documentation

4.2.3.1 globus_result_t globus_callout_handle_init ([globus_callout_handle_t](#) * handle)

Initialize a Globus Callout Handle.

Parameters:

handle Pointer to the handle that is to be initialized

Returns:

GLOBUS_SUCCESS if successful A Globus error object on failure: GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE

4.2.3.2 globus_result_t globus_callout_handle_destroy ([globus_callout_handle_t](#) handle)

Destroy a Globus Callout Handle.

Parameters:

handle The handle that is to be destroyed

Returns:

GLOBUS_SUCCESS

4.3 Callout Configuration

Functions for registering callouts.

Configure Callouts

- globus_result_t [globus_callout_read_config](#) ([globus_callout_handle_t](#) handle, char *filename)
- globus_result_t [globus_callout_register](#) ([globus_callout_handle_t](#) handle, char *type, char *library, char *symbol)

4.3.1 Detailed Description

Functions for registering callouts.

This section defines operations for registering callouts. Callouts may be registered either through a configuration file or through calls to `globus_callout_register`.

4.3.2 Function Documentation

4.3.2.1 `globus_result_t globus_callout_read_config (globus_callout_handle_t handle, char * filename)`

Read callout configuration from file.

This function read a configuration file with the following format:

- Anything after a '#' is assumed to be a comment
- Blanks lines are ignored
- Lines specifying callouts have the format abstract type library symbol where "abstract type" denotes the type of callout, e.g. `globus_gram_jobmanager_authz`, "library" denotes the library the callout can be found in and "symbol" denotes the function name of the callout. The library argument can be specified in two forms, `libfoo` or `libfoo_<flavor>`. When using the former version the current flavor will automatically be added to the library name.

Parameters:

handle The handle that is to be configured

filename The file to read configuration from

Returns:

GLOBAL_SUCCESS A Globus error object on failure: GLOBAL_CALLOUT_ERROR_OPENING_CONF_FILE GLOBAL_CALLOUT_ERROR_PARSING_CONF_FILE GLOBAL_CALLOUT_ERROR_WITH_HASHTABLE GLOBAL_CALLOUT_ERROR_OUT_OF_MEMORY

4.3.2.2 `globus_result_t globus_callout_register (globus_callout_handle_t handle, char * type, char * library, char * symbol)`

Register callout configuration

This function registers a callout type in the given handle.

Parameters:

handle The handle that is to be configured

type The abstract type of the callout

library The location of the library containing the callout

symbol The symbol (ie function name) for the callout

Returns:

GLOBAL_SUCCESS A Globus error object on failure: GLOBAL_CALLOUT_ERROR_WITH_HASHTABLE GLOBAL_CALLOUT_ERROR_OUT_OF_MEMORY

4.4 Callout Invocation

Functions for invoking callouts.

Invoking Callouts

- `globus_result_t globus_callout_call_type (globus_callout_handle_t handle, char *type,...)`

Typedefs

- `typedef globus_result_t(* globus_callout_function_t)(va_list ap)`

4.4.1 Detailed Description

Functions for invoking callouts.

This section defines a operation for invoking callouts by their abstract type.

4.4.2 Typedef Documentation

4.4.2.1 `typedef globus_result_t(* globus_callout_function_t)(va_list ap)`

Callout function type definition.

4.4.3 Function Documentation

4.4.3.1 `globus_result_t globus_callout_call_type (globus_callout_handle_t handle, char * type, ...)`

Call a callout of specified abstract type

This function looks up the callouts corresponding to the given type and invokes them with the passed arguments.

If a invoked callout returns an error it will be chained to a error of the type `GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR` and no more callouts will be called.

Parameters:

handle A configured callout handle

type The abstract type of the callout that is to be invoked

Returns:

`GLOBUS_SUCCESS` A Globus error object on failure: `GLOBUS_CALLOUT_ERROR_TYPE_NOT_REGISTERED` `GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR` `GLOBUS_CALLOUT_ERROR_WITH_DL` `GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE` `GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY`

4.5 Globus Callout Constants

Enumerations

- `enum globus_callout_error_t {`
 `GLOBUS_CALLOUT_ERROR_SUCCESS = 0,`
 `GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE = 1,`
 `GLOBUS_CALLOUT_ERROR_OPENING_CONF_FILE = 2,`
 `GLOBUS_CALLOUT_ERROR_PARSING_CONF_FILE = 3,`
 `GLOBUS_CALLOUT_ERROR_WITH_DL = 4,`
 `GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY = 5,`

```

GLOBUS_CALLOUT_ERROR_TYPE_NOT_REGISTERED = 6,
GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR = 7,
GLOBUS_CALLOUT_ERROR_LAST = 8 }

```

4.5.1 Enumeration Type Documentation

4.5.1.1 enum `globus_callout_error_t`

Globus Callout Error codes.

Enumerator:

GLOBUS_CALLOUT_ERROR_SUCCESS Success - never used.

GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE Hash table operation failed.

GLOBUS_CALLOUT_ERROR_OPENING_CONF_FILE Failed to open configuration file.

GLOBUS_CALLOUT_ERROR_PARSING_CONF_FILE Failed to parse configuration file.

GLOBUS_CALLOUT_ERROR_WITH_DL Dynamic library operation failed.

GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY Out of memory.

GLOBUS_CALLOUT_ERROR_TYPE_NOT_REGISTERED The abstract type could not be found.

GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR The callout itself returned a error.

GLOBUS_CALLOUT_ERROR_LAST Last marker - never used.

5 globus callout Directory Documentation

5.1 `/builddir/build/BUILD/globus_callout-0.7/library/` Directory Reference



Files

- file `globus_callout.c`
- file `globus_callout.h`
- file `globus_callout_constants.h`
- file `globus_callout_error.c`
- file `globus_i_callout.h`

Index

- /builddir/build/BUILD/globus_callout-0.7/library/ Directory Reference, [6](#)
- Activation, [2](#)
- Callout Configuration, [3](#)
- Callout Handle Operations, [2](#)
- Callout Invocation, [4](#)
- Globus Callout Constants, [5](#)
- globus_callout_activation
 - GLOBUS_CALLOUT_MODULE, [2](#)
- globus_callout_call
 - globus_callout_call_type, [5](#)
 - globus_callout_function_t, [5](#)
- globus_callout_call_type
 - globus_callout_call, [5](#)
- globus_callout_config
 - globus_callout_read_config, [4](#)
 - globus_callout_register, [4](#)
- globus_callout_constants
 - GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR, [6](#)
 - GLOBUS_CALLOUT_ERROR_LAST, [6](#)
 - GLOBUS_CALLOUT_ERROR_OPENING_CONF_FILE, [6](#)
 - GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY, [6](#)
 - GLOBUS_CALLOUT_ERROR_PARSING_CONF_FILE, [6](#)
 - GLOBUS_CALLOUT_ERROR_SUCCESS, [6](#)
 - GLOBUS_CALLOUT_ERROR_TYPE_NOT_REGISTERED, [6](#)
 - GLOBUS_CALLOUT_ERROR_WITH_DL, [6](#)
 - GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE, [6](#)
- globus_callout_constants
 - globus_callout_error_t, [6](#)
- GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR
 - globus_callout_constants, [6](#)
- GLOBUS_CALLOUT_ERROR_LAST
 - globus_callout_constants, [6](#)
- GLOBUS_CALLOUT_ERROR_OPENING_CONF_FILE
 - globus_callout_constants, [6](#)
- GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY
 - globus_callout_constants, [6](#)
- GLOBUS_CALLOUT_ERROR_PARSING_CONF_FILE
 - globus_callout_constants, [6](#)
- GLOBUS_CALLOUT_ERROR_SUCCESS
 - globus_callout_constants, [6](#)
- globus_callout_error_t
 - globus_callout_constants, [6](#)
- GLOBUS_CALLOUT_ERROR_TYPE_NOT_REGISTERED
 - globus_callout_constants, [6](#)
- GLOBUS_CALLOUT_ERROR_WITH_DL
 - globus_callout_constants, [6](#)
- GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE
 - globus_callout_constants, [6](#)
- globus_callout_function_t
 - globus_callout_call, [5](#)
- globus_callout_handle
 - globus_callout_handle_destroy, [3](#)
 - globus_callout_handle_init, [3](#)
 - globus_callout_handle_t, [3](#)
- globus_callout_handle_destroy
 - globus_callout_handle, [3](#)
- globus_callout_handle_init
 - globus_callout_handle, [3](#)
- globus_callout_handle_t
 - globus_callout_handle, [3](#)
- GLOBUS_CALLOUT_MODULE
 - globus_callout_activation, [2](#)
- globus_callout_read_config
 - globus_callout_config, [4](#)
- globus_callout_register
 - globus_callout_config, [4](#)