

globus openssl module Reference Manual

1.3

Generated by Doxygen 1.4.4

Wed Jul 21 13:49:45 2010

Contents

1 Globus OpenSSL activation/deactivation	1
2 globus openssl module Module Index	1
3 globus openssl module Directory Hierarchy	1
4 globus openssl module Module Documentation	1
5 globus openssl module Directory Documentation	2

1 Globus OpenSSL activation/deactivation

This is done by allocating a mutex pool and setting relevant callback functions in the module activation functions. Any program that uses OpenSSL functions must include "globus_openssl.h".

2 globus openssl module Module Index

2.1 globus openssl module Modules

Here is a list of all modules:

Activation	1
-------------------	-------------------

3 globus openssl module Directory Hierarchy

3.1 globus openssl module Directories

This directory hierarchy is sorted roughly, but not completely, alphabetically:

library	2
----------------	-------------------

4 globus openssl module Module Documentation

4.1 Activation

Globus OpenSSL uses standard Globus module activation and deactivation.

Defines

- `#define GLOBUS_OPENSSL_MODULE`

4.1.1 Detailed Description

Globus OpenSSL uses standard Globus module activation and deactivation.

Before any OpenSSL functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_OPENSSL_MODULE)
```

This function returns `GLOBUS_SUCCESS` if OpenSSL was successfully initialized, and you are therefore allowed to subsequently call OpenSSL functions. Otherwise, an error code is returned, and OpenSSL functions should not subsequently be called. This function may be called multiple times.

To deactivate the OpenSSL module, the following function must be called:

```
globus_module_deactivate(GLOBUS_OPENSSL_MODULE)
```

This function should be called once for each time OpenSSL was activated.

4.1.2 Define Documentation

4.1.2.1 `#define GLOBUS_OPENSSL_MODULE`

Module descriptor.

5 globus openssl module Directory Documentation

5.1 `/builddir/build/BUILD/globus_openssl_module-1.3/library/` Directory Reference



library

Files

- file `globus_openssl.c`
- file `globus_openssl.h`

Index

/builddir/build/BUILD/globus_openssl_module-
1.3/library/ Directory Reference, [2](#)

Activation, [1](#)

globus_openssl_activation
 GLOBUS_OPENSSL_MODULE, [2](#)
GLOBUS_OPENSSL_MODULE
 globus_openssl_activation, [2](#)