

**globus gram job manager callout error Reference Manual**  
0.2

Generated by Doxygen 1.4.6

Sat Feb 6 12:12:32 2010

# Contents

<b>1 globus gram job manager callout error Module Index</b>	<b>1</b>
<b>2 globus gram job manager callout error Module Documentation</b>	<b>1</b>

## 1 globus gram job manager callout error Module Index

### 1.1 globus gram job manager callout error Modules

Here is a list of all modules:

<b>Activation</b>	<b>1</b>
<b>Datatypes</b>	<b>2</b>

## 2 globus gram job manager callout error Module Documentation

### 2.1 Activation

Globus GRAM Jobmanager Callout Error API uses standard Globus module activation and deactivation.

#### Defines

- #define GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_ERROR\_MODULE

#### 2.1.1 Detailed Description

Globus GRAM Jobmanager Callout Error API uses standard Globus module activation and deactivation.

Before any Globus GRAM Jobmanager Callout Error API functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE)
```

This function returns GLOBUS\_SUCCESS if the Globus GRAM Jobmanager Callout Error API was successfully initialized, and you are therefore allowed to subsequently call Globus GRAM Jobmanager Callout Error API functions. Otherwise, an error code is returned, and Globus GSI Credential functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GRAM Jobmanager Callout Error API, the following function must be called:

```
globus_module_deactivate(GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE)
```

This function should be called once for each time Globus GRAM Jobmanager Callout Error API was activated.

#### 2.1.2 Define Documentation

##### 2.1.2.1 #define GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_ERROR\_MODULE

Module descriptor.

## 2.2 Datatypes

### Enumerations

- enum `globus_gram_jobmanager_callout_error_t` {  
    *GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_BAD\_CREDS* = 0,  
    *GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_AUTHZ\_SYSTEM\_ERROR* = 1,  
    *GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_AUTHZ\_DENIED* = 2,  
    *GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_AUTHZ\_DENIED\_INVALID\_JOB* = 3,  
    *GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_AUTHZ\_DENIED\_BAD\_EXECUTABLE* = 4,  
    *GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_ERROR\_LAST* = 5 }

#### 2.2.1 Enumeration Type Documentation

##### 2.2.1.1 enum `globus_gram_jobmanager_callout_error_t`

GRAM Jobmanager Callout Error codes.

###### Enumerator:

*GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_BAD\_CREDS* Credentials not accepted.

*GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_AUTHZ\_SYSTEM\_ERROR* Authorization system mis-configured.

*GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_AUTHZ\_DENIED* Authorization denied.

*GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_AUTHZ\_DENIED\_INVALID\_JOB* Authorization denied - invalid job id.

*GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_AUTHZ\_DENIED\_BAD\_EXECUTABLE* Authorization denied - executable not allowed.

*GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_ERROR\_LAST* Last marker - never used.

# Index

Activation, 1  
Datatypes, 2

GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_-  
    AUTHZ\_DENIED  
        globus\_gram\_jobmanager\_callout\_error\_-  
            datatypes, 2  
GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_-  
    AUTHZ\_DENIED\_BAD\_EXECUTABLE  
        globus\_gram\_jobmanager\_callout\_error\_-  
            datatypes, 2  
GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_-  
    AUTHZ\_DENIED\_INVALID\_JOB  
        globus\_gram\_jobmanager\_callout\_error\_-  
            datatypes, 2  
GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_-  
    AUTHZ\_SYSTEM\_ERROR  
        globus\_gram\_jobmanager\_callout\_error\_-  
            datatypes, 2  
GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_-  
    BAD\_CREDS  
        globus\_gram\_jobmanager\_callout\_error\_-  
            datatypes, 2  
globus\_gram\_jobmanager\_callout\_error\_activation  
    GLOBUS\_GRAM\_JOBMANAGER\_-  
        CALLOUT\_ERROR\_MODULE, 1  
globus\_gram\_jobmanager\_callout\_error\_datatypes  
    GLOBUS\_GRAM\_JOBMANAGER\_-  
        CALLOUT\_AUTHZ\_DENIED, 2  
    GLOBUS\_GRAM\_JOBMANAGER\_-  
        CALLOUT\_AUTHZ\_DENIED\_BAD\_-  
            EXECUTABLE, 2  
    GLOBUS\_GRAM\_JOBMANAGER\_-  
        CALLOUT\_AUTHZ\_DENIED\_INVALID\_-  
            JOB, 2  
    GLOBUS\_GRAM\_JOBMANAGER\_-  
        CALLOUT\_AUTHZ\_SYSTEM\_ERROR,  
            2  
    GLOBUS\_GRAM\_JOBMANAGER\_-  
        CALLOUT\_BAD\_CREDS, 2  
    GLOBUS\_GRAM\_JOBMANAGER\_-  
        CALLOUT\_ERROR\_LAST, 2  
globus\_gram\_jobmanager\_callout\_error\_datatypes  
    globus\_gram\_jobmanager\_callout\_error\_t, 2  
GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_-  
    ERROR\_LAST  
        globus\_gram\_jobmanager\_callout\_error\_-  
            datatypes, 2  
GLOBUS\_GRAM\_JOBMANAGER\_CALLOUT\_-  
    ERROR\_MODULE  
        globus\_gram\_jobmanager\_callout\_error\_-  
            activation, 1

globus\_gram\_jobmanager\_callout\_error\_t  
    globus\_gram\_jobmanager\_callout\_error\_-  
        datatypes, 2