

ARC::DataMove Reference Manual

Generated by Doxygen 1.3.5

Mon Mar 15 19:05:59 2004

Contents

1	ARC::DataMove Hierarchical Index	1
1.1	ARC::DataMove Class Hierarchy	1
2	ARC::DataMove Class Index	3
2.1	ARC::DataMove Class List	3
3	ARC::DataMove Class Documentation	5
3.1	DataBufferPar Class Reference	5
3.2	DataCache Class Reference	11
3.3	DataCallback Class Reference	15
3.4	DataHandle Class Reference	16
3.5	DataMove Class Reference	20
3.6	DataMovePar Class Reference	25
3.7	DataPoint Class Reference	27
3.8	DataPoint::FileInfo Class Reference	34
3.9	DataPoint::Location Class Reference	36
3.10	DataSpeed Class Reference	37

Chapter 1

ARC::DataMove Hierarchical Index

1.1 ARC::DataMove Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

DataBuffer	
DataBufferPar	5
DataCallback	15
DataCache	11
DataHandle	16
DataMove	20
DataMovePar	25
DataPoint	27
DataPoint::FileInfo	34
DataPoint::Location	36
DataSpeed	37

Chapter 2

ARC::DataMove Class Index

2.1 ARC::DataMove Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

DataBufferPar	5
DataCache	11
DataCallback	15
DataHandle	16
DataMove	20
DataMovePar (Wrapper around DataMove class to handle few transfers at once)	25
DataPoint	27
DataPoint::FileInfo	34
DataPoint::Location	36
DataSpeed	37

Chapter 3

ARC::DataMove Class Documentation

3.1 DataBufferPar Class Reference

```
#include <databufferpar.h>
```

Public Member Functions

- [operator bool](#) (void)
- [DataBufferPar](#) (unsigned int size=65536, int blocks=3)
- [DataBufferPar](#) (Checksum *cksum, unsigned int size=65536, int blocks=3)
- [~DataBufferPar](#) (void)
- [bool set](#) (Checksum *cksum=NULL, unsigned int size=65536, int blocks=3)
- [char * operator\[\]](#) (int n)
- [bool for_read](#) (int &handle, unsigned int &length, bool wait)
- [bool is_read](#) (int handle, unsigned int length, unsigned long long int offset)
- [bool is_read](#) (char *buf, unsigned int length, unsigned long long int offset)
- [bool for_write](#) (int &handle, unsigned int &length, unsigned long long int &offset, bool wait)
- [bool is_written](#) (int handle)
- [bool is_written](#) (char *buf)
- [bool is_notwritten](#) (int handle)
- [bool is_notwritten](#) (char *buf)
- [void eof_read](#) (bool v)
- [void eof_write](#) (bool v)
- [void error_read](#) (bool v)
- [void error_write](#) (bool v)
- [bool eof_read](#) (void)
- [bool eof_write](#) (void)
- [bool error_read](#) (void)
- [bool error_write](#) (void)
- [bool error_transfer](#) (void)
- [bool error](#) (void)
- [bool wait](#) (void)
- [bool wait_used](#) (void)
- [bool checksum_valid](#) (void)
- [const CheckSum * checksum_object](#) (void)

- bool [wait_eof_read](#) (void)
- bool [wait_eof_write](#) (void)
- bool [wait_eof](#) (void)
- unsigned long long int [eof_position](#) (void) const
- unsigned int [buffer_size](#) (void)

Public Attributes

- [DataSpeed](#) [speed](#)

3.1.1 Detailed Description

This class represents set of buffers used during data transfer.

3.1.2 Constructor & Destructor Documentation

3.1.2.1 `DataBufferPar::DataBufferPar (unsigned int size = 65536, int blocks = 3)`

Constructor

Parameters:

- size* size of every buffer in bytes.
- blocks* number of buffers.

3.1.2.2 `DataBufferPar::DataBufferPar (Checksum * cksum, unsigned int size = 65536, int blocks = 3)`

Constructor

Parameters:

- size* size of every buffer in bytes.
- blocks* number of buffers.
- cksum* object which will compute checksum. Should not be destroyed till DataBufferPar itself.

3.1.2.3 `DataBufferPar::~DataBufferPar (void)`

Destructor.

3.1.3 Member Function Documentation

3.1.3.1 `unsigned int DataBufferPar::buffer_size (void)`

Returns size of buffer in object. If not initialized then this number represents size of default buffer.

3.1.3.2 `const CheckSum* DataBufferPar::checksum_object (void)`

Returns CheckSum object specified in constructor.

3.1.3.3 bool DataBufferPar::checksum_valid (void)

Returns true if checksum was successfully computed.

3.1.3.4 unsigned long long int DataBufferPar::eof_position (void) const [inline]

Returns offset following last piece of data transfered.

3.1.3.5 bool DataBufferPar::eof_read (void)

Returns true if object was informed about end of transfer on 'read' side.

3.1.3.6 void DataBufferPar::eof_read (bool v)

Informs object if there will be no more request for 'read' buffers. v true if no more requests.

3.1.3.7 bool DataBufferPar::eof_write (void)

Returns true if object was informed about end of transfer on 'write' side.

3.1.3.8 void DataBufferPar::eof_write (bool v)

Informs object if there will be no more request for 'write' buffers. v true if no more requests.

3.1.3.9 bool DataBufferPar::error (void)

Returns true if object was informed about error or internal error occurred.

3.1.3.10 bool DataBufferPar::error_read (void)

Returns true if object was informed about error on 'read' side.

3.1.3.11 void DataBufferPar::error_read (bool v)

Informs object if error occurred on 'read' side.

Parameters:

v true if error.

3.1.3.12 bool DataBufferPar::error_transfer (void)

Returns true if error occurred inside object.

3.1.3.13 bool DataBufferPar::error_write (void)

Returns true if object was informed about error on 'write' side.

3.1.3.14 void DataBufferPar::error_write (bool *v*)

Informs object if error accured on 'write' side.

Parameters:

v true if error.

3.1.3.15 bool DataBufferPar::for_read (int & *handle*, unsigned int & *length*, bool *wait*)

Request buffer for READING INTO it.

Parameters:

handle returns buffer's number.

length returns size of buffer

wait if true and there are no free buffers, method will wait for one. Returns true on success

3.1.3.16 bool DataBufferPar::for_write (int & *handle*, unsigned int & *length*, unsigned long long int & *offset*, bool *wait*)

Request buffer for WRITING FROM it.

Parameters:

handle returns buffer's number.

length returns size of buffer

wait if true and there are no free buffers, method will wait for one.

3.1.3.17 bool DataBufferPar::is_notwritten (char * *buf*)

Informs object that data was NOT written from buffer (and releases buffer).

Parameters:

buf - address of buffer

3.1.3.18 bool DataBufferPar::is_notwritten (int *handle*)

Informs object that data was NOT written from buffer (and releases buffer).

Parameters:

handle buffer's number.

3.1.3.19 bool DataBufferPar::is_read (char * *buf*, unsigned int *length*, unsigned long long int *offset*)

Informs object that data was read into buffer.

Parameters:

buf - address of buffer

length amount of data.

offset offset in stream, file, etc.

3.1.3.20 bool DataBufferPar::is_read (int *handle*, unsigned int *length*, unsigned long long int *offset*)

Informs object that data was read into buffer.

Parameters:

handle buffer's number.
length amount of data.
offset offset in stream, file, etc.

3.1.3.21 bool DataBufferPar::is_written (char * *buf*)

Informs object that data was written from buffer.

Parameters:

buf - address of buffer

3.1.3.22 bool DataBufferPar::is_written (int *handle*)

Informs object that data was written from buffer.

Parameters:

handle buffer's number.

3.1.3.23 DataBufferPar::operator bool (void) [inline]

Check if DataBufferPar object is initialized.

3.1.3.24]

char* DataBufferPar::operator[] (int *n*)

Direct access to buffer by number.

3.1.3.25 bool DataBufferPar::set (Checksum * *cksum* = NULL, unsigned int *size* = 65536, int *blocks* = 3)

Reinitialize buffers with different parameters.

Parameters:

size size of every buffer in bytes.
blocks number of buffers.
cksum object which will compute checksum. Should not be destroyed till DataBufferPar itself.

3.1.3.26 bool DataBufferPar::wait (void)

Wait (max 60 sec.) till any action happens in object. Returns true if action is eof on any side.

3.1.3.27 bool DataBufferPar::wait_eof (void)

Wait till end of transfer happens on any side.

3.1.3.28 bool DataBufferPar::wait_eof_read (void)

Wait till end of transfer happens on 'read' side.

3.1.3.29 bool DataBufferPar::wait_eof_write (void)

Wait till end of transfer happens on 'write' side.

3.1.3.30 bool DataBufferPar::wait_used (void)

Wait till there are no more used buffers left in object.

3.1.4 Member Data Documentation**3.1.4.1 [DataSpeed DataBufferPar::speed](#)**

This object controls transfer speed.


The documentation for this class was generated from the following file:

- databufferpar.h

3.2 DataCache Class Reference

```
#include <datacache.h>
```

Inheritance diagram for DataCache::



Public Member Functions

- [DataCache](#) (void)
- [DataCache](#) (const char *cache_path, const char *cache_data_path, const char *cache_link_path, const char *id, uid_t cache_uid, gid_t cache_gid)
- [DataCache](#) (const [DataCache](#) &cache)
- [~DataCache](#) (void)
- bool [start](#) (const char *base_url, bool &available)
- const string & [file](#) (void) const
- bool [stop](#) (bool failure, bool invalidate)
- bool [link](#) (const char *link_path)
- bool [link](#) (const char *link_path, uid_t uid, gid_t gid)
- bool [clean](#) (unsigned long long int size=1)
- virtual bool [cb](#) (unsigned long long int size)
- [operator bool](#) (void)
- bool [created_available](#) (void)
- void [created](#) (time_t val)
- void [created_force](#) (time_t val)
- time_t [created](#) (void)
- bool [validtill_available](#) (void)
- time_t [validtill](#) (void)
- void [validtill_force](#) (time_t val)
- void [validtill](#) (time_t val)

3.2.1 Detailed Description

High level interface to cache operations (same functionality :)) and additional functionality to integrate into grid-manager environment.

3.2.2 Constructor & Destructor Documentation

3.2.2.1 DataCache::DataCache (void)

Default constructor (non-functional cache).

3.2.2.2 DataCache::DataCache (const char * *cache_path*, const char * *cache_data_path*, const char * *cache_link_path*, const char * *id*, uid_t *cache_uid*, gid_t *cache_gid*)

Constructor

Parameters:

- cache_path* path to directory with cache info files
- cache_data_path* path to directory with cache data files
- cache_link_path* path used to create link in case *cache_directory* is visible under different name during actual usage
- id* identifier used to claim files in cache
- cache_uid* owner of cache (0 for public cache)
- cache_gid* owner group of cache (0 for public cache)

3.2.2.3 DataCache::DataCache (const DataCache & *cache*)

Copy constructor.

3.2.2.4 DataCache::~DataCache (void)

and destructor

3.2.3 Member Function Documentation

3.2.3.1 virtual bool DataCache::cb (unsigned long long int *size*) [virtual]

Callback implementation to clean at least 1 byte.

Reimplemented from [DataCallback](#).

3.2.3.2 bool DataCache::clean (unsigned long long int *size* = 1)

Remove some amount of oldest information from cache. Returns true on success.

Parameters:

- size* amount to be removed (bytes)

3.2.3.3 time_t DataCache::created (void) [inline]

Get creation time.

3.2.3.4 void DataCache::created (time_t *val*) [inline]

Set creation time (if not already set).

Parameters:

- val* creation time

3.2.3.5 bool DataCache::created_available (void) [inline]

Check if there is an information about creation time.

3.2.3.6 void DataCache::created_force (time_t val) [inline]

Set creation time (even if already set).

Parameters:

val creation time

3.2.3.7 const string& DataCache::file (void) const [inline]

Returns path to file which contains/will contain content of assigned url.

3.2.3.8 bool DataCache::link (const char * link_path, uid_t uid, gid_t gid)**Parameters:**

uid set owner of soft-link to uid

gid set group of soft-link to gid

3.2.3.9 bool DataCache::link (const char * link_path)

Must be called to create soft-link to cache file. All nessary directories will be created. Returns false on error (usually that means soft-link already exists).

Parameters:

link_path path for soft-link.

3.2.3.10 DataCache::operator bool (void) [inline]

Returns true of object is useable.

3.2.3.11 bool DataCache::start (const char * base_url, bool & available)

Prepare cache for downloading file. On success returns true. This function can block for long time if there is another process downloading same url.

Parameters:

base_url url to assign to file in cache (file's identifier)

available contains true on exit if file is already in cache

3.2.3.12 bool DataCache::stop (bool failure, bool invalidate)

This method must be called after file was downloaded or download failed.

Parameters:

failure true if download failed

3.2.3.13 void DataCache::validtill (time_t *val*) [inline]

Get invalidation time.

3.2.3.14 time_t DataCache::validtill (void) [inline]

Set invalidation time (if not already set).

Parameters:

val validity time

3.2.3.15 bool DataCache::validtill_available (void) [inline]

Check if there is an information about invalidation time.

3.2.3.16 void DataCache::validtill_force (time_t *val*) [inline]

Set invalidation time (even if already set).

Parameters:

val validity time


The documentation for this class was generated from the following file:

- datacache.h

3.3 DataCallback Class Reference

```
#include <datacallback.h>
```

Inheritance diagram for DataCallback::



Public Member Functions

- virtual bool **cb** (int)
- virtual bool **cb** (unsigned int)
- virtual bool **cb** (long long int)
- virtual bool **cb** (unsigned long long int)

3.3.1 Detailed Description

This class is used by [DataHandle](#) to report missing space on local filesystem. One of 'cb' functions here will be called if operation initiated by [DataHandle::start_reading](#) runs out of disk space.

The documentation for this class was generated from the following file:

- datacallback.h

3.4 DataHandle Class Reference

```
#include <datahandle.h>
```

Public Types

- enum [failure_reason_t](#) { `common_failure` = 0, `credentials_expired_failure` = 1 }

Public Member Functions

- [DataHandle](#) ([DataPoint](#) *url_)
- [~DataHandle](#) (void)
- bool [start_reading](#) ([DataBufferPar](#) &buffer)
- bool [start_writing](#) ([DataBufferPar](#) &buffer, [DataCallback](#) *space_cb=NULL)
- bool [stop_reading](#) (void)
- bool [stop_writing](#) (void)
- bool [analyze](#) (long int *bufsize, int *bufnum, bool *cache, bool *local)
- bool [check](#) (void)
- bool [remove](#) (void)
- bool [list_files](#) (list< [DataPoint::FileInfo](#) > &files, bool resolve=true)
- bool [out_of_order](#) (void)
- void [out_of_order](#) (bool v)
- void [additional_checks](#) (bool v)
- bool [additional_checks](#) (void)
- void [secure](#) (bool v)
- bool [secure](#) (void)
- void [passive](#) (bool v)
- [failure_reason_t](#) [failure_reason](#) (void)

3.4.1 Detailed Description

DataHandle is kind of generalized file handle. Differently from file handle it does not support operations `read()` and `write()`. Instead it initiates operation and uses object of class [DataBufferPar](#) to pass actual data. It also provides other operations like querying parameters of remote object. It is used by higher-level classes [DataMove](#) and [DataMovePar](#) to provide data transfer service for application.

3.4.2 Member Enumeration Documentation

3.4.2.1 enum [DataHandle::failure_reason_t](#)

Reason of transfer failure.

3.4.3 Constructor & Destructor Documentation

3.4.3.1 [DataHandle::DataHandle](#) ([DataPoint](#) * url_)

Constructor

Parameters:

url_ URL. Should not be destroyed before DataHandle itself.

3.4.3.2 DataHandle::~~DataHandle (void)

Destructor. No comments.

3.4.4 Member Function Documentation**3.4.4.1 bool DataHandle::additional_checks (void) [inline]**

Check if additional checks before 'reading' and 'writing' will be performed.

3.4.4.2 void DataHandle::additional_checks (bool v) [inline]

Allow/disallow to make check for existence of remote file (and probably other checks too) before initiating 'reading' and 'writing' operations.

Parameters:

v true if allowed (default is true).

3.4.4.3 bool DataHandle::analyze (long int * bufsize, int * bufnum, bool * cache, bool * local)

Analyze url and provide hints.

Parameters:

bufsize returns suggested size of buffers to store data.

bufnum returns suggested number of buffers.

cache returns true if url is allowed to be cached.

local return true if URL is accessed locally ([file://](#))

3.4.4.4 bool DataHandle::check (void)

Query remote server or local file system to check if object is accessible.

3.4.4.5 failure_reason_t DataHandle::failure_reason (void) [inline]

Returns reason of transfer failure.

3.4.4.6 bool DataHandle::list_files (list< DataPoint::FileInfo > & files, bool resolve = true)

List files in directory (URL must point to directory/group).

Parameters:

files will contain list of file names and optionally their attributes.

resolve if false no information about attributes will be retrieved.

3.4.4.7 void DataHandle::out_of_order (bool *v*)

Allow/disallow DataHandle to produce scattered data during 'reading' operation.

Parameters:

v true if allowed.

3.4.4.8 bool DataHandle::out_of_order (void)

Returns true if URL can accept scattered data (like arbitrary access to local file) for 'writing' operation.

3.4.4.9 void DataHandle::passive (bool *v*)

Request passive transfers for FTP-like protocols.

Parameters:

true to request.

3.4.4.10 bool DataHandle::remove (void)

Remove/delete object at URL.

3.4.4.11 bool DataHandle::secure (void)

Check if heavy security during data transfer is allowed.

3.4.4.12 void DataHandle::secure (bool *v*)

Allow/disallow heavy security during data transfer.

Parameters:

v true if allowed (default is true only for gsiftp://).

3.4.4.13 bool DataHandle::start_reading ([DataBufferPar](#) & *buffer*)

Start reading data from URL. Separate thread to transfer data will be created. No other operation can be performed while 'reading' is in progress.

Parameters:

buffer operation will use this buffer to put information into. Should not be destroyed before stop_reading was called and returned. Returns true on success.

3.4.4.14 bool DataHandle::start_writing ([DataBufferPar](#) & *buffer*, [DataCallback](#) * *space_cb* = NULL)

Start writing data to URL. Separate thread to transfer data will be created. No other operation can be performed while 'writing' is in progress.

Parameters:

buffer operation will use this buffer to get information from. Should not be destroyed before stop_writing was called and returned. space_cb callback which is called if there is not enough to space storing data. Currently implemented only for [file:///](#) URL. Returns true on success.

3.4.4.15 bool DataHandle::stop_reading (void)

Stop reading. It MUST be called after corresponding start_reading method. Either after whole data is transfered or to cancel transfer. Use 'buffer' object to find out when data is transfered.

3.4.4.16 bool DataHandle::stop_writing (void)

Same as stop_reading but for corresponding start_writing.


The documentation for this class was generated from the following file:

- datahandle.h

3.5 DataMove Class Reference

```
#include <datamove.h>
```

Inheritance diagram for DataMove::



Public Types

- typedef void(* **callback**)(DataMove *, DataMove::result, void *)
- enum **result** {
 success = 0, **read_acquire_error** = 1, **write_acquire_error** = 2, **read_resolve_error** = 3,
 write_resolve_error = 4, **preregister_error** = 5, **read_start_error** = 6, **write_start_error** = 7,
 read_error = 8, **write_error** = 9, **transfer_error** = 10, **read_stop_error** = 11,
 write_stop_error = 12, **postregister_error** = 13, **cache_error** = 14, **system_error** = 15,
 credentials_expired_error = 16, **undefined_error** = -1 }

Public Member Functions

- **DataMove** (void)
- **~DataMove** (void)
- **result Transfer** (DataPoint &source, DataPoint &destination, DataCache &cache, const UriMap &map, callback cb=NULL, void *arg=NULL, const char *prefix=NULL)
- **result Transfer** (DataPoint &source, DataPoint &destination, DataCache &cache, const UriMap &map, unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, callback cb=NULL, void *arg=NULL, const char *prefix=NULL)
- bool **verbose** (void)
- void **verbose** (bool)
- void **verbose** (const string &prefix)
- bool **retry** (void)
- void **retry** (bool)
- void **secure** (bool)
- void **passive** (bool)
- void **force_to_meta** (bool)
- bool **checks** (void)
- void **checks** (bool v)
- void **set_default_min_speed** (unsigned long long int min_speed, time_t min_speed_time)
- void **set_default_min_average_speed** (unsigned long long int min_average_speed)
- void **set_default_max_inactivity_time** (time_t max_inactivity_time)

3.5.1 Detailed Description

A purpose of this class is to provide service for moves data between 2 locations specified by URLs. It's main action is represented by methods [DataMove::Transfer](#).

3.5.2 Member Enumeration Documentation

3.5.2.1 enum [DataMove::result](#)

Error code/failure reason.

Enumeration values:

- success* Operation completed successfully.
- read_acquire_error* Source is bad URL or can't be used due to some reason.
- write_acquire_error* Destination is bad URL or can't be used due to some reason.
- read_resolve_error* Resolving of meta-URL for source failed.
- write_resolve_error* Resolving of meta-URL for destination failed.
- preregister_error* First stage of registration of meta-URL failed.
- read_start_error* Can't read from source.
- write_start_error* Can't write to destination.
- read_error* Failed while reading from source.
- write_error* Failed while writing to destination.
- transfer_error* Failed while transferring data (mostly timeout).
- read_stop_error* Failed while finishing reading from source.
- write_stop_error* Failed while finishing writing to destination.
- postregister_error* Last stage of registration of meta-URL failed.
- cache_error* Error in caching procedure.
- system_error* Some system function returned unexpected error.
- credentials_expired_error* Error due to provided credentials are expired.
- undefined_error* Unknown/undefined error.

3.5.3 Constructor & Destructor Documentation

3.5.3.1 [DataMove::DataMove](#) (void)

Constructor.

3.5.3.2 [DataMove::~~DataMove](#) (void)

Destructor.

3.5.4 Member Function Documentation

3.5.4.1 void DataMove::checks (bool *v*)

Set if to make check for existence of remote file (and probably other checks too) before initiating 'reading' and 'writing' operations.

Parameters:

v true if allowed (default is true).

3.5.4.2 bool DataMove::checks (void)

Check if check for existence of remote file is done before initiating 'reading' and 'writing' operations.

3.5.4.3 void DataMove::force_to_meta (bool)

Set if file should be transfered and registered even if such LFN is already registered and source is not one of registered locations.

3.5.4.4 void DataMove::passive (bool)

Set if passive transfer should be used for FTP-like transfers.

3.5.4.5 void DataMove::retry (bool)

Set if transfer will be retried in case of failure.

3.5.4.6 bool DataMove::retry (void)

Check if transfer will be retried in case of failure.

3.5.4.7 void DataMove::secure (bool)

Set if high level of security (encryption) will be used during transfer if available.

3.5.4.8 void DataMove::set_default_max_inactivity_time (time_t *max_inactivity_time*) [inline]

Set maximal allowed time for waiting for any data. For more information see description of [DataSpeed](#) class.

3.5.4.9 void DataMove::set_default_min_average_speed (unsigned long long int *min_average_speed*) [inline]

Set minimal allowed average transfer speed (default is 0 averaged over whole time of transfer. For more information see description of [DataSpeed](#) class.

3.5.4.10 void DataMove::set_default_min_speed (unsigned long long int *min_speed*, time_t *min_speed_time*) [inline]

Set minimal allowed transfer speed (default is 0) to 'min_speed'. If speed drops below for time longer than 'min_speed_time' error is raised. For more information see description of [DataSpeed](#) class.

3.5.4.11 result DataMove::Transfer ([DataPoint](#) & *source*, [DataPoint](#) & *destination*, [DataCache](#) & *cache*, const [UrlMap](#) & *map*, unsigned long long int *min_speed*, time_t *min_speed_time*, unsigned long long int *min_average_speed*, time_t *max_inactivity_time*, callback *cb* = NULL, void * *arg* = NULL, const char * *prefix* = NULL)

Initiates transfer from 'source' to 'destination'.

Parameters:

min_speed minimal allowed current speed.

min_speed_time time for which speed should be less than 'min_speed' before transfer fails.

min_average_speed minimal allowed average speed.

max_inactivity_time time for which should be no activity before transfer fails.

3.5.4.12 result DataMove::Transfer ([DataPoint](#) & *source*, [DataPoint](#) & *destination*, [DataCache](#) & *cache*, const [UrlMap](#) & *map*, callback *cb* = NULL, void * *arg* = NULL, const char * *prefix* = NULL)

Initiates transfer from 'source' to 'destination'.

Parameters:

source source URL.

destination destination URL.

cache controls caching of downloaded files (if destination url is "file:///"). If caching is not needed default constructor DataCache() can be used.

map URL mapping/conversion table (for 'source' URL).

cb ifnot NULL, transfer is done in separate thread and 'cb' is called after transfer completes/fails.

arg passed to 'cb'.

prefix if 'verbose' is activated this information will be printed before each line representing current transfer status.

3.5.4.13 void DataMove::verbose (const string & *prefix*)

Activate printing information about transfer status.

Parameters:

prefix use this string if 'prefix' in [DataMove::Transfer](#) is NULL.

3.5.4.14 void DataMove::verbose (bool)

Activate printing information about transfer status.

3.5.4.15 `bool DataMove::verbose (void)`

Check if printing information about transfer status is activated.

The documentation for this class was generated from the following file:


- `datamove.h`

3.6 DataMovePar Class Reference

Wrapper around [DataMove](#) class to handle few transfers at once.

```
#include <datamovepar.h>
```

Inheritance diagram for DataMovePar::



Public Member Functions

- [DataMovePar](#) (void)
- [~DataMovePar](#) (void)
- bool [Add](#) (const char *source_url, const char *destination_url)
- bool [Get](#) (string &source_url, string &destination_url, [result](#) &res)
- bool [Transfer](#) (int num=5)
- bool [Transfer](#) ([DataCache](#) cache, const UrlMap &map, int num=5)

3.6.1 Detailed Description

Wrapper around [DataMove](#) class to handle few transfers at once.

3.6.2 Constructor & Destructor Documentation

3.6.2.1 DataMovePar::DataMovePar (void)

Constructor.

3.6.2.2 DataMovePar::~~DataMovePar (void)

Destructor. Object can't be destroyed while there is any transfer in progress.

3.6.3 Member Function Documentation

3.6.3.1 bool DataMovePar::Add (const char * *source_url*, const char * *destination_url*)

Add one more source and destination pair to list of handled transfers.

Parameters:

source_url URL (or meta-URL) of source file

destination_url URL (or meta-URL) of destination file

3.6.3.2 bool DataMovePar::Get (string & *source_url*, string & *destination_url*, [result](#) & *res*)

Get source and destination pair from list with result of transfer

Parameters:

source_url on exit contains URL (or meta-URL) of source file

destination_url on exit contains URL (or meta-URL) of destination file

res result of operation

3.6.3.3 bool DataMovePar::Transfer ([DataCache](#) *cache*, const UrlMap & *map*, int *num* = 5)

Perform transfer

Parameters:

cache to control data caching (use default constructor for no caching)

map to change/map source URLs (use default constructor for no mapping)

num number of simultaneous transfers

3.6.3.4 bool DataMovePar::Transfer (int *num* = 5)

Perform transfer

Parameters:

num number of simultaneous transfers

The documentation for this class was generated from the following file:

- datamovepar.h

3.7 DataPoint Class Reference

```
#include <datapoint.h>
```

Public Member Functions

- [DataPoint](#) (const char *url)
- bool [meta_resolve](#) (bool source)
- bool [meta_resolve](#) (bool source, const UriMap &maps)
- bool [meta_preregister](#) (bool replication, bool force=false)
- bool [meta_postregister](#) (bool replication, bool failure)
- bool [meta_preunregister](#) (bool replication)
- bool [meta_unregister](#) (bool all)
- bool [list_files](#) (list< [DataPoint::FileInfo](#) > &files, bool resolve=true)
- bool [get_info](#) ([DataPoint::FileInfo](#) &fi)
- bool [meta_size_available](#) (void)
- void [meta_size](#) (unsigned long long int val)
- void [meta_size_force](#) (unsigned long long int val)
- unsigned long long int [meta_size](#) (void) const
- bool [meta_checksum_available](#) (void)
- void [meta_checksum](#) (unsigned long long int val)
- void [meta_checksum_force](#) (unsigned long long int val)
- unsigned long long int [meta_checksum](#) (void) const
- bool [meta_created_available](#) (void)
- void [meta_created](#) (time_t val)
- void [meta_created_force](#) (time_t val)
- time_t [meta_created](#) (void) const
- bool [meta_validtill_available](#) (void)
- void [meta_validtill](#) (time_t val)
- void [meta_validtill_force](#) (time_t val)
- time_t [meta_validtill](#) (void) const
- bool [meta](#) (void) const
- void [meta](#) (const [DataPoint](#) &p)
- bool [meta_compare](#) (const [DataPoint](#) &p)
- bool [meta_stored](#) (void)
- bool [local](#) (void) const
- bool [map](#) (const UriMap &maps)
- bool [sort](#) (const UriMap &maps)
- [DataPoint](#) & **operator=** (const [DataPoint](#) &)
- **operator bool** (void) const
- const string & [current_location](#) (void) const
- const string & [current_meta_location](#) (void) const
- bool [next_location](#) (void)
- bool [have_location](#) (void)
- bool [have_locations](#) (void)
- bool [remove_location](#) (void)
- int [tries](#) (void)
- void [tries](#) (int n)
- string [base_url](#) (void) const
- string [canonic_url](#) (void) const
- const char * [lfn](#) (void) const
- bool [add_location](#) (const char *meta, const char *loc)

Public Attributes

- list< [Location](#) > **locations**

Friends

- ostream & **operator**<< (ostream &o, const [DataPoint](#) &point)

3.7.1 Detailed Description

DataPoint is an abstraction of URL. It can handle URLs of type [file://](#), [ftp://](#), [gsiftp://](#), [http://](#), [https://](#), [httpg://](#) (HTTP over GSI), [se://](#) (NG web service over HTTPG) and meta-URLs (URLs of Infexing Services) [rc://](#), [rls://](#). DataPoint provides means to resolve meta-URL into multiple URLs and to loop through them.

3.7.2 Constructor & Destructor Documentation

3.7.2.1 DataPoint::DataPoint (const char * url)

Constructor requires URL or meta-URL to be provided.

3.7.3 Member Function Documentation

3.7.3.1 bool DataPoint::add_location (const char * meta, const char * loc)

Add URL to list.

Parameters:

meta meta-name (name of location/service).

loc URL.

3.7.3.2 string DataPoint::base_url (void) const

Returns URL which was passed to constructor.

3.7.3.3 string DataPoint::canonic_url (void) const

Returns URL which was passed to constructor with location names removed, port number added, etc.

3.7.3.4 const string& DataPoint::current_location (void) const [inline]

Returns current (resolved) URL.

3.7.3.5 const string& DataPoint::current_meta_location (void) const [inline]

Returns meta information used to create curent URL. For RC that is location's name. For RLS that is equal to pfn.

3.7.3.6 bool DataPoint::get_info (DataPoint::FileInfo & fi)

Retrieve properties of object pointed by meta-URL of DataPoint object. It works only for meta-URL.

Parameters:

fi contains retrieved information.

3.7.3.7 bool DataPoint::have_location (void)

Returns false if out of retries.

3.7.3.8 bool DataPoint::have_locations (void)

Returns true if number of resolved URLs is not 0.

3.7.3.9 const char* DataPoint::lfn (void) const [inline]

Returns name which is given to file in Indexing Service (aka LFN).

3.7.3.10 bool DataPoint::list_files (list< DataPoint::FileInfo > & files, bool resolve = true)

Obtain information about objects and their properties available under meta-URL of DataPoint object. It works only for meta-URL.

Parameters:

files list of obtained objects.

resolve if false, do not try to obtain properties of objects.

3.7.3.11 bool DataPoint::local (void) const [inline]

Check if file is local (URL is `file://`).

3.7.3.12 bool DataPoint::map (const UrlMap & maps)

Map url (change it) according to table provided in maps.

Parameters:

maps mapping information.

3.7.3.13 void DataPoint::meta (const DataPoint & p) [inline]

Acquire meta-information from another object. Defined values are not overwritten.

Parameters:

p object from which information is taken.

3.7.3.14 bool DataPoint::meta (void) const [inline]

Check if URL is meta-URL.

3.7.3.15 unsigned long long int DataPoint::meta_checksum (void) const [inline]

Get value of meta-information 'checksum'.

3.7.3.16 void DataPoint::meta_checksum (unsigned long long int *val*) [inline]

Set value of meta-information 'checksum' if not already set.

3.7.3.17 bool DataPoint::meta_checksum_available (void) [inline]

Check if meta-information 'checksum' is available.

3.7.3.18 void DataPoint::meta_checksum_force (unsigned long long int *val*) [inline]

Set value of meta-information 'checksum'.

3.7.3.19 bool DataPoint::meta_compare (const [DataPoint](#) & *p*) [inline]

Compare meta-information form another object. Undefined values are not used for comparison. Default result is 'true'.

Parameters:

p object to which compare.

3.7.3.20 time_t DataPoint::meta_created (void) const [inline]

Get value of meta-information 'creation/modification time'.

3.7.3.21 void DataPoint::meta_created (time_t *val*) [inline]

Set value of meta-information 'creation/modification time' if not already set.

3.7.3.22 bool DataPoint::meta_created_available (void) [inline]

Check if meta-information 'creation/modification time' is available.

3.7.3.23 void DataPoint::meta_created_force (time_t *val*) [inline]

Set value of meta-information 'creation/modification time'.

3.7.3.24 bool DataPoint::meta_postregister (bool *replication*, bool *failure*)

Used for same purpose as meta_preregister. Should be called after actual transfer of file successfully finished.

Parameters:

replication if true then file is being replicated between 2 locations registered in Indexing Service under same name.

failure not used.

3.7.3.25 bool DataPoint::meta_preregister (bool *replication*, bool *force* = false)

This function registers physical location of file into Indexing Service. It should be called *before* actual transfer to that location happens.

Parameters:

replication if true then file is being replicated between 2 locations registered in Indexing Service under same name.

force if true, perform registration of new file even if it already exists. Should be used to fix failures in Indexing Service.

3.7.3.26 bool DataPoint::meta_preunregister (bool *replication*)

Should be called if file transfer failed. It removes changes made by meta_preregister.

3.7.3.27 bool DataPoint::meta_resolve (bool *source*, const UrlMap & *maps*)

Resolve meta-URL into list of ordinary URLs and obtain meta-information about file. Also sort obtained list so that URLs mentioned in UrlMap object are placed first. This is used during transfer to access local locations first.

Parameters:

maps list of mappings of remote URLs to (potentially) local locations.

3.7.3.28 bool DataPoint::meta_resolve (bool *source*)

Resolve meta-URL into list of ordinary URLs and obtain meta-information about file. Can be called for object representing ordinary URL or already resolved object.

Parameters:

source true if DataPoint object represents source of information

3.7.3.29 unsigned long long int DataPoint::meta_size (void) const [inline]

Get value of meta-information 'size'.

3.7.3.30 void DataPoint::meta_size (unsigned long long int *val*) [inline]

Set value of meta-information 'size' if not already set.

3.7.3.31 bool DataPoint::meta_size_available (void) [inline]

Check if meta-information 'size' is available.

3.7.3.32 void DataPoint::meta_size_force (unsigned long long int *val*) [inline]

Set value of meta-information 'size'.

3.7.3.33 bool DataPoint::meta_stored (void) [inline]

Check if file is registered in Indexing Service. Proper value is obtainable only after meta-resolve.

3.7.3.34 bool DataPoint::meta_unregister (bool *all*)

Remove information about file registered in Indexing Service.

Parameters:

all if true information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

3.7.3.35 time_t DataPoint::meta_validtill (void) const [inline]

Get value of meta-information 'validity time'.

3.7.3.36 void DataPoint::meta_validtill (time_t *val*) [inline]

Set value of meta-information 'validity time' if not already set.

3.7.3.37 bool DataPoint::meta_validtill_available (void) [inline]

Check if meta-information 'validity time' is available.

3.7.3.38 void DataPoint::meta_validtill_force (time_t *val*) [inline]

Set value of meta-information 'validity time'.

3.7.3.39 bool DataPoint::next_location (void)

Switch to next location in list of URLs. At last location switch to first if number of allowed retries does not exceeded. Returns false if no retries left.

3.7.3.40 bool DataPoint::remove_location (void)

Remove remove current URL from list.

3.7.3.41 bool DataPoint::sort (const UrlMap & *maps*)

Sort list of URLs so that those listed in mapping table are put first.

Parameters:

maps mapping information.

3.7.3.42 void DataPoint::tries (int *n*) [inline]

Set number of retries.

3.7.3.43 int DataPoint::tries (void) [inline]

Returns number of retries left.

The documentation for this class was generated from the following file:

- datapoint.h

3.8 DataPoint::FileInfo Class Reference

```
#include <datapoint.h>
```

Public Types

- enum **Type** { **file_type_unknown** = 0, **file_type_file** = 1, **file_type_dir** = 2 }

Public Member Functions

- [FileInfo](#) (const char *name_="")
- **operator bool** (void)

Public Attributes

- string **name**
- list< string > **urls**
- unsigned long long int **size**
- bool **size_available**
- unsigned long long int **checksum**
- bool **checksum_available**
- time_t **created**
- bool **created_available**
- time_t **valid**
- bool **valid_available**
- Type **type**

3.8.1 Detailed Description

[FileInfo](#) stores information about file (meta-information). Although all members are public it is not desirable to modify them directly outside [DataPoint](#) class.

3.8.2 Constructor & Destructor Documentation

3.8.2.1 DataPoint::FileInfo::FileInfo (const char * name_ = "") [inline]

File type - usually file_type_file - ordinary file.

3.8.3 Member Data Documentation

3.8.3.1 unsigned long long int DataPoint::FileInfo::checksum

If size is known.

3.8.3.2 bool DataPoint::FileInfo::checksum_available

Checksum of file.

3.8.3.3 `time_t DataPoint::FileInfo::created`

If checksum is known.

3.8.3.4 `bool DataPoint::FileInfo::created_available`

Creation/modification time.

3.8.3.5 `unsigned long long int DataPoint::FileInfo::size`

Physical endpoints/URLs at which file can be accessed.

3.8.3.6 `bool DataPoint::FileInfo::size_available`

Size of file in bytes.

3.8.3.7 `Type DataPoint::FileInfo::type`

If validity is known.

3.8.3.8 `time_t DataPoint::FileInfo::valid`

If time is known.

3.8.3.9 `bool DataPoint::FileInfo::valid_available`

Valid till time.

The documentation for this class was generated from the following file:

- datapoint.h

3.9 DataPoint::Location Class Reference

```
#include <datapoint.h>
```

Public Member Functions

- **Location** (const char *url_)
- **Location** (const char *meta_, const char *url_, bool existing_=true)
- **Location** (const string &url_)
- **Location** (const string &meta_, const string &url_)

Friends

- class [DataPoint](#)
- ostream & **operator**<< (ostream &o, const [DataPoint](#) &point)

3.9.1 Detailed Description

DataPoint::Location represent physical service at which files are located aka "base URL" including it's name (as given in Indexing Service). Currently it is used only internally by [DataPoint](#) class and for printing debug information.

The documentation for this class was generated from the following file:

- datapoint.h

3.10 DataSpeed Class Reference

```
#include <dataspeed.h>
```

Public Member Functions

- [DataSpeed](#) (time_t base=DATASPEED_AVERAGING_PERIOD)
- [DataSpeed](#) (unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, time_t base=DATASPEED_AVERAGING_PERIOD)
- [~DataSpeed](#) (void)
- void [verbose](#) (bool val)
- void [verbose](#) (const string &prefix)
- bool [verbose](#) (void)
- void [set_min_speed](#) (unsigned long long int min_speed, time_t min_speed_time)
- void [set_min_average_speed](#) (unsigned long long int min_average_speed)
- void [set_max_inactivity_time](#) (time_t max_inactivity_time)
- void [set_base](#) (time_t base_=DATASPEED_AVERAGING_PERIOD)
- void [reset](#) (void)
- bool [transfer](#) (unsigned long long int n=0)
- void [hold](#) (bool disable)
- bool [min_speed_failure](#) ()
- bool [min_average_speed_failure](#) ()
- bool [max_inactivity_time_failure](#) ()
- unsigned long long int [transferred_size](#) (void)

3.10.1 Detailed Description

Keeps track of average and instantaneous speed. Also detects data transfer inactivity and other transfer timeouts.

3.10.2 Constructor & Destructor Documentation

3.10.2.1 DataSpeed::DataSpeed (time_t *base* = DATASPEED_AVERAGING_PERIOD)

Constructor

Parameters:

base time period used to average values (default 1 minute).

3.10.2.2 DataSpeed::DataSpeed (unsigned long long int *min_speed*, time_t *min_speed_time*, unsigned long long int *min_average_speed*, time_t *max_inactivity_time*, time_t *base* = DATASPEED_AVERAGING_PERIOD)

Constructor

Parameters:

base time period used to average values (default 1 minute).

min_speed minimal allowed speed (Butes per second). If speed drops and holds below threshold for min_speed_time_ seconds error is triggered.

min_speed_time

min_average_speed_ minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

max_inactivity_time - if no data is passing for specified amount of time (seconds), error is triggered.

3.10.2.3 DataSpeed::~~DataSpeed (void)

Destructor.

3.10.3 Member Function Documentation

3.10.3.1 void DataSpeed::hold (bool *disable*)

Turn off speed control.

Parameters:

disable true to turn off.

3.10.3.2 bool DataSpeed::max_inactivity_time_failure () [inline]

Check if maximal inactivity time error was triggered.

3.10.3.3 bool DataSpeed::min_average_speed_failure () [inline]

Check if minimal average speed error was triggered.

3.10.3.4 bool DataSpeed::min_speed_failure () [inline]

Check if minimal speed error was triggered.

3.10.3.5 void DataSpeed::reset (void)

Reset all counters and triggers.

3.10.3.6 void DataSpeed::set_base (time_t *base_* = DATASPEED_AVERAGING_PERIOD)

Set averaging time period.

Parameters:

base time period used to average values (default 1 minute).

3.10.3.7 void DataSpeed::set_max_inactivity_time (time_t *max_inactivity_time*)

Set inactivity timeout.

Parameters:

max_inactivity_time - if no data is passing for specified amount of time (seconds), error is triggered.

3.10.3.8 void DataSpeed::set_min_average_speed (unsigned long long int *min_average_speed*)

Set minimal average speed.

Parameters:

min_average_speed minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

3.10.3.9 void DataSpeed::set_min_speed (unsigned long long int *min_speed*, time_t *min_speed_time*)

Set minimal allowed speed.

Parameters:

min_speed minimal allowed speed (Bytes per second). If speed drops and holds below threshold for *min_speed_time* seconds error is triggered.

min_speed_time

3.10.3.10 bool DataSpeed::transfer (unsigned long long int *n* = 0)

Inform object, about amount of data has been transferred. All errors are triggered by this method. To make them work application must call this method periodically even with zero value.

Parameters:

n amount of data transferred (bytes).

3.10.3.11 unsigned long long int DataSpeed::transferred_size (void) [inline]

Returns amount of data this object knows about.

3.10.3.12 bool DataSpeed::verbose (void)

Check if speed information is going to be printed.

3.10.3.13 void DataSpeed::verbose (const string & *prefix*)

Print information about current speed and amount of data.

Parameters:

'prefix' add this string at the beginning of every string.

3.10.3.14 void DataSpeed::verbose (bool *val*)

Activate printing information about current time speeds, amount of transferred data.

The documentation for this class was generated from the following file:

- dataspeed.h

Index

- ~DataBufferPar
 - DataBufferPar, [6](#)
- ~DataCache
 - DataCache, [12](#)
- ~DataHandle
 - DataHandle, [17](#)
- ~DataMove
 - DataMove, [21](#)
- ~DataMovePar
 - DataMovePar, [25](#)
- ~DataSpeed
 - DataSpeed, [38](#)
- Add
 - DataMovePar, [25](#)
- add_location
 - DataPoint, [28](#)
- additional_checks
 - DataHandle, [17](#)
- analyze
 - DataHandle, [17](#)
- base_url
 - DataPoint, [28](#)
- buffer_size
 - DataBufferPar, [6](#)
- cache_error
 - DataMove, [21](#)
- canonic_url
 - DataPoint, [28](#)
- cb
 - DataCache, [12](#)
- check
 - DataHandle, [17](#)
- checks
 - DataMove, [22](#)
- checksum
 - DataPoint::FileInfo, [34](#)
- checksum_available
 - DataPoint::FileInfo, [34](#)
- checksum_object
 - DataBufferPar, [6](#)
- checksum_valid
 - DataBufferPar, [6](#)
- clean
 - DataCache, [12](#)
- created
 - DataCache, [12](#)
 - DataPoint::FileInfo, [34](#)
- created_available
 - DataCache, [12](#)
 - DataPoint::FileInfo, [35](#)
- created_force
 - DataCache, [13](#)
- credentials_expired_error
 - DataMove, [21](#)
- current_location
 - DataPoint, [28](#)
- current_meta_location
 - DataPoint, [28](#)
- DataBufferPar, [5](#)
 - DataBufferPar, [6](#)
- DataBufferPar
 - ~DataBufferPar, [6](#)
 - buffer_size, [6](#)
 - checksum_object, [6](#)
 - checksum_valid, [6](#)
 - DataBufferPar, [6](#)
 - eof_position, [7](#)
 - eof_read, [7](#)
 - eof_write, [7](#)
 - error, [7](#)
 - error_read, [7](#)
 - error_transfer, [7](#)
 - error_write, [7](#)
 - for_read, [8](#)
 - for_write, [8](#)
 - is_notwritten, [8](#)
 - is_read, [8](#)
 - is_written, [9](#)
 - operator bool, [9](#)
 - operator[], [9](#)
 - set, [9](#)
 - speed, [10](#)
 - wait, [9](#)
 - wait_eof, [9](#)
 - wait_eof_read, [10](#)
 - wait_eof_write, [10](#)

- wait_used, 10
- DataCache, 11
 - DataCache, 11, 12
- DataCache
 - ~DataCache, 12
 - cb, 12
 - clean, 12
 - created, 12
 - created_available, 12
 - created_force, 13
 - DataCache, 11, 12
 - file, 13
 - link, 13
 - operator bool, 13
 - start, 13
 - stop, 13
 - validtill, 13, 14
 - validtill_available, 14
 - validtill_force, 14
- DataCallback, 15
- DataHandle, 16
 - DataHandle, 16
- DataHandle
 - ~DataHandle, 17
 - additional_checks, 17
 - analyze, 17
 - check, 17
 - DataHandle, 16
 - failure_reason, 17
 - failure_reason_t, 16
 - list_files, 17
 - out_of_order, 17, 18
 - passive, 18
 - remove, 18
 - secure, 18
 - start_reading, 18
 - start_writing, 18
 - stop_reading, 19
 - stop_writing, 19
- DataMove, 20
 - cache_error, 21
 - credentials_expired_error, 21
 - DataMove, 21
 - postregister_error, 21
 - preregister_error, 21
 - read_acquire_error, 21
 - read_error, 21
 - read_resolve_error, 21
 - read_start_error, 21
 - read_stop_error, 21
 - success, 21
 - system_error, 21
 - transfer_error, 21
 - undefined_error, 21
 - write_acquire_error, 21
 - write_error, 21
 - write_resolve_error, 21
 - write_start_error, 21
 - write_stop_error, 21
- DataMove
 - ~DataMove, 21
 - checks, 22
 - DataMove, 21
 - force_to_meta, 22
 - passive, 22
 - result, 21
 - retry, 22
 - secure, 22
 - set_default_max_inactivity_time, 22
 - set_default_min_average_speed, 22
 - set_default_min_speed, 22
 - Transfer, 23
 - verbose, 23
- DataMovePar, 25
 - DataMovePar, 25
- DataMovePar
 - ~DataMovePar, 25
 - Add, 25
 - DataMovePar, 25
 - Get, 25
 - Transfer, 26
- DataPoint, 27
 - DataPoint, 28
- DataPoint
 - add_location, 28
 - base_url, 28
 - canonic_url, 28
 - current_location, 28
 - current_meta_location, 28
 - DataPoint, 28
 - get_info, 28
 - have_location, 29
 - have_locations, 29
 - lfn, 29
 - list_files, 29
 - local, 29
 - map, 29
 - meta, 29
 - meta_checksum, 30
 - meta_checksum_available, 30
 - meta_checksum_force, 30
 - meta_compare, 30
 - meta_created, 30
 - meta_created_available, 30
 - meta_created_force, 30
 - meta_postregister, 30
 - meta_preregister, 31
 - meta_preunregister, 31

- meta_resolve, 31
- meta_size, 31
- meta_size_available, 32
- meta_size_force, 32
- meta_stored, 32
- meta_unregister, 32
- meta_validtill, 32
- meta_validtill_available, 32
- meta_validtill_force, 32
- next_location, 32
- remove_location, 32
- sort, 33
- tries, 33
- DataPoint::FileInfo, 34
- DataPoint::FileInfo
 - checksum, 34
 - checksum_available, 34
 - created, 34
 - created_available, 35
 - FileInfo, 34
 - size, 35
 - size_available, 35
 - type, 35
 - valid, 35
 - valid_available, 35
- DataPoint::Location, 36
- DataSpeed, 37
 - DataSpeed, 37
- DataSpeed
 - ~DataSpeed, 38
 - DataSpeed, 37
 - hold, 38
 - max_inactivity_time_failure, 38
 - min_average_speed_failure, 38
 - min_speed_failure, 38
 - reset, 38
 - set_base, 38
 - set_max_inactivity_time, 38
 - set_min_average_speed, 38
 - set_min_speed, 39
 - transfer, 39
 - transferred_size, 39
 - verbose, 39
- eof_position
 - DataBufferPar, 7
- eof_read
 - DataBufferPar, 7
- eof_write
 - DataBufferPar, 7
- error
 - DataBufferPar, 7
- error_read
 - DataBufferPar, 7
- error_transfer
 - DataBufferPar, 7
- error_write
 - DataBufferPar, 7
- failure_reason
 - DataHandle, 17
- failure_reason_t
 - DataHandle, 16
- file
 - DataCache, 13
- FileInfo
 - DataPoint::FileInfo, 34
- for_read
 - DataBufferPar, 8
- for_write
 - DataBufferPar, 8
- force_to_meta
 - DataMove, 22
- Get
 - DataMovePar, 25
- get_info
 - DataPoint, 28
- have_location
 - DataPoint, 29
- have_locations
 - DataPoint, 29
- hold
 - DataSpeed, 38
- is_notwritten
 - DataBufferPar, 8
- is_read
 - DataBufferPar, 8
- is_written
 - DataBufferPar, 9
- lfn
 - DataPoint, 29
- link
 - DataCache, 13
- list_files
 - DataHandle, 17
 - DataPoint, 29
- local
 - DataPoint, 29
- map
 - DataPoint, 29
- max_inactivity_time_failure
 - DataSpeed, 38
- meta
 - DataPoint, 29

- meta_checksum
 - DataPoint, 30
- meta_checksum_available
 - DataPoint, 30
- meta_checksum_force
 - DataPoint, 30
- meta_compare
 - DataPoint, 30
- meta_created
 - DataPoint, 30
- meta_created_available
 - DataPoint, 30
- meta_created_force
 - DataPoint, 30
- meta_postregister
 - DataPoint, 30
- meta_preregister
 - DataPoint, 31
- meta_preunregister
 - DataPoint, 31
- meta_resolve
 - DataPoint, 31
- meta_size
 - DataPoint, 31
- meta_size_available
 - DataPoint, 32
- meta_size_force
 - DataPoint, 32
- meta_stored
 - DataPoint, 32
- meta_unregister
 - DataPoint, 32
- meta_validtill
 - DataPoint, 32
- meta_validtill_available
 - DataPoint, 32
- meta_validtill_force
 - DataPoint, 32
- min_average_speed_failure
 - DataSpeed, 38
- min_speed_failure
 - DataSpeed, 38
- next_location
 - DataPoint, 32
- operator bool
 - DataBufferPar, 9
 - DataCache, 13
- operator[]
 - DataBufferPar, 9
- out_of_order
 - DataHandle, 17, 18
- passive
 - DataHandle, 18
 - DataMove, 22
- postregister_error
 - DataMove, 21
- preregister_error
 - DataMove, 21
- read_acquire_error
 - DataMove, 21
- read_error
 - DataMove, 21
- read_resolve_error
 - DataMove, 21
- read_start_error
 - DataMove, 21
- read_stop_error
 - DataMove, 21
- remove
 - DataHandle, 18
- remove_location
 - DataPoint, 32
- reset
 - DataSpeed, 38
- result
 - DataMove, 21
- retry
 - DataMove, 22
- secure
 - DataHandle, 18
 - DataMove, 22
- set
 - DataBufferPar, 9
- set_base
 - DataSpeed, 38
- set_default_max_inactivity_time
 - DataMove, 22
- set_default_min_average_speed
 - DataMove, 22
- set_default_min_speed
 - DataMove, 22
- set_max_inactivity_time
 - DataSpeed, 38
- set_min_average_speed
 - DataSpeed, 38
- set_min_speed
 - DataSpeed, 39
- size
 - DataPoint::FileInfo, 35
- size_available
 - DataPoint::FileInfo, 35
- sort
 - DataPoint, 33

- speed
 - DataBufferPar, [10](#)
- start
 - DataCache, [13](#)
- start_reading
 - DataHandle, [18](#)
- start_writing
 - DataHandle, [18](#)
- stop
 - DataCache, [13](#)
- stop_reading
 - DataHandle, [19](#)
- stop_writing
 - DataHandle, [19](#)
- success
 - DataMove, [21](#)
- system_error
 - DataMove, [21](#)
- Transfer
 - DataMove, [23](#)
 - DataMovePar, [26](#)
- transfer
 - DataSpeed, [39](#)
- transfer_error
 - DataMove, [21](#)
- transferred_size
 - DataSpeed, [39](#)
- tries
 - DataPoint, [33](#)
- type
 - DataPoint::FileInfo, [35](#)
- undefined_error
 - DataMove, [21](#)
- valid
 - DataPoint::FileInfo, [35](#)
- valid_available
 - DataPoint::FileInfo, [35](#)
- validtill
 - DataCache, [13](#), [14](#)
- validtill_available
 - DataCache, [14](#)
- validtill_force
 - DataCache, [14](#)
- verbose
 - DataMove, [23](#)
 - DataSpeed, [39](#)
- wait
 - DataBufferPar, [9](#)
- wait_eof
 - DataBufferPar, [9](#)
- wait_eof_read
 - DataBufferPar, [10](#)
- wait_eof_write
 - DataBufferPar, [10](#)
- wait_used
 - DataBufferPar, [10](#)
- write_acquire_error
 - DataMove, [21](#)
- write_error
 - DataMove, [21](#)
- write_resolve_error
 - DataMove, [21](#)
- write_start_error
 - DataMove, [21](#)
- write_stop_error
 - DataMove, [21](#)