

# ARC::DataMove Reference Manual

Generated by Doxygen 1.3.5

Sat Jan 8 12:26:09 2005



# Contents

<b>1</b>	<b>ARC::DataMove Hierarchical Index</b>	<b>1</b>
1.1	ARC::DataMove Class Hierarchy . . . . .	1
<b>2</b>	<b>ARC::DataMove Class Index</b>	<b>3</b>
2.1	ARC::DataMove Class List . . . . .	3
<b>3</b>	<b>ARC::DataMove Class Documentation</b>	<b>5</b>
3.1	DataBufferPar Class Reference . . . . .	5
3.2	DataCache Class Reference . . . . .	11
3.3	DataCallback Class Reference . . . . .	15
3.4	DataHandle Class Reference . . . . .	16
3.5	DataHandle::analyze_t Class Reference . . . . .	20
3.6	DataMove Class Reference . . . . .	21
3.7	DataMovePar Class Reference . . . . .	26
3.8	DataPoint Class Reference . . . . .	28
3.9	DataPoint::FileInfo Class Reference . . . . .	37
3.10	DataPointDirect Class Reference . . . . .	39
3.11	DataPointDirect::Location Class Reference . . . . .	48
3.12	DataPointMeta Class Reference . . . . .	49
3.13	DataSpeed Class Reference . . . . .	53



# Chapter 1

## ARC::DataMove Hierarchical Index

### 1.1 ARC::DataMove Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

DataBuffer	
DataBufferPar . . . . .	5
DataCallback . . . . .	15
DataCache . . . . .	11
DataHandle . . . . .	16
DataHandle::analyze_t . . . . .	20
DataMove . . . . .	21
DataMovePar . . . . .	26
DataPoint . . . . .	28
DataPointDirect . . . . .	39
DataPointFile	
DataPointFTP	
DataPointHTTP	
DataPointMeta . . . . .	49
DataPointRC	
DataPointRLS	
DataPoint::FileInfo . . . . .	37
DataPointDirect::Location . . . . .	48
DataSpeed . . . . .	53



## Chapter 2

# ARC::DataMove Class Index

### 2.1 ARC::DataMove Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

<a href="#">DataBufferPar</a>	5
<a href="#">DataCache</a>	11
<a href="#">DataCallback</a>	15
<a href="#">DataHandle</a>	16
<a href="#">DataHandle::analyze_t</a>	20
<a href="#">DataMove</a>	21
<a href="#">DataMovePar</a> (Wrapper around <a href="#">DataMove</a> class to handle few transfers at once )	26
<a href="#">DataPoint</a>	28
<a href="#">DataPoint::FileInfo</a>	37
<a href="#">DataPointDirect</a>	39
<a href="#">DataPointDirect::Location</a>	48
<a href="#">DataPointMeta</a>	49
<a href="#">DataSpeed</a>	53





## Chapter 3

# ARC::DataMove Class Documentation

### 3.1 DataBufferPar Class Reference

```
#include <databufferpar.h>
```

#### Public Member Functions

- [operator bool](#) (void)
- [DataBufferPar](#) (unsigned int size=65536, int blocks=3)
- [DataBufferPar](#) (Checksum \*cksum, unsigned int size=65536, int blocks=3)
- [~DataBufferPar](#) (void)
- [bool set](#) (Checksum \*cksum=NULL, unsigned int size=65536, int blocks=3)
- [char \\* operator\[\]](#) (int n)
- [bool for\\_read](#) (int &handle, unsigned int &length, bool wait)
- [bool is\\_read](#) (int handle, unsigned int length, unsigned long long int offset)
- [bool is\\_read](#) (char \*buf, unsigned int length, unsigned long long int offset)
- [bool for\\_write](#) (int &handle, unsigned int &length, unsigned long long int &offset, bool wait)
- [bool is\\_written](#) (int handle)
- [bool is\\_written](#) (char \*buf)
- [bool is\\_notwritten](#) (int handle)
- [bool is\\_notwritten](#) (char \*buf)
- [void eof\\_read](#) (bool v)
- [void eof\\_write](#) (bool v)
- [void error\\_read](#) (bool v)
- [void error\\_write](#) (bool v)
- [bool eof\\_read](#) (void)
- [bool eof\\_write](#) (void)
- [bool error\\_read](#) (void)
- [bool error\\_write](#) (void)
- [bool error\\_transfer](#) (void)
- [bool error](#) (void)
- [bool wait](#) (void)
- [bool wait\\_used](#) (void)
- [bool checksum\\_valid](#) (void)
- [const CheckSum \\* checksum\\_object](#) (void)

- bool [wait\\_eof\\_read](#) (void)
- bool [wait\\_read](#) (void)
- bool [wait\\_eof\\_write](#) (void)
- bool [wait\\_write](#) (void)
- bool [wait\\_eof](#) (void)
- unsigned long long int [eof\\_position](#) (void) const
- unsigned int [buffer\\_size](#) (void)

## Public Attributes

- [DataSpeed](#) *speed*

### 3.1.1 Detailed Description

This class represents set of buffers used during data transfer.

### 3.1.2 Constructor & Destructor Documentation

#### 3.1.2.1 **DataBufferPar::DataBufferPar** (unsigned int *size* = 65536, int *blocks* = 3)

Constructor

##### Parameters:

- size* size of every buffer in bytes.  
*blocks* number of buffers.

#### 3.1.2.2 **DataBufferPar::DataBufferPar** (Checksum \* *cksum*, unsigned int *size* = 65536, int *blocks* = 3)

Constructor

##### Parameters:

- size* size of every buffer in bytes.  
*blocks* number of buffers.  
*cksum* object which will compute checksum. Should not be destroyed till DataBufferPar itself.

#### 3.1.2.3 **DataBufferPar::~DataBufferPar** (void)

Destructor.

### 3.1.3 Member Function Documentation

#### 3.1.3.1 unsigned int **DataBufferPar::buffer\_size** (void)

Returns size of buffer in object. If not initialized then this number represents size of default buffer.

**3.1.3.2 const CheckSum\* DataBufferPar::checksum\_object (void)**

Returns CheckSum object specified in constructor.

**3.1.3.3 bool DataBufferPar::checksum\_valid (void)**

Returns true if checksum was successfully computed.

**3.1.3.4 unsigned long long int DataBufferPar::eof\_position (void) const [inline]**

Returns offset following last piece of data transfered.

**3.1.3.5 bool DataBufferPar::eof\_read (void)**

Returns true if object was informed about end of transfer on 'read' side.

**3.1.3.6 void DataBufferPar::eof\_read (bool v)**

Informs object if there will be no more request for 'read' buffers. v true if no more requests.

**3.1.3.7 bool DataBufferPar::eof\_write (void)**

Returns true if object was informed about end of transfer on 'write' side.

**3.1.3.8 void DataBufferPar::eof\_write (bool v)**

Informs object if there will be no more request for 'write' buffers. v true if no more requests.

**3.1.3.9 bool DataBufferPar::error (void)**

Returns true if object was informed about error or internal error occurred.

**3.1.3.10 bool DataBufferPar::error\_read (void)**

Returns true if object was informed about error on 'read' side.

**3.1.3.11 void DataBufferPar::error\_read (bool v)**

Informs object if error occurred on 'read' side.

**Parameters:**

v true if error.

**3.1.3.12 bool DataBufferPar::error\_transfer (void)**

Returns true if error occurred inside object.

**3.1.3.13 bool DataBufferPar::error\_write (void)**

Returns true if object was informed about error on 'write' side.

**3.1.3.14 void DataBufferPar::error\_write (bool *v*)**

Informs object if error occurred on 'write' side.

**Parameters:**

*v* true if error.

**3.1.3.15 bool DataBufferPar::for\_read (int & *handle*, unsigned int & *length*, bool *wait*)**

Request buffer for READING INTO it.

**Parameters:**

*handle* returns buffer's number.

*length* returns size of buffer

*wait* if true and there are no free buffers, method will wait for one. Returns true on success

**3.1.3.16 bool DataBufferPar::for\_write (int & *handle*, unsigned int & *length*, unsigned long long int & *offset*, bool *wait*)**

Request buffer for WRITING FROM it.

**Parameters:**

*handle* returns buffer's number.

*length* returns size of buffer

*wait* if true and there are no free buffers, method will wait for one.

**3.1.3.17 bool DataBufferPar::is\_notwritten (char \* *buf*)**

Informs object that data was NOT written from buffer (and releases buffer).

**Parameters:**

*buf* - address of buffer

**3.1.3.18 bool DataBufferPar::is\_notwritten (int *handle*)**

Informs object that data was NOT written from buffer (and releases buffer).

**Parameters:**

*handle* buffer's number.

**3.1.3.19 bool DataBufferPar::is\_read (char \* *buf*, unsigned int *length*, unsigned long long int *offset*)**

Informs object that data was read into buffer.

**Parameters:**

*buf* - address of buffer

*length* amount of data.

*offset* offset in stream, file, etc.

**3.1.3.20 bool DataBufferPar::is\_read (int *handle*, unsigned int *length*, unsigned long long int *offset*)**

Informs object that data was read into buffer.

**Parameters:**

*handle* buffer's number.

*length* amount of data.

*offset* offset in stream, file, etc.

**3.1.3.21 bool DataBufferPar::is\_written (char \* *buf*)**

Informs object that data was written from buffer.

**Parameters:**

*buf* - address of buffer

**3.1.3.22 bool DataBufferPar::is\_written (int *handle*)**

Informs object that data was written from buffer.

**Parameters:**

*handle* buffer's number.

**3.1.3.23 DataBufferPar::operator bool (void) [inline]**

Check if DataBufferPar object is initialized.

**3.1.3.24 ]**

char\* DataBufferPar::operator[] (int *n*)

Direct access to buffer by number.

**3.1.3.25 bool DataBufferPar::set (Checksum \* *cksum* = NULL, unsigned int *size* = 65536, int *blocks* = 3)**

Reinitialize buffers with different parameters.

**Parameters:**

*size* size of every buffer in bytes.

*blocks* number of buffers.

*cksum* object which will compute checksum. Should not be destroyed till DataBufferPar itself.

**3.1.3.26 bool DataBufferPar::wait (void)**

Wait (max 60 sec.) till any action happens in object. Returns true if action is eof on any side.

**3.1.3.27 bool DataBufferPar::wait\_eof (void)**

Wait till end of transfer happens on any side.

**3.1.3.28 bool DataBufferPar::wait\_eof\_read (void)**

Wait till end of transfer happens on 'read' side.

**3.1.3.29 bool DataBufferPar::wait\_eof\_write (void)**

Wait till end of transfer happens on 'write' side.

**3.1.3.30 bool DataBufferPar::wait\_read (void)**

Wait till end of transfer or error happens on 'read' side.

**3.1.3.31 bool DataBufferPar::wait\_used (void)**

Wait till there are no more used buffers left in object.

**3.1.3.32 bool DataBufferPar::wait\_write (void)**

Wait till end of transfer or error happens on 'write' side.

**3.1.4 Member Data Documentation****3.1.4.1 [DataSpeed DataBufferPar::speed](#)**

This object controls transfer speed.


The documentation for this class was generated from the following file:

- databufferpar.h

## 3.2 DataCache Class Reference

```
#include <datacache.h>
```

Inheritance diagram for DataCache::



### Public Types

- enum `file_state_t` { `file_no_error` = 0, `file_download_failed` = 1, `file_not_valid` = 2, `file_keep` = 4 }

### Public Member Functions

- `DataCache` (void)
- `DataCache` (const char \*cache\_path, const char \*cache\_data\_path, const char \*cache\_link\_path, const char \*id, uid\_t cache\_uid, gid\_t cache\_gid)
- `DataCache` (const `DataCache` &cache)
- `~DataCache` (void)
- bool `start` (const char \*base\_url, bool &available)
- const string & `file` (void) const
- bool `stop` (int file\_state=file\_no\_error)
- bool `link` (const char \*link\_path)
- bool `link` (const char \*link\_path, uid\_t uid, gid\_t gid)
- bool `copy` (const char \*link\_path)
- bool `copy` (const char \*link\_path, uid\_t uid, gid\_t gid)
- bool `clean` (unsigned long long int size=1)
- virtual bool `cb` (unsigned long long int size)
- `operator bool` (void)
- bool `created_available` (void)
- void `created` (time\_t val)
- void `created_force` (time\_t val)
- time\_t `created` (void)
- bool `validtill_available` (void)
- time\_t `validtill` (void)
- void `validtill_force` (time\_t val)
- void `validtill` (time\_t val)

#### 3.2.1 Detailed Description

High level interface to cache operations (same functionality :) ) and additional functionality to integrate into grid-manager environment.

### 3.2.2 Constructor & Destructor Documentation

#### 3.2.2.1 DataCache::DataCache (void)

Default constructor (non-functional cache).

#### 3.2.2.2 DataCache::DataCache (const char \* *cache\_path*, const char \* *cache\_data\_path*, const char \* *cache\_link\_path*, const char \* *id*, uid\_t *cache\_uid*, gid\_t *cache\_gid*)

Constructor

**Parameters:**

*cache\_path* path to directory with cache info files

*cache\_data\_path* path to directory with cache data files

*cache\_link\_path* path used to create link in case *cache\_directory* is visible under different name during actual usage

*id* identifier used to claim files in cache

*cache\_uid* owner of cahce (0 for public cache)

*cache\_gid* owner group of cache (0 for public cache)

#### 3.2.2.3 DataCache::DataCache (const DataCache & *cache*)

Copy constructor.

#### 3.2.2.4 DataCache::~DataCache (void)

and destructor

### 3.2.3 Member Function Documentation

#### 3.2.3.1 virtual bool DataCache::cb (unsigned long long int *size*) [virtual]

Callback implementation to clean at least 1 byte.

Reimplemented from [DataCallback](#).

#### 3.2.3.2 bool DataCache::clean (unsigned long long int *size* = 1)

Remove some amount of oldest information from cache. Returns true on success.

**Parameters:**

*size* amount to be removed (bytes)

#### 3.2.3.3 bool DataCache::copy (const char \* *link\_path*)

Do same as [link\(\)](#) but always create copy.



**3.2.3.4 time\_t DataCache::created (void)** [inline]

Get creation time.

**3.2.3.5 void DataCache::created (time\_t val)** [inline]

Set creation time (if not already set).

**Parameters:**

*val* creation time

**3.2.3.6 bool DataCache::created\_available (void)** [inline]

Check if there is an information about creation time.

**3.2.3.7 void DataCache::created\_force (time\_t val)** [inline]

Set creation time (even if already set).

**Parameters:**

*val* creation time

**3.2.3.8 const string& DataCache::file (void) const** [inline]

Returns path to file which contains/will contain content of assigned url.

**3.2.3.9 bool DataCache::link (const char \* link\_path, uid\_t uid, gid\_t gid)****Parameters:**

*uid* set owner of soft-link to uid

*gid* set group of soft-link to gid

**3.2.3.10 bool DataCache::link (const char \* link\_path)**

Must be called to create soft-link to cache file or to copy it. It's behavior depends on configuration. All necessary directories will be created. Returns false on error (usually that means soft-link already exists).

**Parameters:**

*link\_path* path for soft-link or new file.

**3.2.3.11 DataCache::operator bool (void)** [inline]

Returns true if object is useable.

**3.2.3.12 bool DataCache::start (const char \* *base\_url*, bool & *available*)**

Prepare cache for downloading file. On success returns true. This function can block for long time if there is another process downloading same url.

**Parameters:**

*base\_url* url to assign to file in cache (file's identifier)  
*available* contains true on exit if file is already in cache

**3.2.3.13 bool DataCache::stop (int *file\_state* = file\_no\_error)**

This method must be called after file was downloaded or download failed.

**Parameters:**

*failure* true if download failed

**3.2.3.14 void DataCache::validtill (time\_t *val*) [inline]**

Get invalidation time.

**3.2.3.15 time\_t DataCache::validtill (void) [inline]**

Set invalidation time (if not already set).

**Parameters:**

*val* validity time

**3.2.3.16 bool DataCache::validtill\_available (void) [inline]**

Check if there is an information about invalidation time.

**3.2.3.17 void DataCache::validtill\_force (time\_t *val*) [inline]**

Set invalidation time (even if already set).

**Parameters:**

*val* validity time


The documentation for this class was generated from the following file:

- datacache.h

## 3.3 DataCallback Class Reference

```
#include <datacallback.h>
```

Inheritance diagram for DataCallback::



### Public Member Functions

- virtual bool **cb** (int)
- virtual bool **cb** (unsigned int)
- virtual bool **cb** (long long int)
- virtual bool **cb** (unsigned long long int)

#### 3.3.1 Detailed Description

This class is used by [DataHandle](#) to report missing space on local filesystem. One of 'cb' functions here will be called if operation initiated by [DataHandle::start\\_reading](#) runs out of disk space.

The documentation for this class was generated from the following file:

- datacallback.h

## 3.4 DataHandle Class Reference

```
#include <datahandle.h>
```

### Public Types

- enum [failure\\_reason\\_t](#) { **common\_failure** = 0, **credentials\_expired\_failure** = 1 }

### Public Member Functions

- [DataHandle](#) ([DataPoint](#) \*url\_)
- [~DataHandle](#) (void)
- bool [start\\_reading](#) ([DataBufferPar](#) &buffer)
- bool [start\\_writing](#) ([DataBufferPar](#) &buffer, [DataCallback](#) \*space\_cb=NULL)
- bool [stop\\_reading](#) (void)
- bool [stop\\_writing](#) (void)
- bool [analyze](#) ([analyze\\_t](#) &arg)
- bool [check](#) (void)
- bool [remove](#) (void)
- bool [list\\_files](#) (list< [DataPoint::FileInfo](#) > &files, bool resolve=true)
- bool [out\\_of\\_order](#) (void)
- void [out\\_of\\_order](#) (bool v)
- void [additional\\_checks](#) (bool v)
- bool [additional\\_checks](#) (void)
- void [secure](#) (bool v)
- bool [secure](#) (void)
- void [passive](#) (bool v)
- [failure\\_reason\\_t](#) [failure\\_reason](#) (void)
- void [range](#) (unsigned long long int start=0, unsigned long long end=0)

### 3.4.1 Detailed Description

DataHandle is kind of generalized file handle. Differently from file handle it does not support operations read() and write(). Instead it initiates operation and uses object of class [DataBufferPar](#) to pass actual data. It also provides other operations like querying parameters of remote object. It is used by higher-level classes [DataMove](#) and [DataMovePar](#) to provide data transfer service for application.

### 3.4.2 Member Enumeration Documentation

#### 3.4.2.1 enum [DataHandle::failure\\_reason\\_t](#)

Reason of transfer failure.

### 3.4.3 Constructor & Destructor Documentation

#### 3.4.3.1 DataHandle::DataHandle (DataPoint \* url\_)

Constructor

**Parameters:**

*url\_* URL. Should not be destroyed before DataHandle itself.

#### 3.4.3.2 DataHandle::~~DataHandle (void)

Destructor. No comments.

### 3.4.4 Member Function Documentation

#### 3.4.4.1 bool DataHandle::additional\_checks (void) [inline]

Check if additional checks before 'reading' and 'writing' will be performed.

#### 3.4.4.2 void DataHandle::additional\_checks (bool v) [inline]

Allow/disallow to make check for existence of remote file (and probably other checks too) before initiating 'reading' and 'writing' operations.

**Parameters:**

*v* true if allowed (default is true).

#### 3.4.4.3 bool DataHandle::analyze (analyze\_t & arg)

Analyze url and provide hints.

**Parameters:**

*arg* returns suggested values.

#### 3.4.4.4 bool DataHandle::check (void)

Query remote server or local file system to check if object is accessible. If possible this function will also try to fill meta information about object in associated DataPoint.

#### 3.4.4.5 failure\_reason\_t DataHandle::failure\_reason (void) [inline]

Returns reason of transfer failure.

#### 3.4.4.6 bool DataHandle::list\_files (list< DataPoint::FileInfo > & files, bool resolve = true)

List files in directory or service (URL must point to directory/group/service access point).

**Parameters:**

*files* will contain list of file names and optionally their attributes.

*resolve* if false no information about attributes will be retrieved.

**3.4.4.7 void DataHandle::out\_of\_order (bool *v*)**

Allow/disallow DataHandle to produce scattered data during 'reading' operation.

**Parameters:**

*v* true if allowed.

**3.4.4.8 bool DataHandle::out\_of\_order (void)**

Returns true if URL can accept scattered data (like arbitrary access to local file) for 'writing' operation.

**3.4.4.9 void DataHandle::passive (bool *v*)**

Request passive transfers for FTP-like protocols.

**Parameters:**

*true* to request.

**3.4.4.10 void DataHandle::range (unsigned long long int *start* = 0, unsigned long long int *end* = 0)**  
[inline]

Set range of bytes to retrieve. Default values correspond to whole file.

**3.4.4.11 bool DataHandle::remove (void)**

Remove/delete object at URL.

**3.4.4.12 bool DataHandle::secure (void)**

Check if heavy security during data transfer is allowed.

**3.4.4.13 void DataHandle::secure (bool *v*)**

Allow/disallow heavy security during data transfer.

**Parameters:**

*v* true if allowed (default is true only for gsiftp://).

**3.4.4.14 bool DataHandle::start\_reading (DataBufferPar & buffer)**

Start reading data from URL. Separate thread to transfer data will be created. No other operation can be performed while 'reading' is in progress.

**Parameters:**

*buffer* operation will use this buffer to put information into. Should not be destroyed before stop\_reading was called and returned. Returns true on success.

**3.4.4.15 bool DataHandle::start\_writing (DataBufferPar & buffer, DataCallback \* space\_cb = NULL)**

Start writing data to URL. Separate thread to transfer data will be created. No other operation can be performed while 'writing' is in progress.

**Parameters:**

*buffer* operation will use this buffer to get information from. Should not be destroyed before stop\_writing was called and returned. *space\_cb* callback which is called if there is not enough to space storing data. Currently implemented only for `file:///` URL. Returns true on success.

**3.4.4.16 bool DataHandle::stop\_reading (void)**

Stop reading. It MUST be called after corresponding start\_reading method. Either after whole data is transfered or to cancel transfer. Use 'buffer' object to find out when data is transfered.

**3.4.4.17 bool DataHandle::stop\_writing (void)**

Same as stop\_reading but for corresponding start\_writing.

The documentation for this class was generated from the following file:

- datahandle.h

## 3.5 DataHandle::analyze\_t Class Reference

```
#include <datahandle.h>
```

### Public Attributes

- long int **bufsize**
- int **bufnum**
- bool **cache**
- bool **local**
- bool **readonly**

### 3.5.1 Detailed Description

Structure used in [analyze\(\)](#) call.

#### Parameters:

- bufsize* returns suggested size of buffers to store data.
- bufnum* returns suggested number of buffers.
- cache* returns true if url is allowed to be cached.
- local* return true if URL is accessed locally ([file://](#))

The documentation for this class was generated from the following file:


- datahandle.h



## 3.6 DataMove Class Reference

```
#include <datamove.h>
```

Inheritance diagram for DataMove::



### Public Types

- typedef void(\* **callback**)(DataMove \*, DataMove::result, void \*)
- enum **result** {  
     **success** = 0, **read\_acquire\_error** = 1, **write\_acquire\_error** = 2, **read\_resolve\_error** = 3,  
     **write\_resolve\_error** = 4, **preregister\_error** = 5, **read\_start\_error** = 6, **write\_start\_error** = 7,  
     **read\_error** = 8, **write\_error** = 9, **transfer\_error** = 10, **read\_stop\_error** = 11,  
     **write\_stop\_error** = 12, **postregister\_error** = 13, **cache\_error** = 14, **system\_error** = 15,  
     **credentials\_expired\_error** = 16, **undefined\_error** = -1 }

### Public Member Functions

- DataMove (void)
- ~DataMove (void)
- result Transfer (DataPoint &source, DataPoint &destination, DataCache &cache, const UriMap &map, callback cb=NULL, void \*arg=NULL, const char \*prefix=NULL)
- result Transfer (DataPoint &source, DataPoint &destination, DataCache &cache, const UriMap &map, unsigned long long int min\_speed, time\_t min\_speed\_time, unsigned long long int min\_average\_speed, time\_t max\_inactivity\_time, callback cb=NULL, void \*arg=NULL, const char \*prefix=NULL)
- bool verbose (void)
- void verbose (bool)
- void verbose (const string &prefix)
- bool retry (void)
- void retry (bool)
- void secure (bool)
- void passive (bool)
- void force\_to\_meta (bool)
- bool checks (void)
- void checks (bool v)
- void set\_default\_min\_speed (unsigned long long int min\_speed, time\_t min\_speed\_time)
- void set\_default\_min\_average\_speed (unsigned long long int min\_average\_speed)
- void set\_default\_max\_inactivity\_time (time\_t max\_inactivity\_time)
- void set\_progress\_indicator (DataSpeed::show\_progress\_t func=NULL)

## Static Public Member Functions

- `const char * get_result_string (result r)`

### 3.6.1 Detailed Description

A purpose of this class is to provide service for moves data between 2 locations specified by URLs. It's main action is represented by methods [DataMove::Transfer](#).

### 3.6.2 Member Enumeration Documentation

#### 3.6.2.1 enum [DataMove::result](#)

Error code/failure reason.

##### Enumeration values:

- success* Operation completed successfully.
- read\_acquire\_error* Source is bad URL or can't be used due to some reason.
- write\_acquire\_error* Destination is bad URL or can't be used due to some reason.
- read\_resolve\_error* Resolving of meta-URL for source failed.
- write\_resolve\_error* Resolving of meta-URL for destination failed.
- preregister\_error* First stage of registration of meta-URL failed.
- read\_start\_error* Can't read from source.
- write\_start\_error* Can't write to destination.
- read\_error* Failed while reading from source.
- write\_error* Failed while writing to destination.
- transfer\_error* Failed while transferring data (mostly timeout).
- read\_stop\_error* Failed while finishing reading from source.
- write\_stop\_error* Failed while finishing writing to destination.
- postregister\_error* Last stage of registration of meta-URL failed.
- cache\_error* Error in caching procedure.
- system\_error* Some system function returned unexpected error.
- credentials\_expired\_error* Error due to provided credentials are expired.
- undefined\_error* Unknown/undefined error.

### 3.6.3 Constructor & Destructor Documentation

#### 3.6.3.1 [DataMove::DataMove](#) (void)

Constructor.

#### 3.6.3.2 [DataMove::~DataMove](#) (void)

Destructor.

## 3.6.4 Member Function Documentation

### 3.6.4.1 void DataMove::checks (bool *v*)

Set if to make check for existence of remote file (and probably other checks too) before initiating 'reading' and 'writing' operations.

**Parameters:**

*v* true if allowed (default is true).

### 3.6.4.2 bool DataMove::checks (void)

Check if check for existence of remote file is done before initiating 'reading' and 'writing' operations.

### 3.6.4.3 void DataMove::force\_to\_meta (bool)

Set if file should be transferred and registered even if such LFN is already registered and source is not one of registered locations.

### 3.6.4.4 void DataMove::passive (bool)

Set if passive transfer should be used for FTP-like transfers.

### 3.6.4.5 void DataMove::retry (bool)

Set if transfer will be retried in case of failure.

### 3.6.4.6 bool DataMove::retry (void)

Check if transfer will be retried in case of failure.

### 3.6.4.7 void DataMove::secure (bool)

Set if high level of security (encryption) will be used during transfer if available.

### 3.6.4.8 void DataMove::set\_default\_max\_inactivity\_time (time\_t *max\_inactivity\_time*) [inline]

Set maximal allowed time for waiting for any data. For more information see description of [DataSpeed](#) class.

### 3.6.4.9 void DataMove::set\_default\_min\_average\_speed (unsigned long long int *min\_average\_speed*) [inline]

Set minimal allowed average transfer speed (default is 0 averaged over whole time of transfer. For more information see description of [DataSpeed](#) class.

### 3.6.4.10 void DataMove::set\_default\_min\_speed (unsigned long long int *min\_speed*, time\_t *min\_speed\_time*) [inline]

Set minimal allowed transfer speed (default is 0) to 'min\_speed'. If speed drops below for time longer than 'min\_speed\_time' error is raised. For more information see description of [DataSpeed](#) class.

### 3.6.4.11 result DataMove::Transfer ([DataPoint](#) & *source*, [DataPoint](#) & *destination*, [DataCache](#) & *cache*, const [UrlMap](#) & *map*, unsigned long long int *min\_speed*, time\_t *min\_speed\_time*, unsigned long long int *min\_average\_speed*, time\_t *max\_inactivity\_time*, callback *cb* = NULL, void \* *arg* = NULL, const char \* *prefix* = NULL)

Initiates transfer from 'source' to 'destination'.

#### Parameters:

*min\_speed* minimal allowed current speed.

*min\_speed\_time* time for which speed should be less than 'min\_speed' before transfer fails.

*min\_average\_speed* minimal allowed average speed.

*max\_inactivity\_time* time for which should be no activity before transfer fails.

### 3.6.4.12 result DataMove::Transfer ([DataPoint](#) & *source*, [DataPoint](#) & *destination*, [DataCache](#) & *cache*, const [UrlMap](#) & *map*, callback *cb* = NULL, void \* *arg* = NULL, const char \* *prefix* = NULL)

Initiates transfer from 'source' to 'destination'.

#### Parameters:

*source* source URL.

*destination* destination URL.

*cache* controls caching of downloaded files (if destination url is "file:///"). If caching is not needed default constructor [DataCache\(\)](#) can be used.

*map* URL mapping/conversion table (for 'source' URL).

*cb* ifnot NULL, transfer is done in separate thread and 'cb' is called after transfer completes/fails.

*arg* passed to 'cb'.

*prefix* if 'verbose' is activated this information will be printed before each line representing current transfer status.

### 3.6.4.13 void DataMove::verbose (const string & *prefix*)

Activate printing information about transfer status.

#### Parameters:

*prefix* use this string if 'prefix' in [DataMove::Transfer](#) is NULL.

### 3.6.4.14 void DataMove::verbose (bool)

Activate printing information about transfer status.

**3.6.4.15 bool DataMove::verbose (void)**

Check if printing information about transfer status is activated.

The documentation for this class was generated from the following file:


- datamove.h

## 3.7 DataMovePar Class Reference

Wrapper around [DataMove](#) class to handle few transfers at once.

```
#include <datamovepar.h>
```

Inheritance diagram for DataMovePar::



### Public Member Functions

- [DataMovePar](#) (void)
- [~DataMovePar](#) (void)
- bool [Add](#) (const char \*source\_url, const char \*destination\_url)
- bool [Get](#) (string &source\_url, string &destination\_url, [result](#) &res)
- bool [Transfer](#) (int num=5)
- bool [Transfer](#) ([DataCache](#) cache, const UrlMap &map, int num=5)

### 3.7.1 Detailed Description

Wrapper around [DataMove](#) class to handle few transfers at once.

### 3.7.2 Constructor & Destructor Documentation

#### 3.7.2.1 DataMovePar::DataMovePar (void)

Constructor.

#### 3.7.2.2 DataMovePar::~~DataMovePar (void)

Destructor. Object can't be destroyed while there is any transfer in progress.

### 3.7.3 Member Function Documentation

#### 3.7.3.1 bool DataMovePar::Add (const char \* source\_url, const char \* destination\_url)

Add one more source and destination pair to list of handled transfers.

##### Parameters:

*source\_url* URL (or meta-URL) of source file

*destination\_url* URL (or meta-URL) of destination file

**3.7.3.2 bool DataMovePar::Get (string & *source\_url*, string & *destination\_url*, [result](#) & *res*)**

Get source and destination pair from list with result of transfer

**Parameters:**

*source\_url* on exit contains URL (or meta-URL) of source file  
*destination\_url* on exit contains URL (or meta-URL) of destination file  
*res* result of operation

**3.7.3.3 bool DataMovePar::Transfer ([DataCache](#) *cache*, const UrlMap & *map*, int *num* = 5)**

Perform transfer

**Parameters:**

*cache* to control data caching (use default constructor for no caching)  
*map* to change/map source URLs (use default constructor for no mapping)  
*num* number of simultaneous transfers

**3.7.3.4 bool DataMovePar::Transfer (int *num* = 5)**

Perform transfer

**Parameters:**

*num* number of simultaneous transfers


The documentation for this class was generated from the following file:

- datamovepar.h

## 3.8 DataPoint Class Reference

```
#include <datapoint.h>
```

Inheritance diagram for DataPoint::



### Public Member Functions

- [DataPoint](#) (const char \*url)
- [DataPoint](#) \* **Instance** (void)
- const [DataPoint](#) \* **constInstance** (void) const
- virtual bool [meta\\_resolve](#) (bool source)
- virtual bool [meta\\_resolve](#) (bool source, const UrlMap &maps)
- virtual bool [meta\\_preregister](#) (bool replication, bool force=false)
- virtual bool [meta\\_postregister](#) (bool replication, bool failure)
- virtual bool [meta\\_preunregister](#) (bool replication)
- virtual bool [meta\\_unregister](#) (bool all)
- virtual bool [list\\_files](#) (list< [DataPoint::FileInfo](#) > &files, bool resolve=true)
- virtual bool [get\\_info](#) ([DataPoint::FileInfo](#) &fi)
- virtual bool [meta\\_size\\_available](#) (void) const
- virtual void [meta\\_size](#) (unsigned long long int val)
- virtual void [meta\\_size\\_force](#) (unsigned long long int val)
- virtual unsigned long long int [meta\\_size](#) (void) const
- virtual bool [meta\\_checksum\\_available](#) (void) const
- virtual void [meta\\_checksum](#) (const char \*val)
- virtual void [meta\\_checksum\\_force](#) (const char \*val)
- virtual const char \* [meta\\_checksum](#) (void) const
- virtual bool [meta\\_created\\_available](#) (void) const
- virtual void [meta\\_created](#) (time\_t val)
- virtual void [meta\\_created\\_force](#) (time\_t val)
- virtual time\_t [meta\\_created](#) (void) const
- virtual bool [meta\\_validtill\\_available](#) (void) const
- virtual void [meta\\_validtill](#) (time\_t val)
- virtual void [meta\\_validtill\\_force](#) (time\_t val)
- virtual time\_t [meta\\_validtill](#) (void) const
- virtual bool [meta](#) (void) const
- virtual bool [accepts\\_meta](#) (void)
- virtual bool [provides\\_meta](#) (void)
- virtual void [meta](#) (const [DataPoint](#) &p)



- virtual bool [meta\\_compare](#) (const [DataPoint](#) &p) const
- virtual bool [meta\\_stored](#) (void)
- virtual bool [local](#) (void) const
- virtual bool [map](#) (const UriMap &maps)
- virtual bool [sort](#) (const UriMap &maps)
- virtual **operator bool** (void) const
- virtual bool **operator!** (void) const
- virtual const char \* [current\\_location](#) (void) const
- virtual const char \* [current\\_meta\\_location](#) (void) const
- virtual bool [next\\_location](#) (void)
- virtual bool [have\\_location](#) (void) const
- virtual bool [have\\_locations](#) (void) const
- virtual bool [remove\\_location](#) (void)
- virtual bool [remove\\_locations](#) (const [DataPoint](#) &p)
- virtual int [tries](#) (void)
- virtual void [tries](#) (int n)
- virtual string [base\\_url](#) (void) const
- virtual string [canonic\\_url](#) (void) const
- virtual const char \* [lfn](#) (void) const
- virtual bool [add\\_location](#) (const char \*meta, const char \*loc)

## Static Public Member Functions

- bool [AddProtocol](#) (constructor\_t constructor)
- [DataPoint](#) \* **CreateInstance** (const char \*url)

## Protected Member Functions

- virtual bool **process\_meta\_url** (void)

### 3.8.1 Detailed Description

[DataPoint](#) is an abstraction of URL. It can handle URLs of type [file://](#), [ftp://](#), [gsiftp://](#), [http://](#), [https://](#), [httpg://](#) (HTTP over GSI), [se://](#) (NG web service over HTTPG) and meta-URLs (URLs of Infexing Services) [rc://](#), [rls://](#). [DataPoint](#) provides means to resolve meta-URL into multiple URLs and to loop through them. [DataPoint](#) is both base virtual class and wrapper. It's implementation provides only redirection methods and type definitions.

### 3.8.2 Constructor & Destructor Documentation

#### 3.8.2.1 [DataPoint::DataPoint](#) (const char \* url)

Constructor requires URL or meta-URL to be provided.

### 3.8.3 Member Function Documentation

#### 3.8.3.1 **virtual bool DataPoint::accepts\_meta (void)** [virtual]

If endpoint can have any use from meta information.

Reimplemented in [DataPointDirect](#), and [DataPointMeta](#).

#### 3.8.3.2 **virtual bool DataPoint::add\_location (const char \* *meta*, const char \* *loc*)** [virtual]

Add URL to list.

**Parameters:**

*meta* meta-name (name of location/service).

*loc* URL.

Reimplemented in [DataPointDirect](#).

#### 3.8.3.3 **bool DataPoint::AddProtocol (constructor\_t *constructor*)** [static]

Register new protocol. Any new instance of DataPoint will recognize it.

#### 3.8.3.4 **virtual string DataPoint::base\_url (void) const** [virtual]

Returns URL which was passed to constructor.

Reimplemented in [DataPointDirect](#).

#### 3.8.3.5 **virtual string DataPoint::canonic\_url (void) const** [virtual]

Returns URL which was passed to constructor with location names and options removed, port number added.

Reimplemented in [DataPointDirect](#).

#### 3.8.3.6 **virtual const char\* DataPoint::current\_location (void) const** [virtual]

Returns current (resolved) URL.

Reimplemented in [DataPointDirect](#).

#### 3.8.3.7 **virtual const char\* DataPoint::current\_meta\_location (void) const** [virtual]

Returns meta information used to create curent URL. For RC that is location's name. For RLS that is equal to pfn.

Reimplemented in [DataPointDirect](#).

#### 3.8.3.8 **virtual bool DataPoint::get\_info (DataPoint::FileInfo & *fi*)** [virtual]

Retrieve properties of object pointed by meta-URL of DataPoint object. It works only for meta-URL.

**Parameters:**

*fi* contains retrieved information.

Reimplemented in [DataPointDirect](#), and [DataPointMeta](#).

**3.8.3.9 virtual bool DataPoint::have\_location (void) const** [virtual]

Returns false if out of retries.

Reimplemented in [DataPointDirect](#).

**3.8.3.10 virtual bool DataPoint::have\_locations (void) const** [virtual]

Returns true if number of resolved URLs is not 0.

Reimplemented in [DataPointDirect](#).

**3.8.3.11 virtual const char\* DataPoint::lfn (void) const** [virtual]

Returns name which is given to file in Indexing Service (aka LFN).

Reimplemented in [DataPointMeta](#).

**3.8.3.12 virtual bool DataPoint::list\_files (list< [DataPoint::FileInfo](#) > &files, bool resolve = true)** [virtual]

Obtain information about objects and their properties available under meta-URL of DataPoint object. It works only for meta-URL.

**Parameters:**

*files* list of obtained objects.

*resolve* if false, do not try to obtain properties of objects.

Reimplemented in [DataPointDirect](#).

**3.8.3.13 virtual bool DataPoint::local (void) const** [virtual]

Check if file is local (URL is something like `file://`).

Reimplemented in [DataPointDirect](#).

**3.8.3.14 virtual bool DataPoint::map (const UrlMap &maps)** [virtual]

Map url (change it) according to table provided in maps.

**Parameters:**

*maps* mapping information.

Reimplemented in [DataPointDirect](#).

**3.8.3.15 virtual void DataPoint::meta (const [DataPoint](#) & *p*) [virtual]**

Acquire meta-information from another object. Defined values are not overwritten.

**Parameters:**

*p* object from which information is taken.

Reimplemented in [DataPointDirect](#).

**3.8.3.16 virtual bool DataPoint::meta (void) const [virtual]**

Check if URL is meta-URL.

Reimplemented in [DataPointDirect](#), and [DataPointMeta](#).

**3.8.3.17 virtual const char\* DataPoint::meta\_checksum (void) const [virtual]**

Get value of meta-information 'checksum'.

Reimplemented in [DataPointDirect](#).

**3.8.3.18 virtual void DataPoint::meta\_checksum (const char \* *val*) [virtual]**

Set value of meta-information 'checksum' if not already set.

Reimplemented in [DataPointDirect](#).

**3.8.3.19 virtual bool DataPoint::meta\_checksum\_available (void) const [virtual]**

Check if meta-information 'checksum' is available.

Reimplemented in [DataPointDirect](#).

**3.8.3.20 virtual void DataPoint::meta\_checksum\_force (const char \* *val*) [virtual]**

Set value of meta-information 'checksum'.

Reimplemented in [DataPointDirect](#).

**3.8.3.21 virtual bool DataPoint::meta\_compare (const [DataPoint](#) & *p*) const [virtual]**

are not used for comparison. Default result is 'true'.

**Parameters:**

*p* object to which compare.

Reimplemented in [DataPointDirect](#).

**3.8.3.22 virtual time\_t DataPoint::meta\_created (void) const [virtual]**

Get value of meta-information 'creation/modification time'.

Reimplemented in [DataPointDirect](#).

**3.8.3.23 virtual void DataPoint::meta\_created (time\_t val) [virtual]**

Set value of meta-information 'creation/modification time' if not already set.

Reimplemented in [DataPointDirect](#).

**3.8.3.24 virtual bool DataPoint::meta\_created\_available (void) const [virtual]**

Check if meta-information 'creation/modification time' is available.

Reimplemented in [DataPointDirect](#).

**3.8.3.25 virtual void DataPoint::meta\_created\_force (time\_t val) [virtual]**

Set value of meta-information 'creation/modification time'.

Reimplemented in [DataPointDirect](#).

**3.8.3.26 virtual bool DataPoint::meta\_postregister (bool replication, bool failure) [virtual]**

Used for same purpose as meta\_preregister. Should be called after actual transfer of file successfully finished.

**Parameters:**

*replication* if true then file is being replicated between 2 locations registered in Indexing Service under same name.

*failure* not used.

Reimplemented in [DataPointDirect](#), and [DataPointMeta](#).

**3.8.3.27 virtual bool DataPoint::meta\_preregister (bool replication, bool force = false) [virtual]**

This function registers physical location of file into Indexing Service. It should be called \*before\* actual transfer to that location happens.

**Parameters:**

*replication* if true then file is being replicated between 2 locations registered in Indexing Service under same name.

*force* if true, perform registration of new file even if it already exists. Should be used to fix failures in Indexing Service.

Reimplemented in [DataPointDirect](#), and [DataPointMeta](#).

**3.8.3.28 virtual bool DataPoint::meta\_preunregister (bool replication) [virtual]**

Should be called if file transfer failed. It removes changes made by meta\_preregister.

Reimplemented in [DataPointDirect](#), and [DataPointMeta](#).

**3.8.3.29 virtual bool DataPoint::meta\_resolve (bool *source*, const UrlMap & *maps*)** [virtual]

Resolve meta-URL into list of ordinary URLs and obtain meta-information about file. Also sort obtained list so that URLs mentioned in UrlMap object are placed first. This is used during transfer to access local locations first.

**Parameters:**

*maps* list of mappings of remote URLs to (potentially) local locations.

Reimplemented in [DataPointDirect](#), and [DataPointMeta](#).

**3.8.3.30 virtual bool DataPoint::meta\_resolve (bool *source*)** [virtual]

Resolve meta-URL into list of ordinary URLs and obtain meta-information about file. Can be called for object representing ordinary URL or already resolved object.

**Parameters:**

*source* true if DataPoint object represents source of information

Reimplemented in [DataPointDirect](#), and [DataPointMeta](#).

**3.8.3.31 virtual unsigned long long int DataPoint::meta\_size (void) const** [virtual]

Get value of meta-information 'size'.

Reimplemented in [DataPointDirect](#).

**3.8.3.32 virtual void DataPoint::meta\_size (unsigned long long int *val*)** [virtual]

Set value of meta-information 'size' if not already set.

Reimplemented in [DataPointDirect](#).

**3.8.3.33 virtual bool DataPoint::meta\_size\_available (void) const** [virtual]

Check if meta-information 'size' is available.

Reimplemented in [DataPointDirect](#).

**3.8.3.34 virtual void DataPoint::meta\_size\_force (unsigned long long int *val*)** [virtual]

Set value of meta-information 'size'.

Reimplemented in [DataPointDirect](#).

**3.8.3.35 virtual bool DataPoint::meta\_stored (void)** [virtual]

Check if file is registered in Indexing Service. Proper value is obtainable only after meta-resolve.

Reimplemented in [DataPointDirect](#), and [DataPointMeta](#).

**3.8.3.36 virtual bool DataPoint::meta\_unregister (bool *all*)** [virtual]

Remove information about file registered in Indexing Service.

**Parameters:**

*all* if true information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

Reimplemented in [DataPointDirect](#), and [DataPointMeta](#).

**3.8.3.37 virtual time\_t DataPoint::meta\_validtill (void) const** [virtual]

Get value of meta-information 'validity time'.

Reimplemented in [DataPointDirect](#).

**3.8.3.38 virtual void DataPoint::meta\_validtill (time\_t *val*)** [virtual]

Set value of meta-information 'validity time' if not already set.

Reimplemented in [DataPointDirect](#).

**3.8.3.39 virtual bool DataPoint::meta\_validtill\_available (void) const** [virtual]

Check if meta-information 'validity time' is available.

Reimplemented in [DataPointDirect](#).

**3.8.3.40 virtual void DataPoint::meta\_validtill\_force (time\_t *val*)** [virtual]

Set value of meta-information 'validity time'.

Reimplemented in [DataPointDirect](#).

**3.8.3.41 virtual bool DataPoint::next\_location (void)** [virtual]

Switch to next location in list of URLs. At last location switch to first if number of allowed retries does not exceeded. Returns false if no retries left.

Reimplemented in [DataPointDirect](#).

**3.8.3.42 virtual bool DataPoint::provides\_meta (void)** [virtual]

If endpoint can provide at least some meta information directly.

Reimplemented in [DataPointDirect](#), and [DataPointMeta](#).

**3.8.3.43 virtual bool DataPoint::remove\_location (void)** [virtual]

Remove current URL from list.

Reimplemented in [DataPointDirect](#).

**3.8.3.44 virtual bool DataPoint::remove\_locations (const [DataPoint](#) & *p*)** [virtual]

Remove locations present in another DataPoint object.

Reimplemented in [DataPointDirect](#).

**3.8.3.45 virtual bool DataPoint::sort (const UrlMap & *maps*)** [virtual]

Sort list of URLs so that those listed in mapping table are put first. It can also implement any other algorithm too.

**Parameters:**

*maps* mapping information.

Reimplemented in [DataPointDirect](#).

**3.8.3.46 virtual void DataPoint::tries (int *n*)** [virtual]

Set number of retries.

Reimplemented in [DataPointDirect](#).

**3.8.3.47 virtual int DataPoint::tries (void)** [virtual]

Returns number of retries left.

Reimplemented in [DataPointDirect](#).

The documentation for this class was generated from the following file:

- datapoint.h



## 3.9 DataPoint::FileInfo Class Reference

```
#include <datapoint.h>
```

### Public Types

- enum **Type** { **file\_type\_unknown** = 0, **file\_type\_file** = 1, **file\_type\_dir** = 2 }

### Public Member Functions

- **FileInfo** (const char \*name\_ = "")
- **operator bool** (void)

### Public Attributes

- string **name**
- list< string > **urls**
- unsigned long long int **size**
- bool **size\_available**
- string **checksum**
- bool **checksum\_available**
- time\_t **created**
- bool **created\_available**
- time\_t **valid**
- bool **valid\_available**
- Type **type**

### 3.9.1 Detailed Description

**FileInfo** stores information about file (meta-information). Although all members are public it is not desirable to modify them directly outside **DataPoint** class.

### 3.9.2 Constructor & Destructor Documentation

#### 3.9.2.1 DataPoint::FileInfo::FileInfo (const char \* name\_ = "") [inline]

File type - usually **file\_type\_file** - ordinary file.

### 3.9.3 Member Data Documentation

#### 3.9.3.1 string DataPoint::FileInfo::checksum

If size is known.

#### 3.9.3.2 bool DataPoint::FileInfo::checksum\_available

Checksum of file.

**3.9.3.3** `time_t DataPoint::FileInfo::created`

If checksum is known.

**3.9.3.4** `bool DataPoint::FileInfo::created_available`

Creation/modification time.

**3.9.3.5** `unsigned long long int DataPoint::FileInfo::size`

Physical endpoints/URLs at which file can be accessed.

**3.9.3.6** `bool DataPoint::FileInfo::size_available`

Size of file in bytes.

**3.9.3.7** `Type DataPoint::FileInfo::type`

If validity is known.

**3.9.3.8** `time_t DataPoint::FileInfo::valid`

If time is known.

**3.9.3.9** `bool DataPoint::FileInfo::valid_available`

Valid till time.


The documentation for this class was generated from the following file:

- datapoint.h

## 3.10 DataPointDirect Class Reference

```
#include <datapoint.h>
```

Inheritance diagram for DataPointDirect::



### Public Member Functions

- **DataPointDirect** (const char \*u)
- virtual **operator bool** (void) const
- virtual bool **operator!** (void) const
- virtual string **base\_url** (void) const
- virtual string **canonic\_url** (void) const
- virtual bool **meta\_size\_available** (void) const
- virtual void **meta\_size** (unsigned long long int val)
- virtual void **meta\_size\_force** (unsigned long long int val)
- virtual unsigned long long int **meta\_size** (void) const
- virtual bool **meta\_checksum\_available** (void) const
- virtual void **meta\_checksum** (const char \*val)
- virtual void **meta\_checksum\_force** (const char \*val)
- virtual const char \* **meta\_checksum** (void) const
- virtual bool **meta\_created\_available** (void) const
- virtual void **meta\_created** (time\_t val)
- virtual void **meta\_created\_force** (time\_t val)
- virtual time\_t **meta\_created** (void) const
- virtual bool **meta\_validtill\_available** (void) const
- virtual void **meta\_validtill** (time\_t val)
- virtual void **meta\_validtill\_force** (time\_t val)
- virtual time\_t **meta\_validtill** (void) const
- virtual void **meta** (const DataPoint &p)
- virtual bool **meta\_compare** (const DataPoint &p) const
- virtual bool **meta** (void) const
- virtual bool **accepts\_meta** (void)
- virtual bool **provides\_meta** (void)
- virtual bool **meta\_resolve** (bool source)
- virtual bool **meta\_resolve** (bool source, const UrlMap &maps)
- virtual bool **meta\_preregister** (bool replication, bool force=false)
- virtual bool **meta\_postregister** (bool replication, bool failure)
- virtual bool **meta\_preunregister** (bool replication)

- virtual bool [meta\\_unregister](#) (bool all)
- virtual bool [get\\_info](#) (DataPoint::FileInfo &fi)
- virtual bool [meta\\_stored](#) (void)
- virtual const char \* [current\\_location](#) (void) const
- virtual const char \* [current\\_meta\\_location](#) (void) const
- virtual bool [next\\_location](#) (void)
- virtual bool [have\\_location](#) (void) const
- virtual bool [have\\_locations](#) (void) const
- virtual bool [remove\\_location](#) (void)
- virtual bool [remove\\_locations](#) (const DataPoint &p)
- virtual bool [add\\_location](#) (const char \*meta, const char \*loc)
- virtual int [tries](#) (void)
- virtual void [tries](#) (int n)
- virtual bool [local](#) (void) const
- virtual bool [sort](#) (const UrlMap &maps)
- virtual bool [map](#) (const UrlMap &maps)
- virtual bool [list\\_files](#) (list< DataPoint::FileInfo > &files, bool resolve=true)

## Protected Attributes

- list< [Location](#) > **locations**
- list< [Location](#) >::iterator **location**
- bool **is\_valid**
- string **url**
- string **common\_url\_options**
- unsigned long long int **meta\_size\_**
- bool **meta\_size\_valid**
- string **meta\_checksum\_**
- bool **meta\_checksum\_valid**
- time\_t **meta\_created\_**
- bool **meta\_created\_valid**
- time\_t **meta\_validtill\_**
- bool **meta\_validtill\_valid**
- std::map< string, string > **meta\_attributes**
- int **tries\_left**
- GlobusModuleError **error\_mod**
- GlobusModuleGSIGSSAPI **gsi\_gssapi\_mod**

### 3.10.1 Detailed Description

DataPointDirect implements common purpose private attributes and corresponding methods suitable for any kind of URL. It should never be used directly.

### 3.10.2 Member Function Documentation

#### 3.10.2.1 virtual bool DataPointDirect::accepts\_meta (void) [inline, virtual]

If endpoint can have any use from meta information.

Reimplemented from [DataPoint](#).

Reimplemented in [DataPointMeta](#).

**3.10.2.2 virtual bool DataPointDirect::add\_location (const char \* *meta*, const char \* *loc*)**  
[virtual]

Add URL to list.

**Parameters:**

*meta* meta-name (name of location/service).

*loc* URL.

Reimplemented from [DataPoint](#).

**3.10.2.3 virtual string DataPointDirect::base\_url (void) const** [virtual]

Returns URL which was passed to constructor.

Reimplemented from [DataPoint](#).

**3.10.2.4 virtual string DataPointDirect::canonic\_url (void) const** [virtual]

Returns URL which was passed to constructor with location names and options removed, port number added.

Reimplemented from [DataPoint](#).

**3.10.2.5 virtual const char\* DataPointDirect::current\_location (void) const** [inline, virtual]

Returns current (resolved) URL.

Reimplemented from [DataPoint](#).

**3.10.2.6 virtual const char\* DataPointDirect::current\_meta\_location (void) const** [inline, virtual]

Returns meta information used to create curent URL. For RC that is location's name. For RLS that is equal to pfn.

Reimplemented from [DataPoint](#).

**3.10.2.7 virtual bool DataPointDirect::get\_info (DataPoint::FileInfo & *fi*)** [inline, virtual]

Retrieve properties of object pointed by meta-URL of [DataPoint](#) object. It works only for meta-URL.

**Parameters:**

*fi* contains retrieved information.

Reimplemented from [DataPoint](#).

Reimplemented in [DataPointMeta](#).

**3.10.2.8 virtual bool DataPointDirect::have\_location (void) const** [virtual]

Returns false if out of retries.

Reimplemented from [DataPoint](#).

**3.10.2.9 virtual bool DataPointDirect::have\_locations (void) const** [virtual]

Returns true if number of resolved URLs is not 0.

Reimplemented from [DataPoint](#).

**3.10.2.10 virtual bool DataPointDirect::list\_files (list< [DataPoint::FileInfo](#) > & files, bool resolve = true)** [inline, virtual]

Obtain information about objects and their properties available under meta-URL of [DataPoint](#) object. It works only for meta-URL.

**Parameters:**

*files* list of obtained objects.

*resolve* if false, do not try to obtain properties of objects.

Reimplemented from [DataPoint](#).

**3.10.2.11 virtual bool DataPointDirect::local (void) const** [inline, virtual]

Check if file is local (URL is something like `file://`).

Reimplemented from [DataPoint](#).

**3.10.2.12 virtual bool DataPointDirect::map (const UrlMap & maps)** [virtual]

Map url (change it) according to table provided in maps.

**Parameters:**

*maps* mapping information.

Reimplemented from [DataPoint](#).

**3.10.2.13 virtual bool DataPointDirect::meta (void) const** [inline, virtual]

Check if URL is meta-URL.

Reimplemented from [DataPoint](#).

Reimplemented in [DataPointMeta](#).

**3.10.2.14 virtual void DataPointDirect::meta (const [DataPoint](#) & p)** [inline, virtual]

Acquire meta-information from another object. Defined values are not overwritten.

**Parameters:**

*p* object from which information is taken.

Reimplemented from [DataPoint](#).

**3.10.2.15 virtual const char\* DataPointDirect::meta\_checksum (void) const** [inline, virtual]

Get value of meta-information 'checksum'.

Reimplemented from [DataPoint](#).

**3.10.2.16 virtual void DataPointDirect::meta\_checksum (const char \* val)** [inline, virtual]

Set value of meta-information 'checksum' if not already set.

Reimplemented from [DataPoint](#).

**3.10.2.17 virtual bool DataPointDirect::meta\_checksum\_available (void) const** [inline, virtual]

Check if meta-information 'checksum' is available.

Reimplemented from [DataPoint](#).

**3.10.2.18 virtual void DataPointDirect::meta\_checksum\_force (const char \* val)** [inline, virtual]

Set value of meta-information 'checksum'.

Reimplemented from [DataPoint](#).

**3.10.2.19 virtual bool DataPointDirect::meta\_compare (const [DataPoint](#) & p) const** [inline, virtual]

are not used for comparison. Default result is 'true'.

**Parameters:**

*p* object to which compare.

Reimplemented from [DataPoint](#).

**3.10.2.20 virtual time\_t DataPointDirect::meta\_created (void) const** [inline, virtual]

Get value of meta-information 'creation/modification time'.

Reimplemented from [DataPoint](#).

**3.10.2.21 virtual void DataPointDirect::meta\_created (time\_t val)** [inline, virtual]

Set value of meta-information 'creation/modification time' if not already set.

Reimplemented from [DataPoint](#).

**3.10.2.22 virtual bool DataPointDirect::meta\_created\_available (void) const** [inline, virtual]

Check if meta-information 'creation/modification time' is available.

Reimplemented from [DataPoint](#).

### 3.10.2.23 **virtual void DataPointDirect::meta\_created\_force (time\_t val)** [inline, virtual]

Set value of meta-information 'creation/modification time'.

Reimplemented from [DataPoint](#).

### 3.10.2.24 **virtual bool DataPointDirect::meta\_postregister (bool replication, bool failure)** [inline, virtual]

Used for same purpose as meta\_preregister. Should be called after actual transfer of file successfully finished.

#### Parameters:

**replication** if true then file is being replicated between 2 locations registered in Indexing Service under same name.

**failure** not used.

Reimplemented from [DataPoint](#).

Reimplemented in [DataPointMeta](#).

### 3.10.2.25 **virtual bool DataPointDirect::meta\_preregister (bool replication, bool force = false)** [inline, virtual]

This function registers physical location of file into Indexing Service. It should be called \*before\* actual transfer to that location happens.

#### Parameters:

**replication** if true then file is being replicated between 2 locations registered in Indexing Service under same name.

**force** if true, perform registration of new file even if it already exists. Should be used to fix failures in Indexing Service.

Reimplemented from [DataPoint](#).

Reimplemented in [DataPointMeta](#).

### 3.10.2.26 **virtual bool DataPointDirect::meta\_preunregister (bool replication)** [inline, virtual]

Should be called if file transfer failed. It removes changes made by meta\_preregister.

Reimplemented from [DataPoint](#).

Reimplemented in [DataPointMeta](#).

### 3.10.2.27 **virtual bool DataPointDirect::meta\_resolve (bool source, const UrlMap & maps)** [inline, virtual]

Resolve meta-URL into list of ordinary URLs and obtain meta-information about file. Also sort obtained list so that URLs mentioned in UrlMap object are placed first. This is used during transfer to access local locations first.



**Parameters:**

*maps* list of mappings of remote URLs to (potentially) local locations.

Reimplemented from [DataPoint](#).

Reimplemented in [DataPointMeta](#).

**3.10.2.28 virtual bool DataPointDirect::meta\_resolve (bool *source*)** [inline, virtual]

Resolve meta-URL into list of ordinary URLs and obtain meta-information about file. Can be called for object representing ordinary URL or already resolved object.

**Parameters:**

*source* true if [DataPoint](#) object represents source of information

Reimplemented from [DataPoint](#).

Reimplemented in [DataPointMeta](#).

**3.10.2.29 virtual unsigned long long int DataPointDirect::meta\_size (void) const** [inline, virtual]

Get value of meta-information 'size'.

Reimplemented from [DataPoint](#).

**3.10.2.30 virtual void DataPointDirect::meta\_size (unsigned long long int *val*)** [inline, virtual]

Set value of meta-information 'size' if not already set.

Reimplemented from [DataPoint](#).

**3.10.2.31 virtual bool DataPointDirect::meta\_size\_available (void) const** [inline, virtual]

Check if meta-information 'size' is available.

Reimplemented from [DataPoint](#).

**3.10.2.32 virtual void DataPointDirect::meta\_size\_force (unsigned long long int *val*)** [inline, virtual]

Set value of meta-information 'size'.

Reimplemented from [DataPoint](#).

**3.10.2.33 virtual bool DataPointDirect::meta\_stored (void)** [inline, virtual]

Check if file is registered in Indexing Service. Proper value is obtainable only after meta-resolve.

Reimplemented from [DataPoint](#).

Reimplemented in [DataPointMeta](#).

**3.10.2.34 virtual bool DataPointDirect::meta\_unregister (bool *all*)** [inline, virtual]

Remove information about file registered in Indexing Service.

**Parameters:**

*all* if true information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

Reimplemented from [DataPoint](#).

Reimplemented in [DataPointMeta](#).

**3.10.2.35 virtual time\_t DataPointDirect::meta\_validtill (void) const** [inline, virtual]

Get value of meta-information 'validity time'.

Reimplemented from [DataPoint](#).

**3.10.2.36 virtual void DataPointDirect::meta\_validtill (time\_t *val*)** [inline, virtual]

Set value of meta-information 'validity time' if not already set.

Reimplemented from [DataPoint](#).

**3.10.2.37 virtual bool DataPointDirect::meta\_validtill\_available (void) const** [inline, virtual]

Check if meta-information 'validity time' is available.

Reimplemented from [DataPoint](#).

**3.10.2.38 virtual void DataPointDirect::meta\_validtill\_force (time\_t *val*)** [inline, virtual]

Set value of meta-information 'validity time'.

Reimplemented from [DataPoint](#).

**3.10.2.39 virtual bool DataPointDirect::next\_location (void)** [virtual]

Switch to next location in list of URLs. At last location switch to first if number of allowed retries does not exceeded. Returns false if no retries left.

Reimplemented from [DataPoint](#).

**3.10.2.40 virtual bool DataPointDirect::provides\_meta (void)** [inline, virtual]

If endpoint can provide at least some meta information directly.

Reimplemented from [DataPoint](#).

Reimplemented in [DataPointMeta](#).

**3.10.2.41 virtual bool DataPointDirect::remove\_location (void) [virtual]**

Remove current URL from list.

Reimplemented from [DataPoint](#).

**3.10.2.42 virtual bool DataPointDirect::remove\_locations (const [DataPoint](#) & p) [virtual]**

Remove locations present in another [DataPoint](#) object.

Reimplemented from [DataPoint](#).

**3.10.2.43 virtual bool DataPointDirect::sort (const UrlMap & maps) [virtual]**

Sort list of URLs so that those listed in mapping table are put first. It can also implement any other algorithm too.

**Parameters:**

*maps* mapping information.

Reimplemented from [DataPoint](#).

**3.10.2.44 virtual void DataPointDirect::tries (int n) [inline, virtual]**

Set number of retries.

Reimplemented from [DataPoint](#).

**3.10.2.45 virtual int DataPointDirect::tries (void) [inline, virtual]**

Returns number of retries left.

Reimplemented from [DataPoint](#).

**3.10.3 Member Data Documentation****3.10.3.1 string [DataPointDirect::common\\_url\\_options](#) [protected]**

Initial URL.

**3.10.3.2 list<[Location](#)>::iterator [DataPointDirect::location](#) [protected]**

List of locations at which file can be probably found.

**3.10.3.3 unsigned long long int [DataPointDirect::meta\\_size\\_](#) [protected]**

URL options to be added to all derived URLs.

The documentation for this class was generated from the following file:

- datapoint.h

## 3.11 DataPointDirect::Location Class Reference

```
#include <datapoint.h>
```

### Public Member Functions

- **Location** (const char \*url\_)
- **Location** (const char \*meta\_, const char \*url\_, bool existing\_=true)
- **Location** (const string &url\_)
- **Location** (const string &meta\_, const string &url\_)

### Public Attributes

- string **meta**
- string **url**
- bool **existing**
- void \* **arg**

### Friends

- class [DataPointDirect](#)

#### 3.11.1 Detailed Description

DataPointDirect::Location represents physical service at which files are located aka "base URL" including it's name (as given in Indexing Service). /// Currently it is used only internally by classes derived from [DataPointDirect](#) class and for printing debug information.


The documentation for this class was generated from the following file:

- datapoint.h

## 3.12 DataPointMeta Class Reference

```
#include <datapoint.h>
```

Inheritance diagram for DataPointMeta::



### Public Member Functions

- **DataPointMeta** (const char \*u)
- virtual bool [meta](#) (void) const
- virtual bool [accepts\\_meta](#) (void)
- virtual bool [provides\\_meta](#) (void)
- virtual bool [meta\\_resolve](#) (bool source)
- virtual bool [meta\\_resolve](#) (bool source, const UrlMap &maps)
- virtual bool [meta\\_preregister](#) (bool replication, bool force=false)
- virtual bool [meta\\_postregister](#) (bool replication, bool failure)
- virtual bool [meta\\_preunregister](#) (bool replication)
- virtual bool [meta\\_unregister](#) (bool all)
- virtual bool [get\\_info](#) (DataPoint::FileInfo &fi)
- virtual bool [meta\\_stored](#) (void)
- virtual const char \* [lfn](#) (void) const

### Protected Member Functions

- virtual bool [process\\_meta\\_url](#) (void)
- bool [extract\\_meta\\_attributes](#) (string &lfn)

### Protected Attributes

- bool [is\\_metaexisting](#)
- bool [is\\_resolved](#)
- string [meta\\_service\\_url](#)
- string [meta\\_lfn](#)

#### 3.12.1 Detailed Description

DataPointMeta complements [DataPointDirect](#) with attributes common for meta-URLs. It should never be used directly.

## 3.12.2 Member Function Documentation

### 3.12.2.1 `virtual bool DataPointMeta::accepts_meta (void)` `[inline, virtual]`

If endpoint can have any use from meta information.

Reimplemented from [DataPointDirect](#).

### 3.12.2.2 `virtual bool DataPointMeta::get_info (DataPoint::FileInfo &fi)` `[virtual]`

Retrieve properties of object pointed by meta-URL of [DataPoint](#) object. It works only for meta-URL.

#### Parameters:

*fi* contains retrieved information.

Reimplemented from [DataPointDirect](#).

### 3.12.2.3 `virtual const char* DataPointMeta::lfn (void) const` `[inline, virtual]`

Returns name which is given to file in Indexing Service (aka LFN).

Reimplemented from [DataPoint](#).

### 3.12.2.4 `virtual bool DataPointMeta::meta (void) const` `[inline, virtual]`

Check if URL is meta-URL.

Reimplemented from [DataPointDirect](#).

### 3.12.2.5 `virtual bool DataPointMeta::meta_postregister (bool replication, bool failure)` `[inline, virtual]`

Used for same purpose as meta\_preregister. Should be called after actual transfer of file successfully finished.

#### Parameters:

*replication* if true then file is being replicated between 2 locations registered in Indexing Service under same name.

*failure* not used.

Reimplemented from [DataPointDirect](#).

### 3.12.2.6 `virtual bool DataPointMeta::meta_preregister (bool replication, bool force = false)` `[inline, virtual]`

This function registers physical location of file into Indexing Service. It should be called *\*before\** actual transfer to that location happens.

#### Parameters:

*replication* if true then file is being replicated between 2 locations registered in Indexing Service under same name.

*force* if true, perform registration of new file even if it already exists. Should be used to fix failures in Indexing Service.

Reimplemented from [DataPointDirect](#).

#### 3.12.2.7 virtual bool DataPointMeta::meta\_preunregister (bool *replication*) [inline, virtual]

Should be called if file transfer failed. It removes changes made by meta\_preregister.

Reimplemented from [DataPointDirect](#).

#### 3.12.2.8 virtual bool DataPointMeta::meta\_resolve (bool *source*, const UriMap & *maps*) [virtual]

Resolve meta-URL into list of ordinary URLs and obtain meta-information about file. Also sort obtained list so that URLs mentioned in UriMap object are placed first. This is used during transfer to access local locations first.

**Parameters:**

*maps* list of mappings of remote URLs to (potentially) local locations.

Reimplemented from [DataPointDirect](#).

#### 3.12.2.9 virtual bool DataPointMeta::meta\_resolve (bool *source*) [inline, virtual]

Resolve meta-URL into list of ordinary URLs and obtain meta-information about file. Can be called for object representing ordinary URL or already resolved object.

**Parameters:**

*source* true if [DataPoint](#) object represents source of information

Reimplemented from [DataPointDirect](#).

#### 3.12.2.10 virtual bool DataPointMeta::meta\_stored (void) [inline, virtual]

Check if file is registered in Indexing Service. Proper value is obtainable only after meta-resolve.

Reimplemented from [DataPointDirect](#).

#### 3.12.2.11 virtual bool DataPointMeta::meta\_unregister (bool *all*) [inline, virtual]

Remove information about file registered in Indexing Service.

**Parameters:**

*all* if true information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

Reimplemented from [DataPointDirect](#).

**3.12.2.12 virtual bool DataPointMeta::provides\_meta (void)** [inline, virtual]

If endpoint can provide at least some meta information directly.

Reimplemented from [DataPointDirect](#).

The documentation for this class was generated from the following file:

- datapoint.h



## 3.13 DataSpeed Class Reference

```
#include <dataspeed.h>
```

### Public Types

- typedef void(\* **show\_progress\_t**)(FILE \*o, const char \*s, unsigned int t, unsigned long long int all, unsigned long long int max, double instant, double average)

### Public Member Functions

- [DataSpeed](#) (time\_t base=DATASPEED\_AVERAGING\_PERIOD)
- [DataSpeed](#) (unsigned long long int min\_speed, time\_t min\_speed\_time, unsigned long long int min\_average\_speed, time\_t max\_inactivity\_time, time\_t base=DATASPEED\_AVERAGING\_PERIOD)
- [~DataSpeed](#) (void)
- void [verbose](#) (bool val)
- void [verbose](#) (const string &prefix)
- bool [verbose](#) (void)
- void [set\\_min\\_speed](#) (unsigned long long int min\_speed, time\_t min\_speed\_time)
- void [set\\_min\\_average\\_speed](#) (unsigned long long int min\_average\_speed)
- void [set\\_max\\_inactivity\\_time](#) (time\_t max\_inactivity\_time)
- void [set\\_base](#) (time\_t base\_=DATASPEED\_AVERAGING\_PERIOD)
- void [set\\_max\\_data](#) (unsigned long long int max=0)
- void [set\\_progress\\_indicator](#) (show\_progress\_t func=NULL)
- void [reset](#) (void)
- bool [transfer](#) (unsigned long long int n=0)
- void [hold](#) (bool disable)
- bool [min\\_speed\\_failure](#) ()
- bool [min\\_average\\_speed\\_failure](#) ()
- bool [max\\_inactivity\\_time\\_failure](#) ()
- unsigned long long int [transferred\\_size](#) (void)

#### 3.13.1 Detailed Description

Keeps track of average and instantaneous speed. Also detects data transfer inactivity and other transfer timeouts.

#### 3.13.2 Constructor & Destructor Documentation

##### 3.13.2.1 DataSpeed::DataSpeed (time\_t *base* = DATASPEED\_AVERAGING\_PERIOD)

Constructor

##### Parameters:

*base* time period used to average values (default 1 minute).

### 3.13.2.2 DataSpeed::DataSpeed (unsigned long long int *min\_speed*, time\_t *min\_speed\_time*, unsigned long long int *min\_average\_speed*, time\_t *max\_inactivity\_time*, time\_t *base* = DATASPEED\_AVERAGING\_PERIOD)

Constructor

#### Parameters:

*base* time period used to average values (default 1 minute).

*min\_speed* minimal allowed speed (Butes per second). If speed drops and holds below threshold for *min\_speed\_time\_* seconds error is triggered.

*min\_speed\_time*

*min\_average\_speed\_* minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

*max\_inactivity\_time* - if no data is passing for specified amount of time (seconds), error is triggered.

### 3.13.2.3 DataSpeed::~~DataSpeed (void)

Destructor.

## 3.13.3 Member Function Documentation

### 3.13.3.1 void DataSpeed::hold (bool *disable*)

Turn off speed control.

#### Parameters:

*disable* true to turn off.

### 3.13.3.2 bool DataSpeed::max\_inactivity\_time\_failure () [inline]

Check if maximal inactivity time error was triggered.

### 3.13.3.3 bool DataSpeed::min\_average\_speed\_failure () [inline]

Check if minimal average speed error was triggered.

### 3.13.3.4 bool DataSpeed::min\_speed\_failure () [inline]

Check if minimal speed error was triggered.

### 3.13.3.5 void DataSpeed::reset (void)

Reset all counters and triggers.

**3.13.3.6 void DataSpeed::set\_base (time\_t *base\_* = DATASPEED\_AVERAGING\_PERIOD)**

Set averaging time period.

**Parameters:**

*base* time period used to average values (default 1 minute).

**3.13.3.7 void DataSpeed::set\_max\_data (unsigned long long int *max* = 0)**

Set amount of data to be transfered. Used in verbose messages.

**Parameters:**

*max* amount of data in bytes.

**3.13.3.8 void DataSpeed::set\_max\_inactivity\_time (time\_t *max\_inactivity\_time*)**

Set inactivity timeout.

**Parameters:**

*max\_inactivity\_time* - if no data is passing for specified amount of time (seconds), error is triggered.

**3.13.3.9 void DataSpeed::set\_min\_average\_speed (unsigned long long int *min\_average\_speed*)**

Set minimal average speed.

**Parameters:**

*min\_average\_speed\_* minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

**3.13.3.10 void DataSpeed::set\_min\_speed (unsigned long long int *min\_speed*, time\_t *min\_speed\_time*)**

Set minimal allowed speed.

**Parameters:**

*min\_speed* minimal allowed speed (Bytes per second). If speed drops and holds below threshold for *min\_speed\_time\_* seconds error is triggered.

*min\_speed\_time*

**3.13.3.11 void DataSpeed::set\_progress\_indicator (show\_progress\_t *func* = NULL)**

Specify which external function will print verbose messages. If not specified internal one is used.

**Parameters:**

*pointer* to function which prints information.

**3.13.3.12 bool DataSpeed::transfer (unsigned long long int *n* = 0)**

Inform object, about amount of data has been transfered. All errors are triggered by this method. To make them work application must call this method periodically even with zero value.

**Parameters:**

*n* amount of data transfered (bytes).

**3.13.3.13 unsigned long long int DataSpeed::transferred\_size (void) [inline]**

Returns amount of data this object knows about.

**3.13.3.14 bool DataSpeed::verbose (void)**

Check if speed information is going to be printed.

**3.13.3.15 void DataSpeed::verbose (const string & *prefix*)**

Print information about current speed and amount of data.

**Parameters:**

*'prefix'* add this string at the beginning of every string.

**3.13.3.16 void DataSpeed::verbose (bool *val*)**

Activate printing information about current time speeds, amount of transfered data.

The documentation for this class was generated from the following file:

- dataspeed.h

# Index

- ~DataBufferPar
  - DataBufferPar, [6](#)
- ~DataCache
  - DataCache, [12](#)
- ~DataHandle
  - DataHandle, [17](#)
- ~DataMove
  - DataMove, [22](#)
- ~DataMovePar
  - DataMovePar, [26](#)
- ~DataSpeed
  - DataSpeed, [54](#)
- accepts\_meta
  - DataPoint, [30](#)
  - DataPointDirect, [40](#)
  - DataPointMeta, [50](#)
- Add
  - DataMovePar, [26](#)
- add\_location
  - DataPoint, [30](#)
  - DataPointDirect, [40](#)
- additional\_checks
  - DataHandle, [17](#)
- AddProtocol
  - DataPoint, [30](#)
- analyze
  - DataHandle, [17](#)
- base\_url
  - DataPoint, [30](#)
  - DataPointDirect, [41](#)
- buffer\_size
  - DataBufferPar, [6](#)
- cache\_error
  - DataMove, [22](#)
- canonic\_url
  - DataPoint, [30](#)
  - DataPointDirect, [41](#)
- cb
  - DataCache, [12](#)
- check
  - DataHandle, [17](#)
- checks
  - DataMove, [23](#)
- checksum
  - DataPoint::FileInfo, [37](#)
- checksum\_available
  - DataPoint::FileInfo, [37](#)
- checksum\_object
  - DataBufferPar, [6](#)
- checksum\_valid
  - DataBufferPar, [7](#)
- clean
  - DataCache, [12](#)
- common\_url\_options
  - DataPointDirect, [47](#)
- copy
  - DataCache, [12](#)
- created
  - DataCache, [12](#), [13](#)
  - DataPoint::FileInfo, [37](#)
- created\_available
  - DataCache, [13](#)
  - DataPoint::FileInfo, [38](#)
- created\_force
  - DataCache, [13](#)
- credentials\_expired\_error
  - DataMove, [22](#)
- current\_location
  - DataPoint, [30](#)
  - DataPointDirect, [41](#)
- current\_meta\_location
  - DataPoint, [30](#)
  - DataPointDirect, [41](#)
- DataBufferPar, [5](#)
  - DataBufferPar, [6](#)
- DataBufferPar
  - ~DataBufferPar, [6](#)
  - buffer\_size, [6](#)
  - checksum\_object, [6](#)
  - checksum\_valid, [7](#)
  - DataBufferPar, [6](#)
  - eof\_position, [7](#)
  - eof\_read, [7](#)
  - eof\_write, [7](#)
  - error, [7](#)
  - error\_read, [7](#)

- error\_transfer, 7
- error\_write, 7, 8
- for\_read, 8
- for\_write, 8
- is\_notwritten, 8
- is\_read, 8, 9
- is\_written, 9
- operator bool, 9
- operator[], 9
- set, 9
- speed, 10
- wait, 10
- wait\_eof, 10
- wait\_eof\_read, 10
- wait\_eof\_write, 10
- wait\_read, 10
- wait\_used, 10
- wait\_write, 10
- DataCache, 11
  - DataCache, 12
- DataCache
  - ~DataCache, 12
  - cb, 12
  - clean, 12
  - copy, 12
  - created, 12, 13
  - created\_available, 13
  - created\_force, 13
  - DataCache, 12
  - file, 13
  - link, 13
  - operator bool, 13
  - start, 13
  - stop, 14
  - validtill, 14
  - validtill\_available, 14
  - validtill\_force, 14
- DataCallback, 15
- DataHandle, 16
  - DataHandle, 17
- DataHandle
  - ~DataHandle, 17
  - additional\_checks, 17
  - analyze, 17
  - check, 17
  - DataHandle, 17
  - failure\_reason, 17
  - failure\_reason\_t, 16
  - list\_files, 17
  - out\_of\_order, 18
  - passive, 18
  - range, 18
  - remove, 18
  - secure, 18
  - start\_reading, 18
  - start\_writing, 19
  - stop\_reading, 19
  - stop\_writing, 19
- DataHandle::analyze\_t, 20
- DataMove, 21
  - cache\_error, 22
  - credentials\_expired\_error, 22
  - DataMove, 22
  - postregister\_error, 22
  - preregister\_error, 22
  - read\_acquire\_error, 22
  - read\_error, 22
  - read\_resolve\_error, 22
  - read\_start\_error, 22
  - read\_stop\_error, 22
  - success, 22
  - system\_error, 22
  - transfer\_error, 22
  - undefined\_error, 22
  - write\_acquire\_error, 22
  - write\_error, 22
  - write\_resolve\_error, 22
  - write\_start\_error, 22
  - write\_stop\_error, 22
- DataMove
  - ~DataMove, 22
  - checks, 23
  - DataMove, 22
  - force\_to\_meta, 23
  - passive, 23
  - result, 22
  - retry, 23
  - secure, 23
  - set\_default\_max\_inactivity\_time, 23
  - set\_default\_min\_average\_speed, 23
  - set\_default\_min\_speed, 23
  - Transfer, 24
  - verbose, 24
- DataMovePar, 26
  - DataMovePar, 26
- DataMovePar
  - ~DataMovePar, 26
  - Add, 26
  - DataMovePar, 26
  - Get, 26
  - Transfer, 27
- DataPoint, 28
  - DataPoint, 29
- DataPoint
  - accepts\_meta, 30
  - add\_location, 30
  - AddProtocol, 30
  - base\_url, 30

- canonic\_url, 30
- current\_location, 30
- current\_meta\_location, 30
- DataPoint, 29
  - get\_info, 30
  - have\_location, 31
  - have\_locations, 31
  - lfn, 31
  - list\_files, 31
  - local, 31
  - map, 31
  - meta, 31, 32
  - meta\_checksum, 32
  - meta\_checksum\_available, 32
  - meta\_checksum\_force, 32
  - meta\_compare, 32
  - meta\_created, 32
  - meta\_created\_available, 33
  - meta\_created\_force, 33
  - meta\_postregister, 33
  - meta\_preregister, 33
  - meta\_preunregister, 33
  - meta\_resolve, 33, 34
  - meta\_size, 34
  - meta\_size\_available, 34
  - meta\_size\_force, 34
  - meta\_stored, 34
  - meta\_unregister, 34
  - meta\_validtill, 35
  - meta\_validtill\_available, 35
  - meta\_validtill\_force, 35
  - next\_location, 35
  - provides\_meta, 35
  - remove\_location, 35
  - remove\_locations, 35
  - sort, 36
  - tries, 36
- DataPoint::FileInfo, 37
- DataPoint::FileInfo
  - checksum, 37
  - checksum\_available, 37
  - created, 37
  - created\_available, 38
  - FileInfo, 37
  - size, 38
  - size\_available, 38
  - type, 38
  - valid, 38
  - valid\_available, 38
- DataPointDirect, 39
- DataPointDirect
  - accepts\_meta, 40
  - add\_location, 40
  - base\_url, 41
  - canonic\_url, 41
  - common\_url\_options, 47
  - current\_location, 41
  - current\_meta\_location, 41
  - get\_info, 41
  - have\_location, 41
  - have\_locations, 41
  - list\_files, 42
  - local, 42
  - location, 47
  - map, 42
  - meta, 42
  - meta\_checksum, 42, 43
  - meta\_checksum\_available, 43
  - meta\_checksum\_force, 43
  - meta\_compare, 43
  - meta\_created, 43
  - meta\_created\_available, 43
  - meta\_created\_force, 43
  - meta\_postregister, 44
  - meta\_preregister, 44
  - meta\_preunregister, 44
  - meta\_resolve, 44, 45
  - meta\_size, 45
  - meta\_size\_, 47
  - meta\_size\_available, 45
  - meta\_size\_force, 45
  - meta\_stored, 45
  - meta\_unregister, 45
  - meta\_validtill, 46
  - meta\_validtill\_available, 46
  - meta\_validtill\_force, 46
  - next\_location, 46
  - provides\_meta, 46
  - remove\_location, 46
  - remove\_locations, 47
  - sort, 47
  - tries, 47
- DataPointDirect::Location, 48
- DataPointMeta, 49
- DataPointMeta
  - accepts\_meta, 50
  - get\_info, 50
  - lfn, 50
  - meta, 50
  - meta\_postregister, 50
  - meta\_preregister, 50
  - meta\_preunregister, 51
  - meta\_resolve, 51
  - meta\_stored, 51
  - meta\_unregister, 51
  - provides\_meta, 51
- DataSpeed, 53
- DataSpeed, 53

- DataSpeed
  - ~DataSpeed, 54
  - DataSpeed, 53
  - hold, 54
  - max\_inactivity\_time\_failure, 54
  - min\_average\_speed\_failure, 54
  - min\_speed\_failure, 54
  - reset, 54
  - set\_base, 54
  - set\_max\_data, 55
  - set\_max\_inactivity\_time, 55
  - set\_min\_average\_speed, 55
  - set\_min\_speed, 55
  - set\_progress\_indicator, 55
  - transfer, 55
  - transferred\_size, 56
  - verbose, 56
- eof\_position
  - DataBufferPar, 7
- eof\_read
  - DataBufferPar, 7
- eof\_write
  - DataBufferPar, 7
- error
  - DataBufferPar, 7
- error\_read
  - DataBufferPar, 7
- error\_transfer
  - DataBufferPar, 7
- error\_write
  - DataBufferPar, 7, 8
- failure\_reason
  - DataHandle, 17
- failure\_reason\_t
  - DataHandle, 16
- file
  - DataCache, 13
- FileInfo
  - DataPoint::FileInfo, 37
- for\_read
  - DataBufferPar, 8
- for\_write
  - DataBufferPar, 8
- force\_to\_meta
  - DataMove, 23
- Get
  - DataMovePar, 26
- get\_info
  - DataPoint, 30
  - DataPointDirect, 41
  - DataPointMeta, 50
- have\_location
  - DataPoint, 31
  - DataPointDirect, 41
- have\_locations
  - DataPoint, 31
  - DataPointDirect, 41
- hold
  - DataSpeed, 54
- is\_notwritten
  - DataBufferPar, 8
- is\_read
  - DataBufferPar, 8, 9
- is\_written
  - DataBufferPar, 9
- lfn
  - DataPoint, 31
  - DataPointMeta, 50
- link
  - DataCache, 13
- list\_files
  - DataHandle, 17
  - DataPoint, 31
  - DataPointDirect, 42
- local
  - DataPoint, 31
  - DataPointDirect, 42
- location
  - DataPointDirect, 47
- map
  - DataPoint, 31
  - DataPointDirect, 42
- max\_inactivity\_time\_failure
  - DataSpeed, 54
- meta
  - DataPoint, 31, 32
  - DataPointDirect, 42
  - DataPointMeta, 50
- meta\_checksum
  - DataPoint, 32
  - DataPointDirect, 42, 43
- meta\_checksum\_available
  - DataPoint, 32
  - DataPointDirect, 43
- meta\_checksum\_force
  - DataPoint, 32
  - DataPointDirect, 43
- meta\_compare
  - DataPoint, 32
  - DataPointDirect, 43
- meta\_created
  - DataPoint, 32



- DataPointDirect, 43
- meta\_created\_available
  - DataPoint, 33
  - DataPointDirect, 43
- meta\_created\_force
  - DataPoint, 33
  - DataPointDirect, 43
- meta\_postregister
  - DataPoint, 33
  - DataPointDirect, 44
  - DataPointMeta, 50
- meta\_preregister
  - DataPoint, 33
  - DataPointDirect, 44
  - DataPointMeta, 50
- meta\_preunregister
  - DataPoint, 33
  - DataPointDirect, 44
  - DataPointMeta, 51
- meta\_resolve
  - DataPoint, 33, 34
  - DataPointDirect, 44, 45
  - DataPointMeta, 51
- meta\_size
  - DataPoint, 34
  - DataPointDirect, 45
- meta\_size\_
  - DataPointDirect, 47
- meta\_size\_available
  - DataPoint, 34
  - DataPointDirect, 45
- meta\_size\_force
  - DataPoint, 34
  - DataPointDirect, 45
- meta\_stored
  - DataPoint, 34
  - DataPointDirect, 45
  - DataPointMeta, 51
- meta\_unregister
  - DataPoint, 34
  - DataPointDirect, 45
  - DataPointMeta, 51
- meta\_validtill
  - DataPoint, 35
  - DataPointDirect, 46
- meta\_validtill\_available
  - DataPoint, 35
  - DataPointDirect, 46
- meta\_validtill\_force
  - DataPoint, 35
  - DataPointDirect, 46
- min\_average\_speed\_failure
  - DataSpeed, 54
- min\_speed\_failure
  - DataSpeed, 54
- next\_location
  - DataPoint, 35
  - DataPointDirect, 46
- operator bool
  - DataBufferPar, 9
  - DataCache, 13
- operator[]
  - DataBufferPar, 9
- out\_of\_order
  - DataHandle, 18
- passive
  - DataHandle, 18
  - DataMove, 23
- postregister\_error
  - DataMove, 22
- preregister\_error
  - DataMove, 22
- provides\_meta
  - DataPoint, 35
  - DataPointDirect, 46
  - DataPointMeta, 51
- range
  - DataHandle, 18
- read\_acquire\_error
  - DataMove, 22
- read\_error
  - DataMove, 22
- read\_resolve\_error
  - DataMove, 22
- read\_start\_error
  - DataMove, 22
- read\_stop\_error
  - DataMove, 22
- remove
  - DataHandle, 18
- remove\_location
  - DataPoint, 35
  - DataPointDirect, 46
- remove\_locations
  - DataPoint, 35
  - DataPointDirect, 47
- reset
  - DataSpeed, 54
- result
  - DataMove, 22
- retry
  - DataMove, 23
- secure
  - DataHandle, 18

- DataMove, 23
- set
  - DataBufferPar, 9
- set\_base
  - DataSpeed, 54
- set\_default\_max\_inactivity\_time
  - DataMove, 23
- set\_default\_min\_average\_speed
  - DataMove, 23
- set\_default\_min\_speed
  - DataMove, 23
- set\_max\_data
  - DataSpeed, 55
- set\_max\_inactivity\_time
  - DataSpeed, 55
- set\_min\_average\_speed
  - DataSpeed, 55
- set\_min\_speed
  - DataSpeed, 55
- set\_progress\_indicator
  - DataSpeed, 55
- size
  - DataPoint::FileInfo, 38
- size\_available
  - DataPoint::FileInfo, 38
- sort
  - DataPoint, 36
  - DataPointDirect, 47
- speed
  - DataBufferPar, 10
- start
  - DataCache, 13
- start\_reading
  - DataHandle, 18
- start\_writing
  - DataHandle, 19
- stop
  - DataCache, 14
- stop\_reading
  - DataHandle, 19
- stop\_writing
  - DataHandle, 19
- success
  - DataMove, 22
- system\_error
  - DataMove, 22
- Transfer
  - DataMove, 24
  - DataMovePar, 27
- transfer
  - DataSpeed, 55
- transfer\_error
  - DataMove, 22
- transferred\_size
  - DataSpeed, 56
- tries
  - DataPoint, 36
  - DataPointDirect, 47
- type
  - DataPoint::FileInfo, 38
- undefined\_error
  - DataMove, 22
- valid
  - DataPoint::FileInfo, 38
- valid\_available
  - DataPoint::FileInfo, 38
- validtill
  - DataCache, 14
- validtill\_available
  - DataCache, 14
- validtill\_force
  - DataCache, 14
- verbose
  - DataMove, 24
  - DataSpeed, 56
- wait
  - DataBufferPar, 10
- wait\_eof
  - DataBufferPar, 10
- wait\_eof\_read
  - DataBufferPar, 10
- wait\_eof\_write
  - DataBufferPar, 10
- wait\_read
  - DataBufferPar, 10
- wait\_used
  - DataBufferPar, 10
- wait\_write
  - DataBufferPar, 10
- write\_acquire\_error
  - DataMove, 22
- write\_error
  - DataMove, 22
- write\_resolve\_error
  - DataMove, 22
- write\_start\_error
  - DataMove, 22
- write\_stop\_error
  - DataMove, 22